Realtime and Embedded Specification for Java

Version 2.0

Draft 20 Roanoke Edition 17th of August 2015

Editor
James J. Hunt
aicas GmbH
Haid-und-Neu-Straße 18
D-76131 Karlsruhe, Germany

Copyright © 1999–2012 TimeSys Copyright © 2012–2015 aicas GmbH All rights reserved The Realtime Specification for Java (RTSJ) is under development within the Java Community Process (JCP) by the members of the JSR-282 Expert Group (EG). This group, was lead by TimeSys Inc. Corporation, but has been taken over by aicas GmbH.

JSR-282 Expert Group Membership

James J. Hunt aicas GmbH Benjamin Brosgol Andy Wellings Kelvin Nilsen Ethan Blanton

Past Expert Group Members

Peter Dibble TimeSys David Holmes Oracle

Table of Contents

Contents		i
List of Fi	igures	xii
List of Ta	ables	xiii
	luction	1
1.1 Gu	uiding Principles	
1.1.1	Applicability to Particular Java Environments	
1.1.2	Backward Compatibility	
1.1.3	Write Once, Run Anywhere	. 3
1.1.4	Current Practice vs. Advanced Features	. 3
1.1.5	Predictable Execution	. 3
1.1.6	No Syntactic Extension	. 3
1.1.7	Allow Variation in Implementation Decisions	. 3
1.1.8	Interoperability	. 4
1.2 Are	eas of Enhancement	. 4
1.2.1	Thread Scheduling and Dispatching	. 4
1.2.2	Memory Management	. 5
1.2.3	Synchronization and Resource Sharing	. 5
1.2.4	Asynchronous Event Handling	. 5
1.2.5	Task Interruption	. 5
1.2.6	Raw Memory Access	. 6
1.2.7	Physical Memory Access	
1.2.8	Modularization	. 6
2 Overv	iew	7
2.1 Th	reads and Scheduling	. 7
2.2 Syr	$\begin{array}{cccccccccccccccccccccccccccccccccccc$. 9
2.2.1	Priority Inversion	
2.2.2	Priority Inversion Avoidance	
2.2.3	Execution Eligibility	

2.2.4 Wait-Free Queues	11
2.3 Asynchrony	11
2.3.1 Asynchronous Events	12
σ	13
2.3.3 Principles	13
2.3.3.1 Methodological Principles	14
2.3.3.2 Expressibility Principles	14
2.3.3.3 Semantic Principles	14
2.3.3.4 Pragmatic Principles	15
2.3.4 Asynchronous Realtime Thread Termination	15
2.4 Clocks, Time, and Timers	16
v o	16
v	16
1 3	17
v – – – – – – – – – – – – – – – – – – –	17
1	17
y y	18
	18
V	19
v	19
y 1	19
1	20
2.9 Summary	20
	21
1	21
	22
	22
	24
V	25
•	26
1	27
v 1	28
1	28
1	29
	30
3.6 Definitions	30
4 Conventional Java Classes and Language	33
4.1 Scheduling	33
4.1.1 Priority	34
v	

4.1.1.1 Setting Priority	34
4.1.1.2 Getting Priority	35
4.1.2 Thread Groups	35
4.1.3 Current Thread	36
4.2 Java Memory Model	36
4.3 InterruptedException	37
4.4 Memory Management	37
4.4.1 Memory Areas	
4.4.2 Garbage Collection	38
4.4.3 Realtime Garbage Collections	38
4.4.3.1 Thread-Based Collectors	38
4.4.3.2 Allocation-Based Collectors	38
4.4.3.3 Alternatives to Garbage Collection	
4.4.3.4 Developer Implementation	39
4.5 Summary	
5 Realtime Threads	41
5.1 Overview	
5.2 Semantics	
5.3 Package javax.realtime	
5.3.1 Enumerations	
5.3.1.1 PhasingPolicy	
5.3.2 Classes	
5.3.2.1 ConfigurationParameters	
5.3.2.2 RealtimeThread	
5.4 Rationale	
0.4 Italionale	' '
6 Scheduling	7 9
6.1 Overview	
6.2 Definitions	
6.3 Semantics	83
6.3.1 Schedulers	83
6.3.2 The Base Scheduler	84
6.3.2.1 Priorities	84
6.3.2.2 Dispatching	85
6.3.2.3 Parameter Values	87
6.3.2.4 Cost Monitoring and Cost Enforcement	89
6.3.2.5 Release of a Realtime Thread	91
6.3.2.6 Aperiodic Release Control	98
6.3.2.7 Sporadic Release Control	99
6.3.2.8 Release Control for Asynchronous Event Handlers	101

6.3.3 The	Round-Robin Scheduler	2
6.3.3.1	Priorities	3
6.3.4 Mar	naging Groups of Schedulables	3
6.3.4.1	Scheduling Groups	4
6.3.4.2	Processing Groups	4
6.4 Package	javax.realtime	7
6.4.1 Inte	rfaces	7
6.4.1.1	RealtimeExecutionContext	7
6.4.1.2	Schedulable	7
6.4.2 Clas	sses	7
6.4.2.1	Affinity	7
6.4.2.2	AperiodicParameters	6
6.4.2.3	FirstInFirstOutScheduler	4
6.4.2.4	ImportanceParameters	7
6.4.2.5	PeriodicParameters	9
6.4.2.6	PriorityParameters	6
6.4.2.7	PriorityScheduler	8
6.4.2.8	ProcessingGroup	1
6.4.2.9	ReleaseParameters	8
6.4.2.10	RoundRobinScheduler	5
6.4.2.11	Scheduler	9
6.4.2.12	SchedulingGroup	2
6.4.2.13	SchedulingParameters	5
6.4.2.14	SporadicParameters	
6.5 Rational	e	3
6.5.1 Mul	tiprocessor Support	4
	act of Clock Granularity	
6.5.3 Dea	dline Miss Detection	5
_ ~		_
7 Synchroniz		
	v	
	ns	
	es	
	nitor Control	
	ority Schedulers	
	litional Schedulers	
	javax.realtime	
	sses	
7.4.1.1	MonitorControl	
7.4.1.2	PriorityCeilingEmulation	
7.4.1.3	PriorityInheritance	8

7.4.1.4	WaitFreeDequeue	99
7.4.1.5	WaitFreeReadQueue	99
7.4.1.6	WaitFreeWriteQueue	
7.5 Rationa	$_{ m ale}$	213
8 Asynchron	ny 2	15
8.1 Overvie	ew	215
8.2 Definiti	ions	217
8.3 Semant	iics	218
8.3.1 As	ynchronous Events and their Handlers	218
8.3.2 Ac	etive Events and Dispatching	220
8.3.3 As	ynchronous Transfer of Control	222
8.3.3.1	Summary of ATC Operation	224
8.4 Package	e javax.realtime	226
8.4.1 Int	terfaces	226
8.4.1.1	ActiveEvent	226
8.4.1.2	AsyncTimable	228
8.4.1.3	BoundAbstractAsyncEventHandler	
8.4.1.4	Interruptible	229
8.4.1.5	Releasable	230
	$ m cceptions \dots \dots$	
8.4.2.1	AsynchronouslyInterruptedException	
8.4.2.2	Timed	
	asses	
8.4.3.1	AbstractAsyncEvent	
8.4.3.2	AbstractAsyncEventHandler	
8.4.3.3	ActiveEventDispatcher	
8.4.3.4	AsyncEvent	
8.4.3.5	AsyncEventHandler	
8.4.3.6	AsyncLongEvent	
8.4.3.7	AsyncLongEventHandler	
8.4.3.8	AsyncObjectEvent	
8.4.3.9	AsyncObjectEventHandler	
8.4.3.10	BoundAsyncEventHandler	
8.4.3.11	BoundAsyncLongEventHandler	
8.4.3.12	BoundAsyncObjectEventHandler	
8.5 Rationa	ale	284
9 Time		87
		287
0.2 Definiti	ions	227

9.3 Ser	$\mathrm{mantics}$			_	 288
	ckage javax.realtime				
9.4.1	Classes				
0.1.1	1.1 AbsoluteTime				
9.4.1					
9.4.1					
	s and Timers				325
	verview				
	finitions				
	mantics				
10.3.1	Clock Model				
10.3.2					
10.3.3					
10.3					
10.3	1				
10.3	88 8				
10.3					
10.3	0				
	ckage javax.realtime				
10.4.1	Interfaces				
10.4					
10.4	1.2 Chronograph				 . 335
10.4					
10.4.2	Classes				 . 339
10.4					
10.4					
10.4	.2.3 PeriodicTimer				 . 347
10.4	.2.4 TimeDispatcher $$				 356
10.4	.2.5 Timer				 . 358
10.5 Ra	tionale				 . 379
11 Alteri	native Memory Areas				381
	verview		_	_	
11.1.1	Physical Memory				
11.1.2	Stacked Memory				
11.1.3	Summary				
	finitions				
	mantics				
	Allocation time				

11.3.2	The allocation context $\dots \dots \dots \dots \dots 388$
11.3.3	Гhe Parent Scope
11.3.4	Memory areas and schedulables
11.3.5	Scoped memory reference counting
11.3.6	mmortal memory
11.3.7	Maintaining referential integrity
11.3.8	Object initialization
11.3.9	Maintaining the Scope Stack
	The enter method
11.3.11	The executeInArea or newInstance $methods$
11.3.12	Constructor methods for Schedulables
11.3.13	The Single Parent Rule
11.3.14	Scope Tree Maintenance
11.3.14	.1 On Scope Stack Push of ma
11.3.14	.2 On Scope Stack Pop of ma
11.4 Packa	nge javax.realtime
11.4.1	interfaces
11.4.1.	
11.4.2	Classes
11.4.2.	$1 \text{HeapMemory} \dots \dots 399$
11.4.2.2	
11.4.2.3	3 MemoryArea
11.4.2.4	4 MemoryParameters
11.4.2.	1 0
11.4.2.0	SizeEstimator
	age javax.realtime.memory
11.5.1	nterfaces
11.5.1.	\mathbf{v}
	2 VirtualMemoryCharacteristic
	Enumerations
11.5.2.	PhysicalMemorySelector.CachingBehavior 453
11.5.2.2	v v
11.5.3	Classes
11.5.3.	V
11.5.3.2	PhysicalMemoryFactory
11.5.3.3	v e
11.5.3.4	v
11.5.3.	· · · · · · · · · · · · · · · · · · ·
11.5.3.0	StackedMemory
11.6 The l	Rationale

11.6.1 The	scoped memory model
	physical memory model
11.6.2.1	Problems with the current RTSJ 1.0.2 Physical Memory Frame-
	work
11.6.2.2	The RTSJ 2.0 Physical Memory Framework 493
11.6.2.3	An example
12 Devices and	d Triggering 497
	v
	ns
	es
	Memory
12.3.1.1	Raw Memory Region
12.3.1.2	Raw Memory Factory
12.3.1.3	
12.3.2 Dire	ect Memory Access Support
	ernal Triggering
12.3.3.1	Happenings
12.3.4 Inte	rrupt Service Routines
	javax.realtime.device
	rfaces
12.4.1.1	RawByte
12.4.1.2	RawByteReader
12.4.1.3	RawByteWriter
12.4.1.4	RawDouble
12.4.1.5	RawDoubleReader
12.4.1.6	RawDoubleWriter
12.4.1.7	RawFloat
12.4.1.8	RawFloatReader
12.4.1.9	RawFloatWriter
12.4.1.10	RawInt
12.4.1.11	RawIntReader
12.4.1.12	RawIntWriter
12.4.1.13	RawLong
12.4.1.14	RawLongReader
12.4.1.15	RawLongWriter
12.4.1.16	RawMemory
12.4.1.17	RawMemoryRegionFactory
12.4.1.18	RawShort
12.4.1.19	RawShortReader
12.4.1.20	RawShortWriter

12.4.2 Exc	m eptions
12.4.2.1	UnsupportedRawMemoryRegionException
12.4.3 Cla	sses
12.4.3.1	Happening
12.4.3.2	HappeningDispatcher
12.4.3.3	InterruptServiceRoutine
12.4.3.4	RawBufferFactory
12.4.3.5	RawMemoryFactory
12.4.3.6	RawMemoryRegion
12.5 Rational	le
12.5.1 Ray	v Memory
12.5.1.1	Direct memory access
12.5.2 Inte	errupt Handling
12.5.3 An	Illustrative Example
12.5.3.1	Software architecture
12.5.3.2	Device initialization
12.5.3.3	Responding to external happenings 615
12.5.3.4	Access to the flash controller's device registers 615
100 1	1.0.4
13 System and	
	N
13.2.0.5	CS
13.2.0.6	RealtimeSystem
13.2.0.0 $13.2.0.7$	RealtimeSecurity
13.2.0.8	0
	POSIX Realtime Signals
	sses
13.3.1.1	GarbageCollector
13.3.1.2	POSIXRealtimeSignal
13.3.1.3	· · · · · · · · · · · · · · · · · · ·
13.3.1.4	POSIXRealtimeSignalDispatcher
13.3.1.5	POSIXSignalDispatcher
13.3.1.6	RealtimeSecurity
13.3.1.7	RealtimeSystem
	le
19.4 1(2010112)	
14 Exceptions	649
	v
	nantics

14.2.1 Inte	erfaces
14.2.1.1	PreallocatedThrowable
14.2.2 Exc	eptions
14.2.2.1	ArrivalTimeQueueOverflowException
14.2.2.2	CeilingViolationException
14.2.2.3	DeregistrationException
14.2.2.4	InaccessibleAreaException
14.2.2.5	LateStartException
14.2.2.6	MITViolationException
14.2.2.7	MemoryInUseException
14.2.2.8	MemoryScopeException
14.2.2.9	MemoryTypeConflictException
14.2.2.10	OffsetOutOfBoundsException
14.2.2.11	ProcessorAffinityException
14.2.2.12	RegistrationException
14.2.2.13	ScopedCycleException
14.2.2.14	SizeOutOfBoundsException
14.2.2.15	UnknownHappeningException 671
14.2.2.16	UnsupportedPhysicalMemoryException 672
14.2.3 Clas	sses
14.2.3.1	AlignmentError
14.2.3.2	BacktraceManagement
14.2.3.3	IllegalAssignmentError
14.2.3.4	MemoryAccessError
14.2.3.5	ResourceLimitError
14.2.3.6	ThrowBoundaryError
14.2.4 Rat	ionale
15 Deprecated	
	v
	cs
	javax.realtime
15.3.1 Inte	erfaces
15.3.1.1	PhysicalMemoryTypeFilter
	eptions
15.3.2.1	DuplicateFilterException
15.3.2.2	UnknownHappeningException 691
	sses
15.3.3.1	ImmortalPhysicalMemory
15.3.3.2	LTPhysicalMemory
15.3.3.3	NoHeapRealtimeThread

15.3.3.4	POSIXSignalHandler	. 715
15.3.3.5	PhysicalMemoryManager	. 724
15.3.3.6	ProcessingGroupParameters	
15.3.3.7	RationalTime	
15.3.3.8	RawMemoryAccess	. 742
15.3.3.9	RawMemoryFloatAccess	
15.3.3.10	VTMemory	
15.3.3.11	VTPhysicalMemory	
15.3.3.12	WaitFreeDequeue	
15.4 Rational	le	
16 Conforman	nce, Compliance, and Portability	795
16.1 Minimu	m Implementations	. 795
	· · · · · · · · · · · · · · · · · · ·	
	lly Required Components	
	ployment Implementation	
	on Implementation	
	ntation Requirements	
A Bibliograp	hy	7 99

List of Figures

Sequence Diagram of Some Example Realtime Thread Releases 96
A State Chart for a Realtime Thread without a Deadline Miss Handler 97
A State Chart for a Realtime Thread with a Deadline Miss Handler $$. 98
The Event Class Hierarchy
States of a Simple AbstractAsyncEvent
States of an ActiveEvent
Sequence Diagram for Using a Timer
Sequence Diagram for Realtime Sleep
States of a Timer
Manipulation of StackedMemory Areas
Raw Memory Interface
Event Classes
Happening State Transition Diagram
Interrupt servicing
Creating Raw Memory Accessors
Flash memory device
Flash memory classes
Sequence diagram showing initialization operations 614
Sequence diagrams showing operations to initialize the hardware device 615
The FMSocketController.handleAsync method
Application usage

List of Tables

3.1	RTSJ Options	26
5.1	Effect of PhasingPolicy on the First Release of a RealtimeThread with	
	PeriodicParameters	45
12.1	Device registers	613

 $ext{xiv}$ $ext{LIST OF TABLES}$

Chapter 1

Introduction

The goal of the Real-Time Specification for Java (RTSJ) is to support the use of Java technology in embedded and realtime systems. It provides a specification for refining the Java Language Specification and the Java Virtual Machine Specification and of providing an extended Application Programming Interface that facilitates the creation, verification, analysis, execution, and management of realtime Java programs such as control and sensor applications.

The Java Virtual Machine and the Java Language were conceived as a portable environment for desktop and server applications. The emphasis has been on throughput and responsiveness. These are characteristics obtainable with time-sharing systems. For this conventional Java environment, it is more important that each task makes progress, than that a particular task completes within a predefined time slot.

In a realtime system, the system tries to schedule the most critical task that is ready to run first. This task runs either until it is finished, or it needs to wait for some event or data, or a more critical task is released or a more critical task becomes schedulable after waiting for its event or data.

Realtime scheduling is commonly done with a priority preemptive scheduler, where tasks that have short deadlines are given higher priority than tasks that have longer deadlines. The programmer is responsible for encoding some notion of task importance to priorities. The goal is to see that all tasks finish within their deadlines. Scheduling analysis, such as Rate Monotonic Analysis, can be used to help determine this.

Many realtime systems have nonrealtime components, so it is desirable to be able to combine realtime and nonrealtime tasks in a single system. Realtime tasks are then given preference over nonrealtime tasks. For Java, this means that realtime tasks must be scheduled before threads with conventional Java priorities (1–10). Being able to synchronize between tasks, both realtime and conventional Java threads, adds additional requirements.

Providing realtime semantics and the additional programming interfaces required

is a core part of this specification. So much so that the original specification provided special memory areas to avoid the use of garbage collection. The availability of various techniques for realtime garbage collection has changed the state of practice since RTSJ Version 1.0. Though still part of the specification, these special memory areas are no longer central to it. Realtime scheduling and priority inversion avoidance for synchronization are the core of providing realtime response. These are provided through refinements to the base Java semantics and additional classes.

Realtime tasks can be modeled both with realtime threads and with event handlers. Realtime threads are much the same as conventional Java threads except for how they are scheduled. Event handlers encapsulate a bit of work that is done every time some event occurs. Events are referred to as asynchronous because they generally occur independent of program flow. Thus, a timed event is considered to be an asynchronous event, but scheduled periodically. Event handling provides a less resource intensive means of writing control applications because the underlying thread mechanism can be shared between event handlers. Deadline analysis is also somewhat simpler because the end of the work to be done is well bounded. Event handling is ideal for periodic tasks and responding to external impulses. The specification provides both paradigms.

Though realtime is necessary for many control tasks, it is not sufficient. A significant part of the RTSJ API addresses communication with the outside world through devices and signals. This makes it possible to write control applications without resorting to JNI, thereby maintaining the integrity and safety that Java offers.

Since not all applications need all aspects of the specification, there are now modules to suite the major application scenarios. This should make it easier for conventional JVM providers to include basic specification facilities without negatively impacting their core application domains, but still be compatible with hard realtime implementations. The goal is to make the transition between conventional JVMs and realtime JVMs easier.

1.1 Guiding Principles

Providing a coherent semantics and set of programming interfaces requires some guiding principles around which to organize the RTSJ. These principles delimit the scope of the RTSJ and its compatibility requirements with conventional Java.

1.1.1 Applicability to Particular Java Environments

The RTSJ shall not include specifications that restrict its use to a particular Java environment, such as a particular versions of the Java Development Kit, an Embedded

1 Introduction 3

Java Application Environment, or a Java Edition, beyond the natural development of the Java language.

1.1.2 Backward Compatibility

The RTSJ shall not prevent existing, properly written, conventional Java programs from executing on implementations of the RTSJ.

1.1.3 Write Once, Run Anywhere

The RTSJ should recognize the importance of "Write Once, Run Anywhere", but it should also recognize the difficulty of achieving WORA for realtime programs and not attempt to increase or maintain binary portability at the expense of predictability. Hence, the goal should be "Write Once Carefully, Run Anywhere Conditionally".

1.1.4 Current Practice vs. Advanced Features

The RTSJ should address current realtime system practice as well as allow future implementations to include advanced features.

1.1.5 Predictable Execution

The RTSJ shall hold predictable execution as first priority in all trade-offs; this may sometimes be at the expense of typical general-purpose computing performance measures.

1.1.6 No Syntactic Extension

In order to facilitate the job of tool developers, and thus to increase the likelihood of timely implementations, the RTSJ shall not introduce new keywords or make other syntactic extensions to the Java language.

1.1.7 Allow Variation in Implementation Decisions

Implementations of the RTSJ may vary in a number of implementation decisions, such as the use of efficient or inefficient algorithms, trade-offs between time and space efficiency, inclusion of scheduling algorithms not required in the minimum implementation, and variation in code path length for the execution of byte codes. The RTSJ should not mandate algorithms or specific time constants for such, but require that the semantics of the implementation be met and where necessary put

limits on execution time complexity. The RTSJ offers implementers the flexibility to create implementations suited to meet the requirements of their customers.

1.1.8 Interoperability

It should be possible to implement all aspects of the RTSJ on a conventional JVM with the exception that realtime response and pointer assignment rules would not necessarily be guaranteed. This should ease the transition between conventional and realtime programming and aid functional testing on a conventional JVM. The API should support modules for this as well.

1.2 Areas of Enhancement

Each guiding principle has had a direct effect on the development of the specification. There are eight aspects of these refinements and additions in the specification. Their enumeration should aid the understanding of the rest of the specification.

1.2.1 Thread Scheduling and Dispatching

Portability dictates the specification of at least one standard realtime scheduler, but in light of the significant diversity in scheduling and dispatching models and the recognition that each model has wide applicability in the diverse realtime systems industry, the specification provides an underlying scheduling infrastructure that can be extended to use other scheduling algorithms for scheduling realtime Java threads and event handlers.

To accommodate current practice, the RTSJ shall require a base scheduler in all implementations. The required base scheduler will be familiar to realtime system programmers. It is a priority preemptive scheduler with priorities above the conventional Java priorities (1–10).

The specification is constructed to allow implementations to provide unanticipated scheduling algorithms. Implementations will enable the programmatic assignment of parameters appropriate for the underlying scheduling mechanism as well as provide any necessary methods for the creation, management and termination of realtime Java threads. In the current specification, any other thread, scheduling, and dispatching mechanism may be bound to an implementation; however, there should be enough flexibility in the thread scheduling framework to enable future versions of the specification to build on this release.

1 Introduction 5

1.2.2 Memory Management

Automatic memory management is a particularly important feature of the Java programming environment. The specification enables, as far as possible, the job of memory management to be implemented automatically by the underlying system and not intrude on the programming task. Many automatic memory management algorithms, also known as garbage collection (GC), exist, and many of those apply to certain classes of realtime programming styles and systems. In an attempt to accommodate a diverse set of GC algorithms, the specification defines a memory allocation and reclamation paradigm that

- is independent of any particular GC algorithm,
- requires the VM to precisely characterize its GC algorithm's effect on the preemption of realtime Java tasks, and
- enables the allocation and reclamation of objects outside of any interference by any GC algorithm.

1.2.3 Synchronization and Resource Sharing

Logic often requires serial access to resources, and realtime systems introduce an additional complexity: the need to minimize priority inversion and hence the excessive delay of more critical tasks. The least intrusive specification for enabling realtime safe synchronization is to require that implementations of the Java keyword synchronized implement one or more algorithms that prevent priority inversion among realtime Java tasks that share the serialized resource. In addition, the specification provides other data passing mechanisms to minimize the need for synchronization.

1.2.4 Asynchronous Event Handling

Realtime systems typically interact closely with the real world. With respect to the execution of logic, the real world is asynchronous; therefore, the specification includes efficient mechanisms for programming disciplines that would accommodate this inherent asynchrony. The RTSJ has a general mechanism for asynchronous event handling. This specification provides classes that represent things that can happen and logic that executes when those things happen. The execution of the logic is scheduled and dispatched by the RTSJ runtime.

1.2.5 Task Interruption

Sometimes, the real world changes so drastically (and asynchronously) that the current point of logic execution should be immediately, efficiently, and safely ended and control transferred to another point of execution. The RTSJ provides a mechanism

which extends Java's interrupt and exception handling mechanisms to enable applications to programmatically change the locus of control of another Java task. This mechanism may restrict this asynchronous transfer of control to logic specifically written with the assumption that its locus of control may asynchronously change. Due to the inherent susceptibility to deadlock, the Thread.stop method cannot be used for this.

1.2.6 Raw Memory Access

Accessing device memory is not in and of itself a realtime issue, many realtime systems require it for providing realtime control of a system. This requires an API providing programmers with byte-level access to physical device registers, whether in main memory or in some I/O space. This API must be as efficient as possible, since such access is often under tight time constraints.

1.2.7 Physical Memory Access

Some systems provide memory areas that differ in important aspects, such as time to read or write data and its persistence. Being able to take advantage of these areas can have an impact on performance. This specification enables their efficient use.

1.2.8 Modularization

Not all applications require all aspects of the specification. In fact, having a core set of the APIs presented is useful for conventional Java programming and aids overall interoperability. To this end, the specification provides a core set of APIs and a few optional modules as well as semantics for use in conventional JVMs that do not offer realtime guarantees. This should enable implementations to be optimized for particular use cases and enable conventional Java environments to be used to help develop code that can be more easily shared between realtime and conventional systems.

Chapter 2

Overview

The RTSJ comprises several areas of extended semantics. These areas are discussed in approximate order of their relevance to realtime programming. The semantics and mechanisms of each of threads and scheduling, synchronization, asynchrony, clocks and timers, memory management, device access and raw memory, system options, and exceptions are all crucial to the acceptance of the RTSJ as a viable realtime development platform. Further details, exact requirements, class documentation, and rationale for these extensions are given in subsequent chapters.

2.1 Threads and Scheduling

One of the concerns of realtime programming is to ensure the timely and predictable execution of sequences of machine instructions. Various scheduling schemes name these sequences of instructions differently, for example, thread, task, module, or block. In Java, this computation is executed in the context of a thread. Since Java threads were designed for fair execution¹ rather than predictable execution, the RTSJ introduces the concept of a *schedulable*. These are the objects managed by the base scheduler: RealtimeThread and its subclasses and AbstractAsyncEventHandler and its subclasses. RealtimeThread is a specialization of Java's Thread.

Timely execution of schedulables means that the programmer can determine, by analysis of the program, testing the program on particular implementations, or both, whether particular threads will always complete execution before a given timeliness constraint. This is the essence of realtime programming: the addition of temporal constraints to the correctness conditions for computation. For example, for a program to compute the sum of two numbers, it may no longer be acceptable to

¹Actually, neither the Java Virtual Machine Specification[6] nor the Java Language Specification[5] defines how Java threads should be scheduled, but most implementations, including the reference implementations, use some sort of fair scheduling.

compute only the correct arithmetic answer but the answer must be computed within a particular time interval. Typically, temporal constraints are deadlines expressed in either relative or absolute time.

The term *scheduling* (or *scheduling algorithm*) refers to the production of a sequence (or ordering) for the execution of a set of schedulables (a *schedule*). This schedule attempts to optimize a particular metric (a metric that measures how well the system is meeting the temporal constraints). A *feasibility analysis* determines if a schedule has an acceptable value for the metric. For example in hard realtime systems, the typical metric is "number of missed deadlines" and the only acceptable value for that metric is zero. So called soft realtime systems use other metrics (such as mean tardiness) and may accept various values for the metric in use.

Many systems, including most conventional Java implementations, use thread priority to guide the determination of a schedule. Priority is typically an integer associated with a thread; these integers convey to the system the order in which the threads should execute. The generalization of the concept of priority is *execution eligibility*. The term *dispatching* refers to that portion of the system which selects the thread with the highest execution eligibility from the pool of threads that are ready to run.

In current realtime system practice, the assignment of priorities is typically under programmer control as opposed to under system control. As a base scheduler for realtime tasks, the RTSJ provides preemptive priority-based first-in-first-out (FIFO) scheduler, which also leaves the assignment of priorities to programmer control. Most realtime operation systems (RTOS) are also based on priority preemptive FIFO scheduling.

The RTSJ defines a number of classes with names of the format <string>Parameters such as ReleaseParameters, which provide parameters for resource management. An instance of one of these parameter classes holds a particular resource-demand characteristic for one or more schedulables. For example, the Priority-Parameters subclass of SchedulingParameters contains the execution eligibility metric of the base scheduler, i.e., a priority. At some time (construction-time or later when the parameters are replaced using setter methods), instances of parameter classes are bound to a schedulable. The schedulable then assumes the characteristics of the values in the parameter object. For example, a PriorityParameters instance with its priority set to the value representing the highest priority available on a system is bound to a schedulable, then that schedulable will assume the characteristic that it will execute whenever it is ready in preference to all other schedulables (except, of course, those also with the same priority).

The RTSJ provides implementers with the flexibility to install arbitrary scheduling algorithms in an implementation of the specification. This is to support the widely varying requirements of the realtime systems industry with respect to schedul-

ing. Use of the Java platform may help produce code written once but able to be executed on many different computing platforms. The RTSJ contributes to this goal, but the rigors of realtime systems detract from it. The RTSJ's rigorous specification of the required priority scheduler is critical for portability of time-critical code, but the RTSJ permits and supports platform-specific schedulers which are not necessarily portable.

2.2 Synchronization

If the computation in each thread were independent of the computation in all other threads, scheduling alone would be enough to ensure timeliness; however, this is usually not the case. Threads often need to communicate with one another or share data. Resources must be shared as well. Two threads cannot read different data from the disk at the same time nor write data to a disk at the same time. They cannot send a message to another machine at the same time. They cannot update the same in-memory data at the same time. One thread may have to wait for another thread to get the data it needs. Just as in a normal system, synchronization is required. In a realtime system, this synchronization must not prevent other threads from completing their tasks on time.

2.2.1 Priority Inversion

The additional concern for synchronization in a realtime system, as opposed to a conventional system, is that blocking can cause the wrong thread to run first. A high priority thread can be blocked by a low priority thread that is vying for the same resource. A priority queue can be used to ensure that a highest priority thread goes first, when more than one thread is waiting to enter a synchronized block, but this is not always sufficient.

Consider a single processor system with three threads, t_1 , t_2 , and t_3 , where t_1 has the highest priority and t_3 has the lowest priority. It is possible that t_2 can prevent t_1 from running by preempting t_3 . This is called priority inversion. It occurs when t_1 is blocked by attempting to acquire a lock that is held by thread t_3 and t_3 is preempted by t_2 . When t_2 does run, it may prevent t_3 from running indefinitely, thereby keeping t_1 blocked past its deadline.

What is needed is a mechanism the ensure that, while t_1 is waiting on a resource in use by t_3 , thread t_3 runs before all threads with a priority less than that of t_1 .

2.2.2 Priority Inversion Avoidance

Two of the most common mechanisms for avoiding priority inversion are priority inheritance and priority ceiling emulation (a.k.a. highest locker protocol). Both of these boost the priority of a thread holding the lock in order to prevent a noncontending thread from transitively blocking a higher priority thread which is waiting for the same lock. The difference is how high the priority is raised and when. Both take effect when a thread is in a synchronized section of code.

The first is the default behavior for synchronized blocks and methods. It applies to all code running within the implementation, not just to schedulables. The priority inheritance protocol is a well-known algorithm in the realtime scheduling literature and it has the following effect. If thread t_1 attempts to acquire a lock that is held by a lower-priority thread t_3 , then t_3 's priority is raised to that of t_1 as long as t_3 holds the lock (and recursively if t_3 is itself waiting to acquire a lock held by an even lower-priority thread).

The specification also provides a mechanism by which the programmer can override the default system-wide policy, or control the policy to be used for a particular monitor, provided that policy is supported by the implementation. The second policy, priority ceiling emulation protocol, can be set using this mechanism. It is also a well-known algorithm in the literature. The following three points provide a somewhat simplified description of its effect.

- A monitor is given a "priority ceiling" when it is created; the programmer should choose at least the highest priority of any thread that could attempt to enter the monitor.
- As soon as a thread enters synchronized code, its (active) priority is raised to the monitor's ceiling priority. If, through programming error, a thread has a higher base priority than the ceiling of the monitor it is attempting to enter, then an exception is thrown.
- On leaving the monitor, the thread has its active priority reset. In simple cases it will set be to the thread's previous active priority, but under some circumstances (e.g. a dynamic change to the thread's base priority while it was in the monitor) a different value is possible.

In addition, threads and asynchronous event handlers waiting to acquire a resource must be released from highest to lowest priority (in priority order). This applies to processors as well as to synchronized blocks. If schedulables with the same priority are possible under the active scheduling policy, such schedulables are awakened in FIFO order. This is exemplified in the following scenarios.

- Threads waiting to enter synchronized blocks are granted access to the synchronized block in priority order.
- A blocked thread that becomes ready to run is given access to a processor in priority order.

• A thread whose priority is explicitly set by itself or another thread is given access to a processor in priority order.

- A thread that performs a yield will be given access to the processor after waiting for threads of the same priority to be given a processor.
- Threads that are preempted in favor of a thread with higher priority may be given access to a processor at any time as determined by a particular implementation. The implementation is required to provide documentation stating exactly the algorithm used for granting such access.

In any case, there needs to be a fixed upper bound on the time required to enter a synchronized block for an unlocked monitor.

2.2.3 Execution Eligibility

Since an implementation of the RTSJ may provide schedulers other than priority-based schedulers, the notion of priority can be generalized to execution eligibility. Execution eligibility defines a partial ordering over all tasks for determining which task should run before which other tasks. Execution eligibility may be determined dynamically. For example, earliest deadline first (EDF) scheduling determines execution eligibility ordering by the order of the next deadlines for each of its tasks. The notion of priority, as described above, can be generalized to execution eligibility to integrate other schedulers into an RTSJ implementation.

2.2.4 Wait-Free Queues

While the RTSJ requires that the execution of schedulables which do not access the heap must not be delayed by garbage collection on behalf of lower-priority schedulables, an application can cause such a schedulable to wait for garbage collection by synchronizing using an object shared with a heap-using thread or schedulable. The RTSJ provides wait-free queue classes to provide protected, non-blocking, shared access to objects accessed by both regular Java threads and schedulables, which do not access the heap.

2.3 Asynchrony

Since a realtime system must be able to react to the outside world, the system needs to be able to change its execution flow asynchronously to the current execution. All external signals, whether interrupts, messages, or timed events, are asynchronous with respect to ongoing computation. This means that computation must be both startable and stoppable based on external stimuli.

12 2.3 Asynchrony

2.3.1 Asynchronous Events

Asynchronous event provide a means of starting computation based on external stimuli. The asynchronous event facility is based on two classes: AbstractAsyncEvent and AbstractAsyncEventHandler. An AbstractAsyncEvent object represents something that can happen, like a POSIX signal, a hardware interrupt, or a computed event like an airplane entering a specified region. When one of these events occurs, which is indicated by the fire() method being called, the associated instances of AbstractAsyncEventHandler are scheduled and the handleAsyncEvent() methods are invoked, thus the required logic is performed. Also, methods on AbstractAsyncEvent are provided to manage the set of instances of AbstractAsyncEventHandler associated with the instance of AbstractAsyncEvent.

An instance of an AbstractAsyncEventHandler can be thought of as something similar to a thread. When an event fires, the associated handlers are scheduled and the handleAsyncEvent() methods are invoked. What distinguishes an AbstractAsyncEventHandler from a simple Runnable is that an AbstractAsyncEventHandler has associated instances of ReleaseParameters, SchedulingParameters and MemoryParameters that control the actual execution of the handler once the associated AbstractAsyncEvent is fired. When an event is fired, the handlers are executed asynchronously, scheduled according to the associated ReleaseParameters and SchedulingParameters objects, in a manner that looks like the handler has just been assigned to its own thread. It is intended that the system can cope well with situations where there are large numbers of instances of AbstractAsyncEventHandler (tens of thousands), since the number of fired (in progress) handlers is expected to be much smaller.

There are specialized forms of AbstractAsyncEvent: AsyncEvent, AsyncLong-Event, and AsyncObjectEvent for events that are stateless, carry a long payload, and carry an Object payload, respectively. They are matched by specialized forms of AbstractAsyncEventHandler: AsyncEventHandler, AsyncLongEventHandler, and AsyncObjectEventHandler. Most external events are stateless, but sometimes it is helpful to be able to receive some information about the event or pass some data with the event. The Long and Object variants enable this and the POSIXRealtimeSignal takes advantage of it.

Another specialized form of an AsyncEvent is the Timer class, which represents an event whose occurrence is driven by time. There are two forms of Timers: the OneShotTimer and the PeriodicTimer. Instances of OneShotTimer fire once, at the specified time. Periodic timers fire initially at the specified time, and then periodically according to a specified interval.

Timers are driven by Clock objects. There is a special Clock object, Clock. getRealtimeClock(), that represents the realtime clock. The Clock class may be extended to represent other clocks, which the underlying system might make

available (such as an execution-time clock of some granularity).

2.3.2 Asynchronous Transfer of Control

Many event-driven computer systems that tightly interact with external physical systems (e.g., humans, machines, control processes, etc.) may require mode changes in their computational behavior as a result of significant changes in the non-computer real-world system. It simplifies the architecture of a system when a task can be programmatically terminated when an external physical system change causes its computation to be superfluous. Without this facility, a thread or set of threads have to be coded so that their computational behavior anticipates all of the possible transitions among possible states of the external system. When the external system makes a state transition, the changes in computation behavior can be managed by an oracle that terminates a set of threads required for the old state of the external system, and invokes a new set of threads appropriate for the new state of the external system. Since the possible state transitions of the external system are encoded in only the oracle and not in each thread, the overall system design is simpler.

There is a second requirement for a mechanism to terminate some computation, where a potentially unbounded computation needs to be done in a bounded period of time. In this case, if that computation can be executed with an algorithm that is iterative, and produces successively refined results, the system could abandon the computation early and still have usable results. The RTSJ supports aborting a computation by signalling from another thread, or the passage of time, with a feature termed Asynchronous Transfer of Control (ATC).

An example of the second case is processing compressed video for a human controller. The system knows that a new frame must be produced at a constant update frequency. The cost of each iteration is highly variable and the minimum required latency to terminate the computation and receive the last consistent result is much less than the mean iteration cost and bound. Therefore, using ATC for interrupting a computation to capture an intermediate result at the expiration of a known time bound is a convenient programming style. Of course, there are other kinds of programming tasks that may also benefit from ATC.

2.3.3 Principles

The RTSJ's approach to ATC uses asynchronous interruptions and exceptions, and is based on several guiding principles covering methodology, expressiveness, semantics, and pragmatic concerns.

14 2.3 Asynchrony

2.3.3.1 Methodological Principles

• A method must explicitly indicate its susceptibility to ATC, i.e., it is asynchronously interruptible. Since legacy code or library methods might have been written assuming no ATC, by default ATC must be turned off (more precisely, must be deferred as long as control is in such code).

- Even if a method allows ATC, some code sections must be executed to completion and thus ATC is deferred in such sections. These ATC-deferred sections are synchronized methods, static initializers, and synchronized statements.
- Code that responds to an ATC does not return to the point in the schedulable where the ATC was triggered; that is, an ATC is an unconditional transfer of control. Resumptive semantics, which returns control from the handler to the point of interruption, are not needed since they can be achieved through other mechanisms (in particular, an AsyncEventHandler).

2.3.3.2 Expressibility Principles

- A mechanism is needed through which an ATC can be explicitly triggered in a target schedulable. This triggering may be direct (from a source thread or schedulable) or indirect (through an asynchronously interrupted exception).
- It must be possible to trigger an ATC based on any asynchronous event including an external happening or an explicit event firing from another thread or schedulable. In particular, it must be possible to base an ATC on a timer going off.
- Through ATC it must be possible to abort a realtime thread but in a manner that does not carry the dangers of the Thread class's stop() and destroy() methods.

2.3.3.3 Semantic Principles

- If ATC is modeled by exception handling, there must be some way to ensure that an asynchronous exception is only caught by the intended handler and not, for example, by an all-purpose handler that happens to be on the propagation path.
- Nested ATCs must work properly. For example, consider two, nested ATC-based timers and assume that the outer timer has a shorter time-out than the nested, inner timer. If the outer timer times out while control is in the nested code of the inner timer, then the nested code must be aborted (as soon as it is outside an ATC-deferred section), and control must then transfer to the appropriate catch clause for the outer timer. An implementation that either handles the outer time-out in the nested code, or that waits for the longer (nested) timer, is incorrect.

2.3.3.4 Pragmatic Principles

• There should be straightforward idioms for common cases such as timer handlers and realtime thread termination.

• If code with a time-out completes before the timer's expiration, the timer needs to be automatically stopped and its resources returned to the system.

2.3.4 Asynchronous Realtime Thread Termination

A special case of stopping a particular computation is stopping a thread. Earlier versions of the Java language supplied mechanisms for achieving these effects: in particular the methods stop() and destroy() in class Thread. However, since stop() could leave shared objects in an inconsistent state, stop() has been deprecated. The use of destroy() can lead to deadlock (if a thread is destroyed while it is holding a lock) and although it was not deprecated until version 1.5 of the Java specification, its usage has long been discouraged. A goal of the RTSJ was to meet the requirements of asynchronous thread termination without introducing the dangers of the stop() or destroy() methods.

The RTSJ accommodates safe asynchronous realtime thread termination through a combination of the asynchronous event handling and the asynchronous transfer of control mechanisms. To create such a set of realtime threads consider the following steps:

- make all of the application methods of the realtime thread asynchronously interruptible;
- create an oracle which monitors the external world by setting up an asynchronous event with a number of asynchronous event handlers, which is fired when an appropriate mode change;
- have the handlers call interrupt() on each of the realtime threads affected by the change; then
- after the handlers call interrupt(), have them create a new set of realtime threads appropriate to the current state of the external world.

The effect of the event is to cause each interruptible method to abort abnormally by transferring control to the appropriate catch clause. Ultimately the run() method of the realtime thread will complete normally.

This idiom provides a quick (if coded to be so) but orderly clean up and termination of the realtime thread. Note that the oracle can comprise as many or as few asynchronous event handlers as appropriate.

2.4 Clocks, Time, and Timers

Realtime systems require a high resolution notion of time. Both very small units and very long periods of time must be uniformly representable, a range that is not even representable with a long value. Furthermore, a time can represent an absolute value, usually represented as some absolute fixed point in time plus an offset, or it can represent an interval of time. The time classes defined in Chapter 9 support a longs worth of seconds and another integer for nanoseconds.

2.5 Memory Management

The Java language is designed around automatic memory management, in particular garbage collection. Unfortunately, though garbage collection is a functional safety and security feature, conventional garbage collectors interrupt the normal flow of control in a program. Therefore, garbage-collected memory heaps had been considered an obstacle to realtime programming due to the potential for unpredictable latencies introduced by the garbage collector. Though convention collectors still have these drawbacks, there are now realtime collectors that can be used for hard realtime application. Still, the RTSJ provides an alternative to garbage collection for systems which require it, either because they do not have a garbage collector or deterministic garbage collector, or require heap partitioning for some other reason. Extensions to the memory model, which support memory management in a manner that does not interfere with the ability of realtime code to provide deterministic behavior, are provided to support these alternatives. This goal is accomplished by providing memory areas for the allocation of objects outside of the garbage-collected heap for both short-lived and long-lived objects. In order to provide additional separation between the garbage collector and schedulables which do not require its services, a schedulable can be marked no-heap to indicate that it never accesses the heap.

2.5.1 Memory Areas

The RTSJ introduces the concept of a memory area. A memory area represents an area of memory that may be used for allocating objects. Some memory areas exist outside of the heap and place restrictions on what the system and garbage collector may do with objects allocated within. Objects in some memory areas are never garbage collected; however, the garbage collector must be capable of scanning these memory areas for references to any object within the heap to preserve the integrity of the heap.

There are four basic types of memory areas:

• Heap memory represents an area of memory that is the heap. The RTSJ does not change the determinant of lifetime of objects on the heap. The lifetime is still determined by visibility.

- Immortal memory represents an area of memory containing objects that may be referenced without exception or garbage collection delay by any schedulable, specifically including no-heap realtime threads and no-heap asynchronous event handlers.
- Scoped memory provides a mechanism for managing objects that have a lifetime defined by their scope. It is akin to, but more general than, allocating objects on the thread stack.
- Physical memory allows objects to be created within specific physical memory regions that have particular important characteristics, such as memory that has substantially faster access.

2.5.2 Heap Memory

Heap memory is the memory area used by Java by default. It is garbage collected and the access time to objects in this area are not guaranteed unless the implementation supports realtime garbage collection. The RTSJ, as with conventional Java, supports only one Heap in a system. Multiple heaps are only practical in one of two configurations: the heaps are completely independent of one another or there are subsidiary heaps from which a program may not store references in the main heap. In other words, the subsidiary heaps can reference the main heap but not vice versa. Currently, the RTSJ does not address these cases.

2.5.3 Immortal Memory

ImmortalMemory is a memory resource shared among all schedulable objects and threads in an application. Objects allocated in ImmortalMemory are always available to non-heap threads and asynchronous event handlers without the possibility of a delay for garbage collection.

2.5.4 Scoped Memory

The RTSJ introduces the concept of scoped memory. A memory scope is used to give bounds to the lifetime of any objects allocated within it. When a scope is entered, every use of new causes the memory to be allocated from the active memory scope. A scope may be entered explicitly, or it can be attached to a schedulable which will effectively enter the scope before it executes the object's run() method.

The contents of a scoped memory are discarded when no object in the scope can be accessed. This is done by a technique similar to reference counting the scope. A conforming implementation might maintain a count of the number of external references to each memory area. The reference count for a ScopedMemory area would be increased by entering a new scope through the enter() method of MemoryArea, by the creation of a schedulable using the particular ScopedMemory area, or by the opening of an inner scope. The reference count for a ScopedMemory area would be decreased when returning from the enter() method, when the schedulable using the ScopedMemory terminates, or when an inner scope returns from its enter() method. When the count drops to zero, the finalize method for each object in the memory would be executed to completion. Reuse of the scope is blocked until finalization is complete.

Scopes may be nested. When a nested scope is entered, all subsequent allocations are taken from the memory associated with the new scope. When the nested scope is exited, the previous scope is restored and subsequent allocations are again taken from that scope.

Because of the lifetimes of scoped objects, it is necessary to limit the references to scoped objects, by means of a restricted set of assignment rules. A reference to a scoped object cannot be assigned to a variable from an outer scope, or to a field of an object in either the heap or the immortal area. A reference to a scoped object may only be assigned into the same scope or into an inner scope. The virtual machine must detect illegal assignment attempts and must throw an appropriate exception when they occur.

The flexibility provided in choice of scoped memory types allows the application to use a memory area that has characteristics that are appropriate to a particular syntactically defined region of the code.

2.5.5 Physical Memory Areas

In many cases, systems needing the predictable execution of the RTSJ will also need to access various kinds of memory at particular addresses for performance or other reasons. Consider a system in which very fast static RAM was programmatically available. A design that could optimize performance might wish to place various frequently used Java objects in the fast static RAM. The PhysicalMemoryRegion and PhysicalMemoryFactory classes provide the programmer this flexibility. The programmer would construct a physical memory object on the memory addresses occupied by the fast RAM.

2.5.6 Budgeted Allocation

The RTSJ also provides limited support for providing memory allocation budgets for schedulables using memory areas. Maximum memory area consumption and

2 Overview 19

maximum allocation rates for individual schedulable objects may be specified when they are created.

2.6 Device Access and Raw Memory

The RTSJ defines classes for programmers wishing to directly access physical memory from code written in the Java language. The RawMemory<Size> types, where <Size> is one of Byte, Short, Long, Float, or Double, define methods that enable the programmer to construct an object that represents a vector of consecutive positions in memory where the Size represents a primitive numerical data type, i.e., byte, short, int, long, float, and double repectively. Access to the physical memory is then accomplished through get<Size>() and set<Size>() methods of that object. No semantics other than the set<Size>() and get<Size>() methods are implied. One the other hand, the PhysicalMemoryRegion and PhysicalMemory-Factory classes enable programmers to construct an object that represents a range of physical memory addresses. When this object is used as a MemoryArea other objects can be constructed in the physical memory using the new keyword as appropriate. Factories can be used to create the desired type of both physical and raw memory.

2.6.1 Raw Memory Access

An instance of RawMemoryType models a range of physical memory locations as a fixed sequence of elements of a given size. The elements correspond to Java primitive types. For objects that access more than a single physical address, elements can be accessed through offsets from the base, where the offset is measured in multiples of the element size, not necessarily the byte offset in memory.

The RawMemoryType interface enables a realtime program to implement device drivers, memory-mapped registers, I/O space mapped registers, flash memory, battery-backed RAM, and similar low-level hardware.

A raw memory area cannot contain references to Java objects. Such a capability would be unsafe (since it could be used to defeat Java's type checking) and error prone (since it is sensitive to the specific representational choices made by the Java compiler).

2.7 System Options

POSIX defines some convenient interfaces for interacting with the system. These interactions include catching keyboard interrupts, user-to-process signaling, and interprocess signaling. Many realtime operating systems support this POSIX signal

2.9 Exceptions

interface. For this reason, the RTSJ provides a POSIX signal interface. Though many of the features POSIX signals provide are also available on most other operating systems, the specification does not require the POSIX signal interface to be emulated on these other platforms. Thus they are optional in the sense that they are only required on systems that directly support POSIX signals.

2.8 Exceptions

Aside from several new exceptions, the RTSJ provides a new interface for using exceptions without creating ephemeral objects and some new treatment of exceptions surrounding asynchronous transfer of control.

Using exceptions is resource intensive, since a new exception is allocated for each throw. This is particularly a problem for scoped memory, since scopes may need to be sized much larger than otherwise necessary to hold exceptions and their stack traces. Additionally, the information they contain cannot be propagated beyond the scope in which they are allocated. To better support scoped, immortal, and physical memory, a new class of throwable has been included: PreallocatedThrowable. Exceptions and Errors which implement this interface are not thrown in the usual manner, but with a style that does not require memory to be allocated at all.

Asynchronous transfer of control can cause the exception that triggered it to be propagated even when it is caught but the underlying interrupt is not cleared. The system rethrows the exception once the catch is finished. This is necessary since the exception hierarchy is poorly designed. There is a base class neither for all checked exceptions nor for all errors. There is no common base class for checked exceptions, so application code often contains a catch for Exception when only checked exceptions need to be caught. Even the JVM specification wording is awkward on this point, where a checked exception is an exception that is not a subclass of RuntimeException and an error is a throwable that is not a subclass of Exception.

2.9 Summary

The RTSJ refines the semantics of threads, scheduling, synchronization, memory management, and exceptions and adds features to support realtime threads, realtime scheduling, configuring synchronization, asynchrony, representing time, clocks and timers, additional methods for memory management, device access and raw memory, system options. These features and semantic refinements to the Java language and virtual machine have been outlined above, but the description does not constitute a definition for them. In other words, it is not normative. The normative chapters follow.

Chapter 3

Requirements and Conventions

This specification is a contract between the specification implementer and the user who writes a program to run on an implementation. To be able to support both implementation and use, many chapters provide additional rationale to help both the implementer and the user understand the intention behind the normative text. The remainder of this specification, including this chapter, is normative, except for the introductory text in each chapter and the sections named Rationale.

3.1 Base Requirements

The base requirements of this specification are as follows.

- Except as specifically required by this specification, any implementation shall fully conform to a Java platform configuration.
- Any implementation of this specification shall implement all classes and methods in the base module of this specification.
- Except as noted in this chapter, all classes and methods in an implemented module shall be implemented.
- The javax.realtime package shall contain no public or protected classes or methods not included in this specification.
- A realtime JVM implementation shall not be implemented in a way that permits unbounded priority inversion in any scheduling interaction it implements.
- Subject to the usual assumptions, the methods in javax.realtime can safely be used concurrently by multiple threads unless otherwise documented.
- Static final values, as found in Aperiodic Parameters, Sporadic Parameters, Realtime System, and Priority Scheduler, shall be implemented such that their values cannot be resolved by a conformant Java compiler (Java source to byte code).

22 3.2 Modules

Many aspects of this specification set a minimum requirement, but permit the implementation latitude in its implementation. For instance, the required priority scheduler requires at least 28 consecutively numbered realtime priorities. It does not, however, specify the numeric values of the maximum and minimum realtime priorities. Implementations are encouraged to offer as many realtime priority levels immediately above the conventional Java priorities as they can support.

Except where otherwise specified, when this specification requires object creation the object is created in the current allocation context.

3.2 Modules

The original RTSJ specification was conceived, with the exception of some optional features, as a monolith specification. This has inhibited the adoption of the RTSJ beyond the hard realtime community, because some of the features were considered to have an overly negative impact on overall JVM performance. Version 2.0 addresses this by breaking the specification into modules.

Modules provide a means of grouping like functionality together in a way that promotes maximal adoption for various implementation classes. A conventional JVM could simply implement the Base Module, without providing any realtime guarantees at all, to provide programmers with the benefits of features such as asynchronous event programming as an alternative to conventional threading. A hard realtime implementation could implement all modules to provide the maximal flexibility and functionality to the realtime programmer. Both would benefit from easier migration of code to realtime systems.

Every RTSJ implementation shall provide the Base Module functionality, but all other modules are optional. The optional modules are the Device Module and the Alternative Memory Areas module. In addition, there are a couple of optional features as well. This give the implementation some choice over which modules and features to include and which not.

3.2.1 Base Module

The Base Module adds the concepts of processor affinity, threads with realtime scheduling, and asynchronous event handling. This includes the notion of executing code at a given time interval, providing a much more stable response than using sleep in a loop. These features should have no impact on the overall performance of a system that implements them, but enrich the programming modules available to the programmer. The classes and interfaces required in this module are all in package javax.realtime and are listed below.

• AbsoluteTime (Section 9.4.1.1)

- AbstractAsyncEventHandler¹ (Section 8.4.3.2)
- AbstractAsyncEvent (Section 8.4.3.1)
- ActiveEventDispatcher (Section 8.4.3.3)
- ActiveEvent (Section 8.4.1.1)
- Affinity (Section 6.4.2.1)
- AperiodicParameters (Section 6.4.2.2)
- ArrivalTimeQueueOverflowException (Section 14.2.2.1)
- AsyncEventHandler (Section 8.4.3.5)
- AsyncEvent (Section 8.4.3.4)
- AsyncLongEventHandler (Section 8.4.3.7)
- AsyncLongEvent (Section 8.4.3.6)
- AsyncObjectEventHandler (Section 8.4.3.9)
- AsyncObjectEvent (Section 8.4.3.8)
- BoundAbstractAsyncEventHandler (Section 8.4.1.3)
- BoundAsyncEventHandler (Section 8.4.3.10)
- BoundAsyncLongEventHandler (Section 8.4.3.11)
- BoundAsyncObjectEventHandler (Section 8.4.3.12)
- CeilingViolationException (Section 14.2.2.2)
- Clock (Section 10.4.2.1)
- ConfigurationParameters (Section 5.3.2.1)
- DeregistrationException (Section 14.2.2.3)
- DuplicateFilterException (Section 15.3.2.1)
- GarbageCollector (Section 13.3.1.1)
- HeapMemory (Section 11.4.2.1)
- HighResolutionTime (Section 9.4.1.2)
- ImmortalMemory (Section 11.4.2.2)
- ImportanceParameters (Section 6.4.2.4)
- LateStartException (Section 14.2.2.5)
- MemoryArea (Section 11.4.2.3)
- MITViolationException (Section 14.2.2.6)
- MonitorControl (Section 7.4.1.1)
- OneShotTimer (Section 10.4.2.2)
- PeriodicParameters (Section 6.4.2.5)
- PeriodicTimer (Section 10.4.2.3)
- PhasingPolicy (Section 5.3.1.1)
- PriorityCeilingEmulation (Section 7.4.1.2)
- PriorityInheritance (Section 7.4.1.3)
- PriorityParameters (Section 6.4.2.6)
- PriorityScheduler (Section 6.4.2.7)

¹The no-heap flag is present, but can only be set if the Memory Module is supported.

3.2 Modules

- ProcessingGroupParameters (Section 15.3.3.6)
- ProcessorAffinityException (Section 14.2.2.11)
- RealtimeSecurity (Section 13.3.1.6)
- RealtimeSystem (Section 13.3.1.7)
- RealtimeThread (Section 5.3.2.2)
- RegistrationException (Section 14.2.2.12)
- RelativeTime (Section 9.4.1.3)
- ReleaseParameters (Section 6.4.2.9)
- ResourceLimitError (Section 14.2.3.5)
- Schedulable (Section 6.4.1.2)
- Scheduler (Section 6.4.2.11)
- SchedulingParameters (Section 6.4.2.13)
- SizeEstimator (Section 11.4.2.6)
- SporadicParameters (Section 6.4.2.14)
- Timable (Section 10.4.1.3)
- TimeDispatcher (Section 10.4.2.4)
- Timer (Section 10.4.2.5)

3.2.2 Device Module

The Device Module provides a low level interface for interacting with the real world. Though realtime control systems need this kind of interaction, other systems can benefit from it as well. Data collection, that is not time critical is a good example. For instance, monitoring the temperature or humidity in a room could be done easily with off-the-self hardware using this module. The classes required in this module are all in the package <code>javax.realtime.device</code> and are listed below.

- Happening (Section 12.4.3.1)
- HappeningDispatcher (Section 12.4.3.2)
- InterruptServiceRoutine (Section 12.4.3.3)
- POSIXRealtimeSignal (Section 13.3.1.2)
- POSIXRealtimeSignalDispatcher (Section 13.3.1.3)
- POSIXSignal (Section 13.3.1.4)
- POSIXSignalDispatcher (Section 13.3.1.5)
- RawBufferFactory (Section 12.4.3.4)
- RawMemory (Section 12.4.1.16)
- RawMemoryFactory (Section 12.4.3.5)
- RawMemoryRegion (Section 12.4.3.6)
- RawMemoryRegionFactory (Section 12.4.1.17)
- RawByte (Section 12.4.1.1)
- RawByteReader (Section 12.4.1.2)
- RawByteWriter (Section 12.4.1.3)

- RawDouble (Section 12.4.1.4)
- RawDoubleReader (Section 12.4.1.5)
- RawDoubleWriter (Section 12.4.1.6)
- RawFloat (Section 12.4.1.7)
- RawFloatReader (Section 12.4.1.8)
- RawFloatWriter (Section 12.4.1.9)
- RawInt (Section 12.4.1.10)
- RawIntReader (Section 12.4.1.11)
- RawIntWriter (Section 12.4.1.12)
- RawLong (Section 12.4.1.13)
- RawLongReader (Section 12.4.1.14)
- RawLongWriter (Section 12.4.1.15)
- RawMemoryFactory (Section 12.4.3.5)
- RawMemoryRegionFactory (Section 12.4.1.17)
- RawShort (Section 12.4.1.18)
- RawShortReader (Section 12.4.1.19)
- RawShortWriter (Section 12.4.1.20)
- UnsupportedRawMemoryRegionException (Section 12.4.2.1)

3.2.3 Alternative Memory Areas Module

The Alternative Memory Areas Module provides an alternative to a single heap with garbage collection model for memory management. Most of the facilities are centered around providing an alternative to garbage collection, but facilities for providing what memory to use for Java objects is also addressed. The classes required in this module are all in package javax.realtime.memory and are listed below.

- AlignmentError (Section 14.2.3.1)
- ChildScopeVisitor (Section 11.4.1.1)
- IllegalAssignmentError (Section 14.2.3.3)
- InaccessibleAreaException (Section 14.2.2.4)
- LTMemory (Section 11.5.3.1)
- MemoryAccessError (Section 14.2.3.4)
- MemoryInUseException (Section 14.2.2.7)
- MemoryParameters (Section 11.4.2.4)
- MemoryScopeException (Section 14.2.2.8)
- MemoryTypeConflictException (Section 14.2.2.9)
- OffsetOutOfBoundsException (Section 14.2.2.10)
- PhysicalMemoryCharacteristic (Section 11.5.1.1)
- Physical Memory Factory (Section 11.5.3.2)
- Physical Memory Region (Section 11.5.3.3)
- PhysicalMemorySelector (Section 11.5.3.4)

26 3.2 Modules

- PinnableMemory (Section 11.5.3.5)
- ScopedCycleException (Section 14.2.2.13)
- ScopedMemory (Section 11.4.2.5)
- SizeOutOfBoundsException (Section 14.2.2.14)
- StackedMemory (Section 11.5.3.6)
- ThrowBoundaryError (Section 14.2.3.6)
- UnsupportedPhysicalMemoryException (Section 14.2.2.16)
- VirtualMemoryCharacteristic (Section 11.5.1.2)
- WaitFreeReadQueue (Section 7.4.1.5)
- WaitFreeWriteQueue (Section 7.4.1.6)

3.2.4 Optional Features

Even with modules it is difficult to elliminate all optional features. These features are either not easy to implement on all platforms or have the potential to cause a significant performance overhead. Therefore, an application cannot depend on them to be present in every implementation. However, if an optional facility is implemented, the application may rely on it to behave as specified here. Those extensions are illustrated in Table 3.1.

Cost enforcement	Enables the application to control the processor			
	utilization of a schedulable.			
Processing Group enforce-	Enables the application to control the processor			
ment	utilization of a group of schedulables			
Processing Group deadline	Enables the application to specify a processing			
less than period	group deadline less than the processing group			
	period			
Allocation-rate enforcement	Enables the application to limit the rate at			
on heap allocation	which a schedulable creates objects in the heap.			
Interrupt Service Routine	Provides first level interrupt processing in Java.			
Asynchronous Transfer of	Enables schedules to be interrupted asyn-			
Control (ATC)	chronously.			

Table 3.1: RTSJ Options

The ProcessingGroupParameters class is only functional on systems that support the processing group enforcement option. Cost enforcement, and cost overruns handlers are only functional on systems that support the cost enforcement option. If processing group enforcement is supported, ProcessingGroupParameters shall function as specified. If cost enforcement is supported, cost enforcement, and cost overrun handlers shall function as specified.

In implementations where the processing group deadline less than period is not supported, values passed to the constructor for ProcessingGroupParameters and its setDeadline method are constrained to be equal to the period. If the option is supported, processing group deadlines less than the period shall be supported and function as specified.

In implementations where heap allocation rate enforcement is supported, it shall be implemented as specified. If heap allocation rate enforcement is not supported, the allocation rate attribute of MemoryParameters shall be checked for validity but otherwise ignored by the implementation.

First level interrupt handling can only be supported in certain contexts, such as in kernel space and in a device driver context in user space on systems that support this feature. Normally user space programs cannot handle interrupts directly. The class should be present in every system that implements the device module, but in implementations that do not support first level interrupt handling, the register should always throw an UnsupportedOperationException.

ATC, if implemented, requires the following classes:

- Timed (Section 8.4.2.2)
- AsynchronouslyInterruptedException (Section 8.4.2.1)
- Interruptible (Section 8.4.1.4)

Extensions to this specification are allowed, but shall not require changes to the javax.realtime package tree.

3.2.5 Deprecated Classes

Classes that have been deprecated as of this specification are not part of any module, but may be implemented by a full RTSJ implementation. They comprise the following classes:

- ImmortalPhysicalMemory (Section 15.3.3.1)
- Physical Memory Manager (Section 15.3.3.5)
- PhysicalMemoryTypeFilter (Section 15.3.1.1)
- POSIXSignalHandler (Section 15.3.3.4)
- RationalTime (Section 15.3.3.7)
- RawMemoryAccess (Section 15.3.3.8)
- RawMemoryFloatAccess (Section 15.3.3.9)
- VTMemory (Section 15.3.3.10)
- VTPhysicalMemory (Section 15.3.3.11)
- WaitFreeDequeue (Section 15.3.3.12)

They are documented fully in Chapter 15.

3.3 Conditionally-Required Facilities

An implementation shall support conditionally-required facilities if the underlying hardware and software permits. This specification includes two conditionally-required facilities:

POSIXSignal	This class shall be implemented on every platform where POSIX		
	signals are supported.		
RawMemory	If the system supports address translation, e.g., has an MMU, and		
	implements the Device Module, the implementation shall support		
	the memory mapping features of the raw memory access classes.		

3.3.1 Options for Development Platforms

The following semantics are optional for an RTSJ implementation designed and licensed exclusively as a development tool.

- The priority scheduler need not support fixed-priority preemptive scheduling or the priority inversion avoidance algorithms. This does not excuse an implementation from fully supporting the relevant APIs. It only reduces the required behavior of the underlying scheduler to the level of the scheduler in the Java specification extended to at least 28 priorities.
- No semantics constraining timing beyond the requirements of the Java specifications need be supported. Specifically, garbage collection may delay any thread without bound and any delay in delivering asynchronously interrupted exceptions is permissible including never delivering the exception. Note, however, that if any AIE other than the generic AIE is delivered, it shall meet the AIE semantics, and all heap-memory-related semantics other than preemption remain fully in effect. Further, relaxed timing does not imply relaxed sequencing. For instance, semantics for scoped memory shall be fully implemented.
- The RTSJ semantics that alter standard Java method behavior, such as the modified semantics for Thread.setPriority and Thread.interrupt, are not required for a development tool, but such deviations from the RTSJ shall be documented, and the implementation shall be able to generate a runtime warning each time one of these methods deviates from standard RTSJ behavior.

These relaxed requirements set a floor for RTSJ development system tool implementations. A development tool may choose to implement semantics that are not required.

3.4 Required Documentation

Each implementation of the RTSJ is required to provide documentation for several behaviors.

- If schedulers other than the base priority scheduler are available to applications, the behavior of the scheduler and its interaction with each other scheduler as detailed in the Scheduling chapter shall be documented. The list of classes that constitute schedulable objects for the scheduler, unless that list is the same as the list of schedulables for the base scheduler, shall be included. If there are restrictions on use of the scheduler from a non-heap context, these restrictions shall be documented as well.
- A schedulable that is preempted by a higher-priority schedulable is placed in the queue for its active priority, at a position determined by the implementation. If the preempted schedulable is not placed at the front of the appropriate queue the implementation shall document the algorithm used for such placement. Placement at the front of the queue may be required in a future version of this specification.
- An implementation is required to document the granularity at which the current CPU consumption is updated for cost monitoring and cost enforcement, when the later is implemented.
- The implementation shall fully document the behavior of any subclasses of GarbageCollector.
- An implementation that provides any MonitorControl subclasses not detailed in this specification shall document their effects, particularly with respect to priority inversion control and which (if any) schedulers fail to support the new policy.
- If on losing "boosted" priority due to a priority inversion avoidance algorithm, the schedulable is not placed at the front of its new queue, the implementation shall document the queuing behavior.
- For any available scheduler other than the base scheduler, an implementation shall document how, if at all, the semantics of synchronization differ from the rules defined for the default PriorityInheritance monitor control policy. It shall supply documentation for the behavior of the new scheduler with priority inheritance (and, if it is supported, priority ceiling emulation protocol) equivalent to the semantics for the base priority scheduler found in the Synchronization chapter. If there are restrictions on use of the scheduler from a no-heap context, the documentation shall detail the effect of these restrictions for each RTSJ API.
- The worst-case response interval between firing an AsyncEvent because of a bound happening to releasing an associated AsyncEventHandler (assuming no higher-priority schedulables are runnable) shall be documented for some

3.6 Conventions

reference architecture.

• The interval between firing an AsynchronouslyInterruptedException at an ATC-enabled thread and first delivery of that exception (assuming no higher-priority schedulables are runnable) shall be documented for some reference architecture.

- If cost enforcement is supported, and the implementation assigns the cost of running finalizers for objects in scoped memory to any schedulable other than the one that caused the scope's reference count to drop to zero by leaving the scope, the rules for assigning the cost shall be documented.
- If cost enforcement is supported, and enforcement (blocked-by-cost-overrun) can be delayed beyond the enforcement time granularity, the maximum such delay shall be documented.
- If the implementation of RealtimeSecurity is more restrictive than the required implementation, or has run-time configuration options, those features shall be documented.
- For each supported clock, the documentation shall specify whether the resolution is settable, and if it is settable the documentation shall indicate the supported values.
- If an implementation includes any clocks other than the required realtime clock, their documentation shall indicate in what contexts those clocks can be used. If they cannot be used in no-heap context, the documentation shall detail the consequences of passing the clock, or a time that uses the clock to a no-heap schedulable.

3.5 Conventions

Throughout the RTSJ, when we use the word *code*, we mean code written in the Java programming language. When we mention the Java language in the RTSJ, that also refers to the Java programming language. The use of the term *heap* in the RTSJ will refer to the heap used by the runtime of the Java language.

3.6 Definitions

A thread is an instance of the java.lang. Thread class.

A realtime thread is an instance of the javax.realtime.RealtimeThread class.

A Java thread is a thread that is not a realtime thread.

A no-heap realtime thread is an instance of the javax.realtime.RealtimeThread class that will not access the heap.

An event handler is an instance of the javax.realtime.AbstractAsyncEventHandler class.

The term *schedulable* refers to any object that is of type <code>Schedulable</code>, and is recognized as a dispatchable entity by the base scheduler. The base scheduler's set of schedulables comprises instances of <code>RealtimeThread</code> and <code>AsyncEventHandler</code>. Other schedulers may support a different set of schedulables, but this specification only defines the behavior of the base scheduler so the term schedulable should be understood as "schedulable by the base scheduler."

3.6 Definitions

Chapter 4

Conventional Java Classes and Language

Though compatibility with conventional Java, i.e., any Java runtime environments that implement the Java Virtual Machine Specification and the Java Language Specification but not the RTSJ, is the first concern of this specification, there are several several cases where being able to meet realtime constraints requires a tightening of the semantics of the virtual machine and some subtle changes to the semantics of two key classes: java.lang.Thread and java.lang.ThreadGroup. These constraints and changes place additional requirements on scheduling, the memory model, and memory management. Finally, the specification defines a new type of concurrent activity called an asynchronous event handler; hence, the meaning of current thread has a different interpretation than in standard java.

4.1 Scheduling

How threads are scheduled in a realtime system is quite different than what one expects in a conventional Java virtual machine. For compatibility, this means that there must be a domain where conventional Java threads are scheduled in a familiar way and another domain that supports realtime scheduling. This separation is done in part via thread priority.

Threads running with the conventional ten priorities defined in Java should be scheduled as expected. Unfortunately, in order to ease the porting of Java to different environments, the scheduling of conventional Java threads is under specified. This has been resolved to avoid surprising the programmer in practice by providing some sort of fair scheduling for these threads, i.e, scheduling that at least prevents thread starvation, but may also try to balance CPU availablility across threads. For threads running in these priorities an implementation of this specification should provide

34 4.1 Scheduling

some notion of fair scheduling between threads with priority between one and ten inclusive.

Realtime threads need a stronger notion of prioritization than conventional Java threads, so this specification requires the implementation of at least a priority-preemptive scheduler with run to completion (or next suspension point) semantics. Priorities above the conventional ten priorities are used for this. Multithreaded code that runs with the priority-preemptive scheduler (or any other realtime scheduler) is more prone to deadlock or starvation than code run with fair scheduling. The changes to Thread and ThreadGroup are to support this realtime scheduling.

- The semantics of set and get methods for priority in Thread differ for realtime threads.
- The ThreadGroup class's behavior differs with respect to realtime threads.
- The behavior of the ThreadGroup-related methods in Thread differ when they are applied to realtime threads.

Code running at realtime priorities can also block conventional Java threads, possibly indefinitely.

4.1.1 Priority

The methods setPriority and getPriority in java.lang. Thread are final. The realtime thread classes are consequently not able to override them and modify their behavior to suit the requirements of the RTSJ scheduler. To bring the java.lang. Thread class in line with its realtime subclasses, the semantics of the getPriority and setPriority methods must be modified.

4.1.1.1 Setting Priority

The setPriority method has the following additional requirements.

- Use of Thread.setPriority() shall not affect the correctness of the priority inversion avoidance algorithms controlled by PriorityCeilingEmulation and PriorityInheritance. Changes to the base priority of a realtime thread as a result of invoking Thread.setPriority() are governed by semantics from Chapter 7 on Synchronization.
- realtime threads may use **setPriority** to apply the expanded range of priorities available to realtime threads. When a realtime thread's priority parameters object is not shared, **setPriority** behaves effectively as if it included the following code snippet:
- 1 PriorityParameters pp = getSchedulingParameters();
- pp.setPriority(newPriority);

- When the realtime thread's priority parameters object is shared with other schedulables, setPriority must give the thread an unshared PriorityParameters instance allocated in the same memory area as the realtime thread object and containing the new priority value.
- setPriority throws IllegalArgumentException when the thread is a realtime thread and the new priority is outside the range allowed by the realtime thread's scheduler.
- setPriority throws ClassCastException when the thread is a realtime thread and its current scheduling parameters object is not an instance of Priority-Parameters.

4.1.1.2 Getting Priority

The getPriority method has the following additional requirements.

• When used on a realtime thread, **getPriority** behaves effectively as if it included the following code snippet:

```
1 (PriorityParameters)t.getSchedulingParameters()).getPriority()};
```

• When the scheduling parameters are not of type PriorityParameters, then a ClassCastException is thrown.

All supported monitor control policies must apply to Java threads as well as to all schedulables.

4.1.2 Thread Groups

Thread groups are rooted at a base ThreadGroup object which may be created in heap or immortal memory. All thread group objects hold references to all their member threads, and subgroups, and a reference to their parent group. Since heap and immortal memory can not hold references to scoped memory, it follows that a thread group can never be allocated in scoped memory. It then follows that no thread allocated in scoped memory may be referenced from any thread group, and consequently such threads are not part of any thread group and will hold a null thread group reference. Similarly, a nonheap RealtimeThread can not be a member of a heap allocated thread group.

- 1. Realtime threads with null thread groups are not included in any operation on any thread group. This applies to enumeration and interruption, as well as the deprecated actions stop, resume, and suspend. However, when the current thread is a realtime thread with a null thread group:
 - The Thread.enumerate class method returns the integer 1, and populates its array argument with the current realtime thread.

- Thread.activeCount returns 1.
- Thread.getThreadGroup returns null in all cases, not only when the thread has terminated.
- 2. A Java thread (not a realtime thread) that is created from a realtime thread without an explicit thread group and is not assigned a thread group by the security manager inherits the thread group of the realtime thread, when it has one; otherwise an attempt is made to add it to the application root thread group. The constructor shall throw a SecurityException when the Java thread is not permitted to use the application root thread group.
- 3. The thread group of a Java thread created by an asynchronous event handler is assigned as if it was created by a realtime thread without a thread group (as described in 2. above)
- 4. A thread group cannot be created in scoped memory. The constructor shall throw an IllegalAssignmentError.
- 5. Setting a maximum priority on a thread group, either explicitly or via it parent, has no influence on the realtime threads in that group.
- 6. Except as specified previously, realtime threads have the same ThreadGroup membership rules as the parent Thread class.

4.1.3 Current Thread

In Java, the currently executing thread can always be determined by calling the static method Thread.currentThread(). In the RTSJ, there are two types of schedulable entities: threads and asynchronous event handlers. The latter may be mapped dynamically by the realtime Java virtual machine onto the underlying thread model. The method Thread.currentThread() when called from an unbound asynchronous event handler will return the thread that is being used as the current execution engine for that event handler. The program should not rely on this being constant for the lifetime of the program. It can rely on it being constant for the current release of the handler (see 6.2 for the definition of a release). It is not recommended that the program perform any operations on this underlying thread as it may have an impact beyond that of the current event handler. This also means that thread local memory cannot be relied on in unbound event handlers, because data saved in one release may not be available in the next release.

4.2 Java Memory Model

Some aspects of the Java Memory Model must be tightened for this specification, in particular with regards to interactions with native code or when using the Device Module. A conforming implementation must ensure that volatile loads and stores,

raw memory operations (see 12.3.1), and RawBufferFactory fence methods are all ordered in a way that is consistent with respect to native code or hardware devices using platform-native memory coherence protocols to access raw memory or raw byte buffers shared with the virtual machine.

4.3 InterruptedException

The specification extends the use of the InterruptedException to support asynchronous transfer of control.

The interruptible methods in the standard libraries (such as Object.wait, Thread.sleep, and Thread.join) have their contract expanded slightly such that they will respond to interruption not only when the interrupt method is invoked on the current thread, but also, for schedulables, when executing within a call to AIE.doInterruptible and that AIE is fired. See Chapter 8 on Asynchrony.

4.4 Memory Management

The specification provides for two means of managing memory: garbage collection and special memory areas, which are not collected by the garbage collector. Since memory allocated in Java is always in the heap, or at least appears to be, the initial allocation area is the heap. Furthermore, the allocation area can only be changed either by entering another memory area or by calling a method that explicitly causes allocation in another area. When this alternate memory management module is not present, the conventional java semantics for allocation prevails.

4.4.1 Memory Areas

Using a conventional class in a memory area other than a heap can result in unexpected behavior. This is particularly the case when a method of a class is called in a different area than the object was created, which can lead to exceptions. In general, memory areas other than the heap may become full much faster than expected, because objects that are no longer referenced will not be collected automatically.

A method that allocates an object or takes an object that was created in a different memory area and tries to assign it to a field of its associated object can fail. For example, creating a List on the heap and adding to it from a scoped memory will most likely cause an exception. Although using other memory areas such as scoped memory is useful for helping to improving determinism, its use complicates the logic of application and library code.

On systems that support memory areas other than heap and do not support realtime garbage collection, some global resources must be put in immortal memory.

System properties and their **String** values allocated during system initialization shall be allocated in immortal memory. For such a system, class objects should also be stored there. Though this avoids priority inversion with the garbage collector, it can cause higher memory use than expected.

4.4.2 Garbage Collection

Garbage collection is an important safety feature of the Java language and runtime environment. Unfortunately, the garbage collection process can interfere with a realtime program's ability to always meet its timing deadlines. This specification provides two main means of circumventing this problem: using a realtime garbage collector or using the memory area module as an alternative to garbage collection for realtime code. Additionally, an implementation may ignore the problem for an implementation meant as a development system or for systems that choose not to provide realtime guarantees. In any case, an implementation must document what realtime guarantees it gives and which method it uses to do so.

4.4.3 Realtime Garbage Collections

Industrial realtime garbage collectors are available with varying approaches to providing realtime response. Though new collectors will undoubtably be developed, all current ones use a variant of the mark-and-sweep algorithm. In all cases, the collectors are incremental: realtime response is obtained by limiting how much of a collection cycle is done each time the collector runs. Even on a multicore machine, the garbage collector must be incremental, because it must tolerate changes to the heap during garbage collection. Then CPU use is limited by tying the collector to one ore more cores.

4.4.3.1 Thread-Based Collectors

A realtime thread-based collector is an incremental garbage collector that has its own thread of control and runs at intervals. In this case, the garbage collector needs to be scheduled to ensure that it runs often enough and long enough at each interval to recycle discarded objects fast enough to keep up with allocations. There should also be some maximum time after which the garbage collector can be interrupted.

4.4.3.2 Allocation-Based Collectors

A realtime allocation-based garbage collector does not have its own thread of control. Instead, some interval of garbage collection work is done at each allocation. This work is generally a function of the size of the object being allocated. This work

becomes part of the execution time of the program. Again, there should be some maximum time after which the garbage collector can be interrupted.

4.4.3.3 Alternatives to Garbage Collection

This specification provide an Alternative Memory Areas Module for managing memory without garbage collection. An implementation of this specification may provide realtime response by requiring applications to use that module instead of providing a realtime garbage collector. This means that all realtime threads would have to run above the priority of the garbage collector and all communication with conventional threads would have to use some nonblocking protocol.

4.4.3.4 Developer Implementation

An implementation that simply provides all the API but no realtime guarantee is also permitted. This is useful as a development environment. Also, many of the APIs are useful event in a conventional Java implementation.

4.5 Summary

The refinements and changes to the semantics of the Java runtime environment and classes shall not affect the functional correctness of Java code written for a conventional Java implementation when running on a Java runtime environment which implements this specification. There may be changes in the relative timing of threads, but these should not violate the conventional Java specifications. The use of some RTSJ features with code written for a conventional Java implementation may, however, be surprising. This is particularly true when using alternate memory areas, asynchronous transfer of control, and thread local memory in conjunction with unbound asynchronous event handlers.

40 4.5 Summary

Chapter 5

Realtime Threads

This section describes the realtime thread classes. This classes provides for the creation of

- realtime threads that have more precise scheduling semantics than java.-lang.Thread, and
- realtime threads that have no dependency on the heap.

The RealtimeThread class extends java.lang.Thread. The ReleaseParameters, SchedulingParameters, MemoryParameters and ProcessingGroupParameters objects passed to the RealtimeThread constructor allow the temporal and processor demands of the thread to be communicated to the *scheduler*. The ConfigurationParameters class defines, amongst other things, the size of Java thread stack; it also indicates whether the RealtimeThread is allowed to allocate or even reference objects from the Java heap (and can thus safely execute in preference to the garbage collector). The PhasingPolicy class defines the relationship between the threads start time and its first release time when the start time is in the past.

5.1 Overview

The RTSJ provides two types of objects which implement the Schedulable interface: realtime threads and asynchronous event handlers. This chapter defines the facilities that are available to realtime threads. In many cases these facilities are also available to asynchronous event handlers. In particular:

- the default scheduler must support the scheduling of both realtime threads and asynchronous event handlers;
- realtime threads and asynchronous event handlers are allowed to enter into memory areas and consequently they have associated scope stacks;
- the flow of control of realtime threads and asynchronous event handlers are affected by the RTSJ asynchronous transfer of control facilities;

42 5.2 Semantics

Where the semantics apply to both realtime threads and asynchronous event handlers, the term *schedulable* will be used.

5.2 Semantics

- 1. Garbage collection executing in the context of a Java thread must not in itself block execution of a no-heap thread with a higher execution eligibility; however application locks work as specified even when the lock causes synchronization between a heap-using thread and a no-heap thread.
- 2. Each realtime thread has an attribute which indicates whether an Asynchron-ouslyInterruptedException is pending. This attribute is set when a call to RealtimeThread.interrupt() is made on the associated realtime thread, and when an asynchronously interrupted exception's fire method is invoked between the time the realtime thread has entered that exception's doInterruptible method, and before it has return from doInterruptible. (See Chapter 8 on Asynchrony.)
- 3. A call to RealtimeThread.interrupt() generates the system's generic AsynchronouslyInterruptedException. (See Chapter 8 on Asynchrony.)
- 4. The RealtimeThread.waitForNextPeriod, RealtimeThread.waitForNext-Release, RealtimeThread.waitForNextPeriodInterruptible and RealtimeThread.waitForNextReleaseInterruptible methods are for use by realtime threads that have periodic or aperiodic release parameters. In the absence of any deadline miss or cost overrun, or an interrupt in the case of waitForNextReleaseInterruptible, the methods return when the realtime thread's next period/release is due.
- 5. In the presence of a cost overrun or a deadline miss, the behavior of wait-ForNextRelease and waitForNextReleaseInterruptible is governed by the thread's scheduler.
- 6. The first release time of a realtime thread is governed by the value of any start time in its associated ReleaseParameter object and the time at which the RealtimeThread.start method is called (or the RealtimeThread.start-Periodic method is called and the value of any PhasingPolicy parameter passed to it).
- 7. Instances of RealtimeThread that are created in scoped memory and instances of RealtimeThread with the no-heap flag set do not have conventional references to thread groups nor do thread groups have conventional references to these threads. For the purposes of this version of the specification, those references are null.
- 8. Realtime threads with null thread groups respond to uncaught exceptions as follows:

5 Realtime Threads 43

• when the exception is a subclass of ThreadDeath, the thread simply terminates,

- otherwise the thread prints a stack trace of the exception to System.err before it terminates.
- 9. System-related termination activity (such as execution of finalizers for scoped objects in scoped memory areas that become unreferenced) triggered by termination of a realtime thread is not subject to cost enforcement or deadline miss detection.

5.3 Package javax.realtime

5.3.1 Enumerations

5.3.1.1 PhasingPolicy

This class defines a set of constants that specify the supported policies for starting a thread or periodic timer, when it is started later than the assigned absolute time. The following table specifies the effective start time (that is, the first release time of a periodic real-time thread). The effective start time of a periodic timer is similar; where the first firing is equivalent to the first release.

Available since RTSJ 2.0

Inheritance

java.lang.Object java.lang.Enum javax.realtime.PhasingPolicy

5.3.1.1.1 Enumeration Constants

STRICT_PHASING

public static final STRICT_PHASING

ADJUST_FORWARD

public static final ADJUST_FORWARD

ADJUST_BACKWARD

public static final ADJUST_BACKWARD

ADJUST_TO_START

public static final ADJUST_TO_START

2.0 (Draft 20)

Table 5.1: Effect of Phasing Policy on the First Release of a Realtime Thread with Periodic Parameters

	STRICT	ADJUST	ADJUST	ADJUST
	PHASING	FORWARD	BACK-	TO START
			WARD	
Relative Time	The time of	The time of	The time of	The time of
	start method	start method	start method	start method
	invocation	invocation	invocation	invocation
	plus start	plus start	plus start	plus start
	time.	time.	time.	time.
Absolute	The start	All releases	The first re-	Release im-
Time, earlier	method	before the	lease occurs	mediately
than call to	throws an	time start	immediately	and set next
start	exception.	is called are	and the next	release time
		ignored. The	release is	to be at the
		first release is	at the start	time the start
		at the start	time plus	method was
		time plus	the smallest	invoked plus
		the smallest	multiple of	period.
		multiple of	period whose	
		period whose	time is af-	
		time is af-	ter the time	
		ter the time	start was	
		start was	called.	
A.1. 1	77.	called.		
Absolute	First release is	First release is	First release is	First release is
Time, later	at time passed	at time passed	at time passed	at time passed
than call to	to start.	to start.	to start.	to start.
start	T 1	D	D: / 1	T: / 1
Without	First release	First release	First release	First release
Time	is at time of			
	start method	start method	start method	start method
	invocation	invocation	invocation	invocation

5.3.1.1.2 Methods

values

```
Signature
    public static
    javax.realtime.PhasingPolicy[] values()
```

valueOf(String)

```
Signature
    public static
    javax.realtime.PhasingPolicy valueOf(String name)
```

5.3.2 Classes

5.3.2.1 ConfigurationParameters

Configuration parameters provide a way to specify various implementation-dependent parameters such as the Java stack and native stack sizes, and to configure the statically allocated ThrowBoundaryError¹ associated with a Schedulable².

Note that these parameters are immutable.

Available since RTSJ 2.0

Inheritance

```
java.lang.Object
javax.realtime.ConfigurationParameters
```

5.3.2.1.1 Constructors

 $^{^{1}}$ Section 14.2.3.6

 $^{^2}$ Section 6.4.1.2

ConfigurationParameters(MemoryArea, boolean, int, int, long[])

Creates a parameter object for initializing the state of a Schedulable³. The parameters provide the data for this initialization. For RealtimeThread⁴ and bound versions of AbstractAsyncEventHandler⁵, the stack and message buffers can be set exactly, but for the unbound event handlers, the system cannot give any guarentees to allow thread sharing.

Signature

public

ConfigurationParameters(MemoryArea area, boolean mayUseHeap, int messageLengt

throws IllegalStateException

Parameters 1

area Specifies the MemoryArea⁶ in which a thread should start or a handler should be executed. When null, the memory area will be that of the current Thread or Schedulable. The default is the current MemoryArea when set to @null or an instance of this class is not provided.

mayUseHeap indicates whether or not the schedulable may use the heap. The default is true when an instance of this class is not provided.

messageLength Memory space in bytes dedicated to the message associated with Schedulable⁷ objects created with these parameters' preallocated exceptions, plus references to the method names/identifiers in the stack trace. The value 0 indicates that no message should be stored. The value of -1 uses the system default and is the default when an instance of this class is not provided.

stackTraceLength Length of the stack trace buffer dedicated to Schedulable⁸ objects created with these parameters' preallocated exceptions, in frames. The amount of space this requires is implementation-specific. The value 0 indicates that no stack trace should be stored. The value of -1 uses the system default and is the default when an instance of this class is not provided.

 $^{^3}$ Section 6.4.1.2

⁴Section 5.3.2.2

⁵Section 8.4.3.2

⁶Section 11.4.2.3

⁷Section 6.4.1.2

⁸Section 6.4.1.2

sizes An array of implementation-specific values dictating memory parameters for Schedulable objects created with these parameters, such as maximum Java and native stack sizes. The sizes array will not be stored in the constructed object. The default is system dependent when set to null or an instance of this class is not provided.

Throws

IllegalStateException when mayUseHeap is false and area is an instance of HeapMemory⁹.

ConfigurationParameters(int, int, long[])

Same as ConfigurationParameters (MemoryArea, boolean, int, int, long[])¹⁰ with arguments {null, false, messageLength, stackTraceLength, sizes}.

Signature

```
public
```

ConfigurationParameters(int messageLength, int stackTraceLength, long[] sizes)

throws IllegalStateException

ConfigurationParameters(MemoryArea, boolean, int, int)

Same as ConfigurationParameters (MemoryArea, boolean, int, int, long[])¹¹ with arguments area, mayUseHeap, messageLength, stackTraceLength, null.

Signature

public

ConfigurationParameters (MemoryArea area, boolean mayUseHeap, int messageLength, in

⁹Section 11.4.2.1

 $^{^{10}}$ Section 5.3.2.1.1

¹¹Section 5.3.2.1.1

ConfigurationParameters(MemoryArea, int, int, long[])

Same as ConfigurationParameters (MemoryArea, boolean, int, int, long[])¹² with arguments area, true, messageLength, stackTraceLength, null.

Signature

public

 ${\tt Configuration Parameters} ({\tt Memory Area\ area,\ int\ message Length,\ int\ stack Trace Le$

ConfigurationParameters(MemoryArea, boolean)

Same as ConfigurationParameters (MemoryArea, boolean, int, int, long []) 13 with arguments area, true, -1, -1, null.

Signature

public

ConfigurationParameters(MemoryArea area, boolean mayUseHeap)

Configuration Parameters (Memory Area)

Same as ConfigurationParameters (MemoryArea, boolean, int, int, long[]) 14 with arguments area, true, -1, -1, null.

Signature

public

ConfigurationParameters(MemoryArea area)

¹²Section 5.3.2.1.1

¹³Section 5.3.2.1.1

¹⁴Section 5.3.2.1.1

ConfigurationParameters(long[])

```
Same as ConfigurationParameters (MemoryArea, boolean, int, int, long []) ^{15} with arguments HeapMemory.instance(), true, -1, -1, sizes.
```

Signature

```
public
  ConfigurationParameters(long[] sizes)
```

5.3.2.1.2 Methods

getMemoryArea

Gets the initial memory area specified.

```
public
    javax.realtime.MemoryArea getMemoryArea()
Returns
    the initial memory area, when one is set; otherwise null.
```

mayUseHeap

Find out if heap access is set.

```
Signature

public
boolean mayUseHeap()

Returns

true when the heap may be accessed.
```

2.0 (Draft 20)

¹⁵Section 5.3.2.1.1

getMessageLength

Gets the memory space in bytes dedicated to the message associated with Schedulable¹⁶ objects created with these parameters' preallocated exceptions, plus references to the method names/identifiers in the stack trace. The value 0 indicates that no message will be stored.

```
Signature

public

int getMessageLength()

Returns

Reserved memory size in bytes.
```

getStackTraceLength

Gets the length of the stack trace buffer dedicated to Schedulable¹⁷ objects created with these parameters' preallocated exceptions, in frames. The amount of space this requires is implementation-specific. The value 0 indicates that no stack trace will be stored.

```
Signature

public

int getStackTraceLength()

Returns
```

Reserved memory size in implementation-dependent stack frames.

getSizes

Gets the array of implementation-specific sizes associated with Schedulable¹⁸ objects created with these parameters. This method may allocate memory.

```
Signature

public
long[] getSizes()

16Section 6.4.1.2
17Section 6.4.1.2
18Section 6.4.1.2
```

Returns

Array of implementation-specific sizes.

5.3.2.2 RealtimeThread

Class RealtimeThread extends Thread and adds access to realtime services such as asynchronous transfer of control, nonheap memory, and advanced scheduler services.

As with java.lang.Thread, there are two ways to create a usable Realtime-Thread.

- Create a new class that extends RealtimeThread and override the run() method with the logic for the thread.
- Create an instance of RealtimeThread using one of the constructors with a logic parameter. Pass a Runnable object whose run() method implements the logic of the thread.

Inheritance

```
java.lang.Object
    java.lang.Thread
    javax.realtime.RealtimeThread

Interfaces
BoundSchedulable
AsyncTimable
```

5.3.2.2.1 Constructors

RealtimeThread(SchedulingParameters, ReleaseParameters, MemoryParameters, ConfigurationParameters, ProcessingGroup-Parameters, TimeDispatcher, ThreadGroup, Runnable)

Create a realtime thread with the given characteristics and a specified Runnable. The thread group of the new thread is inherited from its creator unless the newly-created realtime thread is allocated in scoped memory, then its thread group is (effectively) null.

The newly-created realtime thread is associated with the scheduler in effect during execution of the constructor.

The newly-created realtime thread inherits the affinity of its creator unless it was created by a Java thread or an unbound asynchronous event handler. In these cases,

the affinity is that which is returned from Affinity.getHeapDefault()¹⁹. When the newly-created realtime thread has ProcessingGroupParameters²⁰ and the intersection of the group's affinity and the newly-created realtime thread's affinity (as specified above) is null, then the newly-created realtime thread's affinity is set to that which is returned by Affinity.getProcessingGroupDefault²¹.

Available since RTSJ 2.0

Signature

public

RealtimeThread(SchedulingParameters scheduling, ReleaseParameters release, Me

Parameters 1

scheduling The SchedulingParameters²² associated with this (And possibly other instances of Schedulable²³). When scheduling is null and the creator is a schedulable, SchedulingParameters²⁴ is a clone of the creator's value created in the same memory area as this. When scheduling is null and the creator is a Java thread, the contents and type of the new SchedulingParameters object is governed by the associated scheduler.

release The ReleaseParameters²⁵ associated with this (and possibly other instances of Schedulable²⁶). When release is null the new RealtimeThread will use a clone of the default ReleaseParameters for the associated scheduler created in the memory area that contains the RealtimeThread object.

memory The MemoryParameters²⁷ associated with this (and possibly other instances of Schedulable²⁸). When memory is null, the new RealtimeThread receives null value for its memory parameters, and the amount or rate of memory allocation for the new thread is unrestricted.

pgp The ProcessingGroupParameters²⁹ associated with this (and possibly

```
<sup>19</sup>Section ??

<sup>20</sup>Section 15.3.3.6

<sup>21</sup>Section ??

<sup>22</sup>Section 6.4.2.13

<sup>23</sup>Section 6.4.1.2

<sup>24</sup>Section 6.4.2.13

<sup>25</sup>Section 6.4.2.9

<sup>26</sup>Section 6.4.1.2

<sup>27</sup>Section 11.4.2.4

<sup>28</sup>Section 6.4.1.2

<sup>29</sup>Section 15.3.3.6
```

other instances of Schedulable³⁰). When null, the new RealtimeThread will not be associated with any processing group.

sizing The ConfigurationParameters³¹ associated with this (and possibly other instances of Schedulable³². When sizing is null, this Realtime-Thread will reserve no space for preallocated exceptions and implementation-specific values will be set to their implementation-defined defaults.

dispatcher The TimeDispatcher³³ to use for realtime sleep and determining the period of a periodic thread.

group The ThreadGroup of the newly created realtime thread.

logic The Runnable object whose run() method will serve as the logic for the new RealtimeThread. When logic is null, the run() method in the new object will serve as its logic.

Throws

IllegalArgumentException when the parameters are not compatible with the associated scheduler.

IllegalAssignmentError when the new RealtimeThread instance cannot hold a reference to any of the values of scheduling release memory or group, when those parameters cannot hold a reference to the new RealtimeThread, when the new RealtimeThread instance cannot hold a reference to the values of area or logic, when the initial memory area is not specified and the new RealtimeThread instance cannot hold a reference to the default initial memory area, and when the thread may not use the heap, as specified by its configuration, and any of the following is true:

- the initial memory are is not specified,
- the initial memory is heap memory,
- the initial memory area, scheduling release, memory, or group is allocated in heap memory.
- when this is in heap memory, or
- logic is in heap memory.

RealtimeThread(SchedulingParameters, ReleaseParameters, MemoryParameters, ConfigurationParameters, ProcessingGroup-Parameters, Runnable)

Create a realtime thread with the given SchedulingParameters³⁴, ReleasePar-

 $^{^{30}}$ Section 6.4.1.2

 $^{^{31}}$ Section 5.3.2.1

³²Section 6.4.1.2

³³Section 10.4.2.4

 $^{^{34}}$ Section 6.4.2.13

ameters³⁵, MemoryParameters³⁶, MemoryArea³⁷ ProcessingGroupParameters³⁸, ConfigurationParameters³⁹, a specified Runnable, and default values for all other parameters.

This constructor is equivalent to RealtimeThread(scheduling, release, memory, configuration, group, null, null, logic).

Available since RTSJ 2.0 Create a realtime thread with the given characteristics and a specified Runnable. The thread group of the new thread is inherited from its creator unless the newly-created realtime thread is allocated in scoped memory, then its thread group is (effectively) null.

Signature

public

RealtimeThread(SchedulingParameters scheduling, ReleaseParameters release, Me

RealtimeThread(SchedulingParameters, ReleaseParameters, ConfigurationParameters, Runnable)

Create a realtime thread with the given SchedulingParameters⁴⁰, ReleaseParameters⁴¹, MemoryArea⁴² and a specified Runnable and default values for all other parameters.

This constructor is equivalent to RealtimeThread(scheduling, release, configuration, null, null, logic).

Available since RTSJ 2.0

Signature

public

RealtimeThread(SchedulingParameters scheduling, ReleaseParameters release, Co

 $^{^{35}}$ Section 6.4.2.9

 $^{^{36}}$ Section 11.4.2.4

 $^{^{37}}$ Section 11.4.2.3

 $^{^{38}\}mathrm{Section}\ 15.3.3.6$

³⁹Section 5.3.2.1

⁴⁰Section 6.4.2.13

⁴¹Section 6.4.2.9

⁴²Section 11.4.2.3

RealtimeThread(SchedulingParameters, ReleaseParameters, ConfigurationParameters)

Create a realtime thread with the given SchedulingParameters⁴³, ReleaseParameters⁴⁴ and MemoryArea⁴⁵ and default values for all other parameters.

This constructor is equivalent to RealtimeThread(scheduling, release, null, area, null, null, null, null).

Available since RTSJ 2.0

Signature

public

RealtimeThread(SchedulingParameters scheduling, ReleaseParameters release, Configu

$\label{lem:RealtimeThread} RealtimeThread(SchedulingParameters, \, ReleaseParameters, \, Runnable)$

Create a realtime thread with the given $SchedulingParameters^{46}$, $ReleaseParameters^{47}$ and a specified Runnable and default values for all other parameters.

This constructor is equivalent to RealtimeThread(scheduling, release, null, null, null, null, logic).

Available since RTSJ 2.0

Signature

public

RealtimeThread(SchedulingParameters scheduling, ReleaseParameters release, Runnabl

 $^{^{43}}$ Section 6.4.2.13

 $^{^{44}}$ Section 6.4.2.9

⁴⁵Section 11.4.2.3

⁴⁶Section 6.4.2.13

 $^{^{47}}$ Section 6.4.2.9

RealtimeThread(SchedulingParameters, ReleaseParameters, MemoryParameters, MemoryArea, ProcessingGroupParameters, Runnable)

Create a realtime thread with the given characteristics and a Runnable. This is equivalent to RealtimeThread(scheduling, release, memory, new ConfigurationParameters(area), group, null, null, logic).

Signature

public

RealtimeThread(SchedulingParameters scheduling, ReleaseParameters release, Me

RealtimeThread(SchedulingParameters, ReleaseParameters)

Create a realtime thread with the given SchedulingParameters⁴⁸ and Release-Parameters⁴⁹ and default values for all other parameters.

This constructor is equivalent to RealtimeThread(scheduling, release, null, null, null, null, null).

Signature

public

RealtimeThread(SchedulingParameters scheduling, ReleaseParameters release)

RealtimeThread(SchedulingParameters, TimeDispatcher)

Create a realtime thread with the given SchedulingParameters⁵⁰ and TimeDispatcher⁵¹ and default values for all other parameters. This constructor is equivalent to RealtimeThread(scheduling, null, null, null, null, null, null).

 $^{^{48}\}mathrm{Section}\ 6.4.2.13$

⁴⁹Section 6.4.2.9

⁵⁰Section 6.4.2.13

⁵¹Section 10.4.2.4

Available since RTSJ 2.0

```
Signature
```

```
public
```

RealtimeThread(SchedulingParameters scheduling, TimeDispatcher dispatcher)

RealtimeThread(SchedulingParameters)

Create a realtime thread with the given SchedulingParameters⁵² and default values for all other parameters. This constructor is equivalent to RealtimeThread(scheduling, null, null, null, null, null).

Signature

```
public
```

RealtimeThread(SchedulingParameters scheduling)

RealtimeThread

Create a realtime thread with default values for all parameters. This constructor is equivalent to RealtimeThread(null, null, null, null, null, null, null).

Signature

```
public
  RealtimeThread()
```

5.3.2.2.2 Methods

⁵²Section 6.4.2.13

currentRealtimeThread

Gets a reference to the current instance of RealtimeThread.

It is permissible to call currentRealtimeThread when control is in an Async-EventHandler⁵³. The method will return a reference to the RealtimeThread supporting that release of the async event handler.

```
Signature
```

```
public static
javax.realtime.RealtimeThread currentRealtimeThread()
throws ClassCastException
```

Throws

 ${\it Class Cast Exception} \ {\rm when} \ {\rm the \ current} \ {\rm execution} \ {\rm context} \ {\rm is} \ {\rm that} \ {\rm of} \ {\rm a} \ {\rm Java \ thread}.$ ${\it Returns}$

A reference to the current instance of RealtimeThread.

getCurrentMemoryArea

Return a reference to the MemoryArea⁵⁴ object representing the current allocation context.

When this method is invoked from a Java thread it will return that thread's current memory area (heap or immortal memory).

```
Signature
```

```
public static
javax.realtime.MemoryArea getCurrentMemoryArea()
```

Returns

A reference to the ${\tt MemoryArea}^{55}$ object representing the current allocation context.

${\tt getInitialMemoryAreaIndex}$

Gets the position of the initial memory area for the current Schedulable⁵⁶ in the memory area stack. Memory area stacks may include inherited stacks from

 $^{^{53}}$ Section 8.4.3.5

⁵⁴Section 11.4.2.3

⁵⁵Section 11.4.2.3

 $^{^{56}}$ Section 6.4.1.2

parent threads. The initial memory area of a RealtimeThread⁵⁷ or an Abstract-AsyncEventHandler⁵⁸ is the memory area specified in its constructor. The index of the initial memory area in the initial memory area stack is a fixed property of a Schedulable.

When the current memory area stack of the current realtime thread is not the original stack and the memory area at the initial memory area index is not the initial memory area, then IllegalStateException is thrown.

Signature

```
public static
int getInitialMemoryAreaIndex()
throws IllegalStateException, ClassCastException
```

Throws

IllegalStateException when the memory area stack of the current Realtime—Thread has changed from its initial configuration and the memory area at the originally specified initial memory area index is not the initial memory area.

ClassCastException when the current execution context is that of a Java thread.

Returns

The index into the initial memory area stack of the initial memory area of the current RealtimeThread.

getMemoryAreaStackDepth

Gets the size of the stack of MemoryArea⁵⁹ instances to which the current schedulable has access.

Note: The current memory area (getCurrentMemoryArea()⁶⁰) is found at memory area stack index of getMemoryAreaStackDepth() - 1.

Signature

```
public static
int getMemoryAreaStackDepth()
throws ClassCastException
```

Throws

ClassCastException when the current execution context is that of a Java thread.

Returns

```
<sup>57</sup>Section 5.3.2.2

<sup>58</sup>Section 8.4.3.2

<sup>59</sup>Section 11.4.2.3

<sup>60</sup>Section 5.3.2.2.2
```

The size of the stack of MemoryArea⁶¹ instances.

getOuterMemoryArea(int)

Gets the instance of MemoryArea⁶² in the memory area stack at the index given. When the given index does not exist in the memory area scope stack then null is returned.

Note: The current memory area (getCurrentMemoryArea()⁶³) is found at memory area stack index getMemoryAreaStackDepth() - 1, so getCurrentMemoryArea() == getOutMemoryArea(getMemoryAreaStackDepth() - 1).

Signature

```
public static
javax.realtime.MemoryArea getOuterMemoryArea(int index)
throws ClassCastException, MemoryAccessError
```

Parameters

index The offset into the memory area stack.

Throws

ClassCastException when the current execution context is that of a Java thread. MemoryAccessError when the memory area is allocate in heap memory and the caller is a schedulable that may not use the heap.

Returns

The instance of MemoryArea⁶⁴ at index or null when the given value does not correspond to a position in the stack.

sleep(javax.realtime.HighResolutionTime<?>)

A sleep method that is controlled by a generalized clock. Since the time is expressed as a HighResolutionTime⁶⁵, this method is an accurate timer with nanosecond granularity. The actual resolution available for the clock and even the quantity it measures depends on clock. The time base is the given Clock⁶⁶. The sleep time may be relative or absolute. When relative, then the calling thread is blocked for the amount of time given by time, and measured by clock. When absolute, then

```
61 Section 11.4.2.3

62 Section 11.4.2.3

63 Section 5.3.2.2.2

64 Section 11.4.2.3

65 Section 9.4.1.2

66 Section 10.4.2.1
```

the calling thread is blocked until the indicated value is reached by clock. When the given absolute time is less than or equal to the current value of clock, the call to sleep returns immediately.

It is permissible to call sleep when control is in an AsyncEventHandler⁶⁷. The method cause the handler to sleep.

This method must not throw IllegalAssignmentError. It must tolerate time instances that may not be stored in this.

Signature

```
public static
void sleep(javax.realtime.HighResolutionTime<?> time)
throws InterruptedException, ClassCastException,
IllegalArgumentException
```

Parameters

time The amount of time to sleep or the point in time at which to awaken.

Throws

InterruptedException when the thread is interrupted by interrupt()⁶⁸ or AsynchronouslyInterruptedException.fire()⁶⁹ during the time between calling this method and returning from it.

ClassCastException when the current execution context is that of a Java thread. IllegalArgumentException when time is null, or when time is a relative time less than zero.

waitForNextRelease

Causes the current realtime thread to delay until the next release. (See release()⁷⁰.) Used by threads that have a reference to either periodic or aperiodic ReleaseParameters⁷¹. The first release starts when this thread is released as a consequence of the action of one of the start()⁷² family of methods. Each time this method is called it will block until the next release unless the thread is in a deadline miss condition. In that case, the operation of waitForNextRelease is controlled by this thread's scheduler. (See PriorityScheduler⁷³.)

```
<sup>67</sup>Section 8.4.3.5

<sup>68</sup>Section 5.3.2.2.2

<sup>69</sup>Section 8.4.2.1.2

<sup>70</sup>Section 5.3.2.2.2

<sup>71</sup>Section 6.4.2.9

<sup>72</sup>Section 5.3.2.2.2

<sup>73</sup>Section 6.4.2.7
```

Available since RTSJ 2.0

```
Signature

public static
boolean waitForNextRelease()
throws IllegalThreadStateException, ClassCastException
Throws
```

IllegalThreadStateException when this does not have a reference to a ReleaseParameters⁷⁴ type of either PeriodicParameters⁷⁵ or AperiodicParameters⁷⁶.

ClassCastException when the current thread is not an instance of Realtime-Thread.

Returns

Either false when the thread is in a deadline miss condition or true otherwise. When a deadline miss condition occurs is defined by its thread's scheduler.

wait For Next Release Interruptible

Causes the current realtime thread to delay until the next release. (See re-lease()⁷⁷.) Used by threads that have a reference to aperiodic ReleaseParameters⁷⁸. The first release starts when this thread is released as a consequence of the action of one of the start()⁷⁹ family of methods. Each time it is called this method will block until the next release unless the thread is in a deadline miss condition. In that case the operation of waitForNextRelease is controlled by this thread's scheduler. (See PriorityScheduler⁸⁰.)

Available since RTSJ 2.0

```
Signature
public static
boolean waitForNextReleaseInterruptible()

74Section 6.4.2.9
75Section 6.4.2.5
76Section 6.4.2.2
77Section 5.3.2.2.2
78Section 6.4.2.9
79Section 5.3.2.2.2
80Section 6.4.2.7
```

throws IllegalThreadStateException, InterruptedException, ClassCastException

Throws

InterruptedException when interrupted.

IllegalThreadStateException when this does not have a reference to a ReleaseParameters⁸¹ type of AperiodicParameters⁸².

ClassCastException when the current thread is not an instance of Realtime-Thread.

Returns

Either false when the thread is in a deadline miss condition or true otherwise. When a deadline miss condition occurs is defined by its thread's scheduler.

release

Generate a release for this RealtimeThread. The action of this release is governed by the schedule. It may, for instance, act immediately, or be queued, delayed, or discarded.

Available since RTSJ 2.0

```
Signature

public

void release()
```

Throws

IllegalThreadStateException when this does not have a reference to a ReleaseParameters⁸³ type of AperiodicParameters⁸⁴.

deschedule

When the ReleaseParameters⁸⁵ object associated with this RealtimeThread is an instance of is AperiodicParameters⁸⁶, perform any *deschedule* actions specified

```
81 Section 6.4.2.9

82 Section 6.4.2.2

83 Section 6.4.2.9

84 Section 6.4.2.2

85 Section 6.4.2.9

86 Section 6.4.2.2
```

by this thread's scheduler. When the type of the associated instance of Release-Parameters⁸⁷ is not AperiodicParameters⁸⁸ nothing happens.

Available since RTSJ 2.0

```
Signature

public

void deschedule()
```

getMemoryArea

Return the initial memory area for this RealtimeThread. When not specified through the constructor, the default is a *reference* to the current allocation context when this was constructed.

Available since RTSJ 1.0.1

```
Signature

public
 javax.realtime.MemoryArea getMemoryArea()

Returns

A reference to the initial memory area for this thread.
```

getMemoryParameters

@inheritDoc

```
Signature

public
javax.realtime.MemoryParameters getMemoryParameters()

Returns
@inheritDoc

87 Section 6.4.2.9
88 Section 6.4.2.2
```

getProcessingGroup

@inheritDoc

```
Signature

public

javax.realtime.ProcessingGroup getProcessingGroup()

Returns

@inheritDoc
```

getProcessingGroupParameters

@inheritDoc

```
Signature

public
 javax.realtime.ProcessingGroupParameters
 getProcessingGroupParameters()

Returns

@inheritDoc
```

getConfigurationParameters

@inheritDoc

```
Signature

public
 javax.realtime.ConfigurationParameters
 getConfigurationParameters()

Returns

@inheritDoc
```

${\bf get Release Parameters}$

@inheritDoc

```
public javax.realtime.ReleaseParameters getReleaseParameters()

Returns
@inheritDoc

getScheduler
@inheritDoc

Signature public javax.realtime.Scheduler getScheduler()

Returns
@inheritDoc

getSchedulingParameters

@inheritDoc

Signature
```

@inheritDoc

interrupt

Returns

public

Extends the function of Thread.interrupt(), generates the generic AsynchronouslyInterruptedException and targets it at this, and sets the interrupted state to pending. (See AsynchronouslyInterruptedException⁸⁹.

javax.realtime.SchedulingParameters getSchedulingParameters()

The semantics of Thread.interrupt() are preserved.

```
Signature

public
void interrupt()

89 Section 8.4.2.1
```

schedule

Begin unblocking RealtimeThread.waitForNextRelease⁹⁰ for an periodic thread. When deadline miss detection is disabled, enable it. Typically used when an aperiodic schedulable is in a deadline miss condition.

The details of the interaction of this method with deschedule⁹¹, waitForNex-tRelease⁹² and release⁹³ are dictated by this thread's scheduler. When this Real-timeThread does not have a type of AperiodicParameters⁹⁴ as its ReleaseParameters⁹⁵ nothing happens.

Available since RTSJ 2.0

```
Signature

public

void schedule()
```

setMemoryParameters(MemoryParameters)

@inheritDoc

```
Signature

public
void setMemoryParameters (MemoryParameters memory)

Parameters

memory @inheritDoc

Throws

IllegalArgumentException @inheritDoc
IllegalAssignmentError @inheritDoc
IllegalThreadStateException @inheritDoc
```

setProcessingGroupParameters(ProcessingGroupParameters)

```
90 Section 5.3.2.2.2

91 Section 5.3.2.2.2

92 Section 5.3.2.2.2

93 Section 5.3.2.2.2

94 Section 6.4.2.2

95 Section 6.4.2.9
```

```
@inheritDoc
Signature
    public
    void setProcessingGroupParameters(ProcessingGroupParameters
Parameters 1  
    group @inheritDoc
Throws
    IllegalArgumentException @inheritDoc
    IllegalAssignmentError @inheritDoc
    IllegalThreadStateException @inheritDoc
setReleaseParameters(ReleaseParameters)
  @inheritDoc
Signature
    void setReleaseParameters(ReleaseParameters release)
release @inheritDoc
Throws
    IllegalArgumentException @inheritDoc
    IllegalAssignmentError @inheritDoc
     IllegalThreadStateException @inheritDoc
setScheduler(Scheduler)
  @inheritDoc
Signature
    void setScheduler(Scheduler scheduler)
scheduler @inheritDoc
```

2.0 (Draft 20)

Throws

 $\label{legalArgumentException} $$ \mbox{ @inheritDoc} $$ IllegalAssignmentError @inheritDoc $$ SecurityException @inheritDoc $$ IllegalThreadStateException @inheritDoc $$ \mbox{ @inheritDoc} $$ $$ \mbox{ } $$$

setScheduler(Scheduler, SchedulingParameters, ReleaseParameters, MemoryParameters, ProcessingGroupParameters)

@inheritDoc

Signature

public
void setScheduler(Scheduler scheduler, SchedulingParameters
scheduling, ReleaseParameters release, MemoryParameters
memoryParameters, ProcessingGroupParameters group)

Parameters

scheduler @inheritDoc scheduling @inheritDoc release @inheritDoc memoryParameters @inheritDoc group @inheritDoc

Throws

IllegalArgumentException @inheritDoc IllegalAssignmentError @inheritDoc IllegalThreadStateException @inheritDoc SecurityException @inheritDoc

setSchedulingParameters(SchedulingParameters)

@inheritDoc

Signature

 $\begin{array}{c} \text{public} \\ \text{void setSchedulingParameters(SchedulingParameters scheduling)} \\ Parameters \\ scheduling @inheritDoc \end{array}$

2.0 (Draft 20)

Throws

$$\label{legalArgumentException} \begin{split} IllegalArgumentException & @inheritDoc \\ IllegalAssignmentError & @inheritDoc \\ IllegalThreadStateException & @inheritDoc \\ \end{split}$$

startPeriodic(PhasingPolicy)

Start the thread with the specified phasing policy.

Available since RTSJ 2.0

Signature

```
public
void startPeriodic(PhasingPolicy phasingPolicy)
throws LateStartException
```

Parameters

phasingPolicy The phasing policy to be applied when the start time given in the realtime thread's associated PeriodicParameters⁹⁶ is in the past.

Throws

javax.realtime.LateStartException when the actual start time is after the assigned start time and the phasing policy is PhasingPolicy.STRICT_PHASING⁹⁷. IllegalArgumentException when the thread is not periodic, or when its start time is not absolute.

start

Set up the realtime thread's environment and start it. The set up might include delaying it until the assigned start time and initializing the thread's scope stack. (See ScopedMemory⁹⁸.)

Signature

```
public
void start()
```

⁹⁶Section 6.4.2.5 ⁹⁷Section 5.3.1.1.1

⁹⁸Section 11.4.2.5

getLastReleaseTime

```
Equivalent to getLastReleaseTime(null)

Available since RTSJ 2.0
```

```
Signature
    public
    javax.realtime.AbsoluteTime getLastReleaseTime()
```

getLastReleaseTime(AbsoluteTime)

Return the absolute time of this thread's last release, whether periodic or aperiodic.

The clock in the returned absolute time shall be the realtime clock for aperiodic releases and the clock used for the periodic release for periodic releases.

Available since RTSJ 2.0

```
Signature
    public
    javax.realtime.AbsoluteTime getLastReleaseTime(AbsoluteTime dest)
Returns
```

the last release time in dest. When dest is null, create a new absolute time instance in the current memory area.

getEffectiveStartTime

```
Equivalent to getEffectiveStartTime(null). Available since RTSJ 2.0
```

```
Signature

public
 javax.realtime.AbsoluteTime getEffectiveStartTime()

2.0 (Draft 20)
```

getEffectiveStartTime(AbsoluteTime)

Return the effective start time of this realtime thread. This is not necessarily the same as the start time in the release parameters.

- When the release parameters' start time is relative, the effective start time is the time of the first release.
- When the release parameters' start time is an absolute time after start() is invoked, the effective start time is the same as the release parameters' start time.
- When the release parameters' start time is an absolute time before start() is invoked, the effective start time depends on the phasing policy.

The default is to set the effective start time equal to the time start() is invoked.

Available since RTSJ 2.0

```
Signature
    public
    javax.realtime.AbsoluteTime getEffectiveStartTime(AbsoluteTime
    dogt)
```

Returns

The effective start time in dest. When dest is null, return the effective start time in an AbsoluteTime⁹⁹ instance created in the current memory area.

getCurrentConsumption(RelativeTime)

Available since RTSJ 2.0

```
Signature
    public static
    javax.realtime.RelativeTime getCurrentConsumption(RelativeTime
    dest)
```

Throws

IllegalStateException when the caller is not a RealtimeThread¹⁰⁰.

Returns

```
<sup>99</sup>Section 9.4.1.1

<sup>100</sup>Section 5.3.2.2
```

The CPU consumption for this release. When dest is null, return the CPU consumption in a RelativeTime¹⁰¹ instance created in the current execution context. When dest is not null, return the CPU consumption in dest

getCurrentConsumption

Equivalent to getCurrentConsumption(null). Available since RTSJ 2.0

```
Signature
```

```
public static
javax.realtime.RelativeTime getCurrentConsumption()
```

getMinConsumption(RelativeTime)

Get the minimum CPU consumption measured for any completed release of this thread.

Available since RTSJ 2.0

Signature

public

javax.realtime.RelativeTime getMinConsumption(RelativeTime dest)

Returns

the minimum CPU consumption in dest. When dest is null return the minimum CPU consumption in a RelativeTime¹⁰² instance created in the current memory area.

${\bf get Min Consumption}$

Equivalent to getMinConsumption(null).

Available since RTSJ 2.0

 $^{^{101}\}mathrm{Section}~9.4.1.3$

 $^{^{102}\}mathrm{Section}~9.4.1.3$

```
Signature
```

```
public
javax.realtime.RelativeTime getMinConsumption()
```

getMaxConsumption(RelativeTime)

Get the maximum CPU consumption measured for any completed release of this thread.

Available since RTSJ 2.0

```
Signature
```

```
public
  javax.realtime.RelativeTime getMaxConsumption(RelativeTime dest)
```

the maximum CPU consumption in dest. When dest is null return the maximum CPU consumption in a RelativeTime¹⁰³ instance created in the current memory area.

getMaxConsumption

Equivalent to getMaxConsumption(null).

Available since RTSJ 2.0

```
Signature
```

```
public
javax.realtime.RelativeTime getMaxConsumption()
```

getDispatcher

Get the dispatcher responsible for handling sleep requests issued by this thread See Section AsyncTimable.getDispatcher()

Available since RTSJ 2.0

¹⁰³Section 9.4.1.3

```
Signature
    public
    javax.realtime.TimeDispatcher getDispatcher()
```

fire

Used by the $\{\# link\ Clock\}$ infrastructure to cause a call to waitForNextRelease 104 to return.

See Section AsyncTimable.fire()

Available since RTSJ 2.0

```
Signature

public final

void fire()
```

mayUseHeap

Determine whether or not this schedulable may use the heap.

Available since RTSJ 2.0

```
Signature public boolean mayUseHeap()
```

Returns

true only when this Schedulable may allocate on the heap and may enter the Heap.

awaken

Used by the {#link Clock} infrastructure to cause a call to sleep¹⁰⁵ to return.

¹⁰⁴Section 5.3.2.2.2 ¹⁰⁵Section 5.3.2.2.2

5 Realtime Threads 77

See Section Schedulable.awaken()

Available since RTSJ 2.0

Signature

public final

void awaken()

5.4 Rationale

The RTSJ platform's priority-preemptive dispatching model is very similar to the dispatching model found in the majority of commercial realtime operating systems. However, the dispatching semantics were purposefully relaxed in order to allow execution on a wide variety of operating systems. Thus, it is appropriate to specify realtime threads by extending java.lang.Thread.

The ReleaseParameters and MemoryParameters provided to the Realtime-Thread constructor allow for a number of common realtime thread types, including periodic threads.

The ConfigurationParameters class is provided with a no-heap option in order to allow time-critical schedulables to execute in preference to the garbage collector given appropriate assignment of execution eligibility. The memory access and assignment semantics of these no-heap schedulables are designed to guarantee that the execution of such threads does not lead to an inconsistent heap state.

78 5.4 Rationale

Chapter 6

Scheduling

6.1 Overview

Scheduling is a key differenciator between a conventional Java implementation and a realtime Java implementation. Whereas conventional Java implementations relies on some sort of fair scheduling, a realtime Java implementation must provide a realtime scheduler. In a realtime scheduler, ensuring that important task finish on time is more important than overall throughput or fairness.

The scheduler required by this specification is fixed-priority preemptive with at least 28 unique priority levels. It is represented by the class FirstInFirstOutScheduler, a subclass of PriorityScheduler, and is called the *base scheduler*. As the name implies, this scheduler does not time-slice threads at a given priority, but rather runs each to completion, so long as no higher priority thread become ready to run. In that case, the current thread is preempted by the higher priority thread.

The schedulables required by this specification are denoted by the Schedulable interface and include the classes RealtimeThread, AsyncEventHandler, and AsyncLongEventHandler. AsyncObjectEventHandler, and BoundAsyncEventHandler. The base scheduler assigns processor resources according to the schedulables' release characteristics, execution eligibility, affinity, and processing group values. Subclasses of these schedulables are also schedulables and behave as these required classes.

The scheduler dispatches a schedulable, that is ready to run, on a CPU. Some systems, such as multicore systems, have more than one CPU to choose from. By default, a ready schedulable would be dispatched on the next available CPU; however, the specification provides an interface, Affinity to control, on which sets of CPUs a given schedulable may run.

An instance of the SchedulingParameters class contains values of execution eligibility. A schedulable is considered to have the execution eligibility represented by the SchedulingParameters object currently bound to it. For implementations

6.1 Overview

providing only the base scheduler, the scheduling parameters object is an instance of PriorityParameters (a subclass of SchedulingParameters).

An instance of the ReleaseParameters class or its subclasses, PeriodicParameters, AperiodicParameters, and SporadicParameters, contains values that define a particular release characteristic. A schedulable is considered to have the release characteristics of a single associated instance of the ReleaseParameters class.

For a realtime thread, the scheduler defines the behavior of the realtime thread's waitForNextRelease and waitForNextReleaseInterruptible methods. For all Schedulables, the scheduler monitors cost overrun and deadline miss conditions based on its release parameters. Release parameters also govern the treatment of the minimum interarrival time for sporadic schedulables.

The ThreadGroup class has special significance in an RTSJ implementation. As in conventional Java, the maximum priority of a thread is governed in part by its thread group, but the CPU affinity of a thread is also governed by its thread group along with the Affinity class. Furthermore, there are two important subclasses: SchedulingGroup and ProcessingGroup. These classes provide additional means of managing tasks.

An instance of the SchedulingGroup provides scheduling constraints for schedulables similar to how a TheadGroup does for convention Java threads. The scheduler and maximum SchedulingParameters can be set. In fact, a schedulable can only be created in an instance of SchedulingParameters or its subclass. Therefore the root thread group and the thread group of the initial thread must both be scheduling groups in an RTSJ implementation.

The ProcessingGroup class is a subclass of SchedulingGroup. An instance of the ProcessingGroup class contains values that define a temporal scope for a processing group. When a schedulable has an associated instance of the ProcessingGroup class, it is said to execute within the temporal scope defined by that instance. A single instance of the ProcessingGroup class can be, and typically is, associated with many schedulables. In an implementation that supports cost enforcement, the combined processor demand of all of the schedulables associated with an instance of the ProcessingGroup class must not exceed the values in that instance (i.e., the defined temporal scope). The processor demand is determined by the Scheduler.

The scheduling classes provide the necessary support for realtime scheduling. These classes

- enable the definition of schedulables,
- manage the assignment of execution eligibility to schedulable objects,
- manage the execution of instances of the AbstractAsyncEventHandler and RealtimeThread classes,
- assign release characteristics to schedulables,
- assign execution eligibility values to schedulables, and

6 Scheduling 81

• manage the execution of groups of schedulables that collectively exhibit additional release characteristics.

6.2 Definitions

Task is the name given a unit of independent execution. In conventional Java, this is a thread. The Schedulable interface marks realtime tasks. The classes that implement Schedulable are subject to the scheduling behavior of realtime schedulars. Instances of these classes are referred to as Schedulables (SO) and provide three execution states: executing, blocked, and eligible-for-execution.

- Executing refers to the state where the schedulable is currently running on a processor.
- Blocked refers to the state where the schedulable is not among those schedulables that could be selected to have their state changed to executing. The blocked state will have a reason associated with it, e.g., blocked-for-I/O-completion, blocked-for-release-event, or blocked-by-cost-overrun.
- Eligible-for-execution refers to the state where the schedulable could be selected to have its state changed to executing.

Each type of schedulable defines its own *release events*, for example, the release events for a periodic schedulable are caused by the passage of time and occur at programmatically specified intervals.

Release is the changing of the state of a schedulable from blocked-for-release-event to eligible-for-execution. When the state of a schedulable is blocked-for-release-event when a release event occurs then the state of the schedulable is changed to eligible-for-execution. Otherwise, a state transition from blocked-for-release-event to eligible-for-execution is queued; this is known as a pending release. When the next transition of the schedulable into state blocked-for-release-event occurs, and there is a pending release, the state of the schedulable is immediately changed to eligible-for-execution. (Some actions implicitly clear any pending releases.)

Completion is the changing of the state of a schedulable from executing to blockedfor-release-event. Each completion corresponds to a release. A realtime thread is deemed to complete its most recent release when it terminates.

Deadline refers to a time before which a schedulable expects to complete. The i^{th} deadline is associated with the i^{th} release event and a deadline miss occurs when the i^{th} completion would occur after the i^{th} deadline.

Deadline monitoring is the process by which the implementation responds to deadline misses. When a deadline miss occurs for a schedulable object, the deadline miss handler, if any, for that schedulable is released. This behaves as if there were an asynchronous event associated with the schedulable, to which the miss handler was bound, and which was fired when the deadline miss occurred.

82 6.2 Definitions

Periodic, sporadic, and aperiodic are adjectives applied to schedulables which describe the temporal relationship between consecutive release events. Let R_i denote the time at which a schedulable has had the i^{th} release event occur. Ignoring the effect of release jitter:

- a schedulable is periodic when there exists a value T > 0 such that for all i, $R_{i+1} R_i = T$, where T is called the period;
- a schedulable that is not periodic is said to be aperiodic; and
- an aperiodic schedulable is said to be sporadic when there is a known value T > 0 such that for all i, $R_{i+1} R_i >= T$. T is then called the minimum interarrival time (MIT).

The *cost* of a schedulable is an estimate of the maximum amount of CPU time that the schedulable requires between a release and its associated completion.

The *current CPU consumption* of a schedulable is the amount of CPU time that the schedulable has consumed since its last release.

A cost overrun occurs when the schedulable's current CPU consumption becomes greater than, or equal to, its cost.

Cost monitoring is the process by which the implementation tracks CPU consumption and responds to cost overruns. When a cost overrun occurs for a schedulable, the cost overrun handler, if any, for that schedulable is released. This behaves as if there were an asynchronous event associated with the schedulable, to which the overrun handler was bound, and which was fired when the cost overrun occurred.

Cost enforcement is the process by which the implementation ensures that the CPU consumption of a schedulable is no more than the value of the cost parameter in its associated ReleaseParameters. (Cost enforcement is an optional facility in an implementation of the RTSJ.)

The base priority of a schedulable is the priority given in its associated PriorityParameters object; the base priority of a Java thread is the priority returned by its getPriority method.

When it is not in the enforced state, the *active priority* of a schedulable or a Java thread is the maximum of its base priority and any priority it has acquired due to the action of priority inversion avoidance algorithms (see the *Synchronization Chapter*).

A processing group is a collection of schedulables whose combined execution has further execution time constraints which the scheduler uses to govern the group's execution eligibility.

A *scheduler* manages the execution of schedulables: it detects deadline misses and monitors costs. It also manages the execution of Java threads.

The base scheduler is an instance of the PriorityScheduler class as defined in this specification. This is the initial default scheduler.

6 Scheduling 83

The *round-robin scheduler* is an instance of the RoundRobinScheduler class as defined in this specification. It is specified to execute in tandem with the base scheduler in a predictable fashion.

A processor is a logical processing element that is capable of physically executing a single thread of control at any point in time. Hence, multicore platforms have multiple processors, platforms that support hyperthreading also have more than one processor. It is assumed that all processors are capable of executing the same instruction sets.

An *affinity* is a set of processors on which the global scheduling of a schedulable can be supported.

6.3 Semantics

Scheduling semantics determined which task run when. Bot *The Java Virtual Machine Specification*[6] and *The Java Language Specification*[5] are silent on the semantics for scheduling; only for semantics for synchronization is provided. Since scheduling is central to realtime programming, here is a detail semantic applicable across the classes defined below, along with definitions of the required scheduling algorithms. Semantics that apply to particular classes, constructors, methods, and fields can be found in the class description and the constructor, method, and field detail sections.

6.3.1 Schedulers

There are four basic requirements for schedulers.

- 1. A scheduler may only change the execution eligibility of the schedulables which it manages and only in accordance with its scheduling algorithm.
- 2. Each scheduler provided for application code by an RTSJ implementation must have documentation describing its semantics including at least the following: the algorithm used to determine eligibility, what schedulables may be scheduled by it, the subclasses of Scheduler and SchedulingParameters used to control the scheduler, and any other classes needed by the scheduler.
- 3. Every implementation must provide a round robin scheduler and a first in scheduler using priorities above the ten (1–10) conventional Java priorities as documented below.
- 4. Tasks with priorities a convention Java priority (1–10) should be scheduled such that when two or more threads run at the same priority, one thread cannot block another indefinitely and not violate the requirements dictated by java.lang.Thread.

84 6.3 Semantics

6.3.2 The Base Scheduler

The semantics for the base scheduler assume a uniprocessor or shared memory multiprocessor execution environment. Scheduling is priority preemptive with run to completion, also known as first-in-first-out (FIFO) semantics. The base scheduler supports the execution of all schedulables.

6.3.2.1 Priorities

The base scheduler is a priority scheduler with the following requirements.

- 1. The base scheduler must support at least 28 distinct values (realtime priorities) that can be stored in an instance of PriorityParameters in addition to the values 1 through 10 required to support the priorities defined by java.lang.Thread.
- 2. The realtime priority values must be greater than 10, and they must include all integers from the base scheduler's getMinPriority() value to its getMax-Priority() value inclusive.
- 3. Higher priority values in an instance of PriorityParameters have a higher execution eligibility.
- 4. The 10 priorities defined for java.lang.Thread must effectively have lower execution eligibility than the realtime priorities.
- 5. When the round-robin scheduler is present, the base scheduler must support at least one priority value numerically greater than the maximum allowable round-robin priority.
- 6. For realtime scheduling, the base priority of each Schedulable under the control of the base scheduler must be from the range of realtime priorities. A Schedulable with a priority in the java.lang.Thread range will be scheduled as if it where an instance of java.lang.Thread.
- 7. Assignment of any of the realtime priority values to any Schedulable controlled by the base priority scheduler is legal. It is the responsibility of application logic to make rational priority assignments.
- 8. The base scheduler does not use the importance value in the ImportanceParameters subclass of PriorityParameters.
- 9. Calling the java.lang.Thread.setPriority on a thread can only be used to set the thread's priority to a convention Java priority (1–10).
- 10. For schedulables managed by the base scheduler, the implementation must not change the execution eligibility for any reason other than
 - (a) the implementation of a priority inversion avoidance algorithm requires it or
 - (b) as a result of a program's request to change the priority parameters associated with one or more schedulables; e.g., by changing a value in a

6 Scheduling 85

scheduling parameter object that is used by one or more schedulables, or by using setSchedulingParameters() to give a schedulable a different SchedulingParameters value.

- 11. Use of Thread.setPriority(), any of the methods defined for schedulables, or any of the methods defined for parameter objects must not affect the correctness of the priority inversion avoidance algorithms controlled by PriorityCeilingEmulation and PriorityInheritance—see the *Synchronization* chapter.
- 12. When schedulable A managed by the base scheduler creates a Java thread, B, then the initial base priority of B is the minimum of the priority value returned by the getMaxPriority method of B's java.lang.ThreadGroup object and the priority of A.
- 13. PriorityScheduler.getNormPriority() shall be set to

```
1 ((PriorityScheduler.getMaxPriority() - 2 PriorityScheduler.getMinPriority()) / 3) + 3 PriorityScheduler.getMinPriority()
```

14. Hardware priorities, where supported, have values above the base scheduler (see Section 12.3.4).

6.3.2.2 Dispatching

The execution scheduling semantics described in this section are defined in terms of a conceptual model that contains a set of queues of schedulables that are eligible for execution. There is, conceptually, one queue for each priority on each processor. No implementation structures are necessarily implied by the use of this conceptual model. It is assumed that no time elapses during operations described using this model, and therefore no simultaneous operations are possible.

The RTSJ dispatching model specifies its dispatching rules for the default priority scheduler.

- 1. A Schedulable can become a running schedulable only when it is ready and one of the processors in its requested affinity is available.
- 2. When two schedulables have different active priorities and request the same processor, the schedulable with the higher active priority will always execute in preference to the schedulable with the lower value when both are eligible for execution.
- 3. Processors are allocated to schedulables based on each schedulable's active priority and their associated affinity.
- 4. Schedulable dispatching is the process by which one ready schedulable is selected for execution on a processor. This selection is done at certain points

86 6.3 Semantics

during the execution of a schedulable called schedulable dispatching points.

- 5. A schedulable reaches a schedulable dispatching point whenever it becomes blocked, when it terminates, or when a higher priority schedulable becomes ready for execution on its processor. That is, a schedulable that is executing will continue to execute until it either blocks, terminates or is preempted by a higher-priority schedulable.
- 6. The dispatching policy is specified in terms of ready queues and schedulable states. The ready queues are purely conceptual; there is no requirement that such lists physically exist in an implementation. A ready queue is an ordered list of ready schedulable objects. The first position in a queue is called the head of the queue, and the last position is called the tail of the queue.
- 7. A schedulable is ready when it is in a ready queue, or when it is running. Each processor has one ready queue for each priority value. At any instant, each ready queue of a processor contains exactly the set of schedulables of that priority that are ready for execution on that processor, but are not running on any processor; that is, those schedulables that are ready, are not running on any processor, and can be executed using that processor.
- 8. A schedulable can be on the ready queues of more than one processor.
- 9. Each processor has one running schedulable, which is the schedulable currently being executed by that processor. Whenever a schedulable running on a processor reaches a schedulable dispatching point, a new schedulable object is selected to run on that processor. The schedulable selected is the one at the head of the highest priority nonempty ready queue for that processor; this schedulable is then removed from all ready queues to which it belongs.
- 10. In a multiprocessor system, a schedulable can be on the ready queues of more than one processor. At the extreme, when several processors share the same set of ready schedulables, the contents of their ready queues are identical, and so they can be viewed as sharing one ready queue, and can be implemented that way. Thus, the dispatching model covers multiprocessors where dispatching is implemented using a single ready queue, as well as those with separate dispatching domains.
- 11. The dispatching mechanism must allow the preemption of the execution of schedulables and Java threads with a bounded delay at a point not governed by the preempted object. The bound on this delay may be implementation-defined, and could be the time to the next point in execution that the heap is in a consistent state or some similar restriction. The implementation should document this bound.
- 12. A schedulable that is preempted by a higher priority schedulable is placed in the queue for its active priority, at a position determined by the implementation. The implementation must document the algorithm used for such

6 Scheduling 87

placement. It is recommended that a preempted schedulable be placed at the front of the appropriate queue.

- 13. A realtime thread that performs a yield() is placed at the tail of the queues (dictated by its affinity) for its active priority level.
- 14. A blocked schedulable that becomes eligible for execution is added to the tail of the queues (dictated by its affinity) for that priority. This behavior also applies to the initial release of a schedulable.
- 15. For a schedulable whose active priority is raised as a result of explicitly setting its base priority (through the PriorityParameters setPriority() method, the RealtimeThread setSchedulingParameters() method, or Thread's setPriority() method), this schedulable is added to the tail of the queues (dictated by its affinity) for its new priority level; otherwise, it continues to run.
- 16. Queuing when priorities are adjusted by priority inversion avoidance algorithms is governed by semantics specified in the *Synchronization* chapter.

6.3.2.3 Parameter Values

The scheduler uses the values contained in the different parameter objects associated with a schedulable to control the behavior of the schedulable. The scheduler determines what values are valid for the schedulables it manages, which defaults apply and how changes to parameter values are acted upon by the scheduler. Invalid parameter values result in exceptions, as documented in the relevant classes and methods.

- 1. The default values for the base scheduler are as follows.
 - (a) Scheduling parameters are copied from the creating schedulable when possible; when the creating schedulable does not have scheduling parameters, the default is an instance of the default priority parameters value.
 - (b) Release parameters default to an instance of the default aperiodic parameters (see AperiodicParameters).
 - (c) Memory parameters default to null which signifies that memory allocation by the schedulable is not constrained by the scheduler.
 - (d) The default scheduling parameter values for parameter objects created by a schedulable controlled by the base scheduler are given by the following table (see PriorityScheduler).

Attribute	Default Value
Priority parameters	
priority	norm priority
Importance parameters	
importance	No default.
	A value must be supplied.

88 6.3 Semantics

2. All numeric or **RelativeTime** attributes in parameter values must be greater than or equal to zero.

- 3. Values of period must be greater than zero.
- 4. Deadline values in ReleaseParameters objects must be less than or equal to their period values (where applicable), but the deadline may be greater than the minimum interarrival time in a SporadicParameters object.
- 5. Changes to scheduling, release, memory, and processing group parameters (by methods on the schedulables bound to the parameters or by altering the parameter objects themselves) have the following effects.
 - (a) They potentially modify the behavior of the scheduler with regard to those schedulables. When such changes in behavior take effect depends on the parameter in question, and the type of schedulable, as described below.
- 6. When changes to a parameter type—scheduling, release, memory, and processing group—take effect depends on the parameter type.
 - (a) Changes to scheduling parameters take effect immediately except when constrained by priority inversion avoidance algorithms.
 - (b) Changes to release parameters depend on the parameter being changed, the type of release parameter object and the type of schedulable:
 - i. changes to the deadline and the deadline miss handler take effect at each release event as follows: when the i_{th} release event occurred at a time t_i , then the i^{th} deadline is the time $t_i + D_i$, where D_i is the value of the deadline stored in the schedulable's release parameters object at the time t_i . When a deadline miss occurs then it is the deadline miss handler that was installed in the schedulable's release parameters at time t_i that is released;
 - ii. changes to cost and the cost overrun handler take effect immediately;
 - iii. changes to the period and start time values in PeriodicParameters objects are described in "Release of realtime Threads" below;
 - iv. changes to the additional values in AperiodicParameters objects and SporadicParameters are described, respectively, in "Aperiodic Release Control" and "Sporadic Release Control", below; and
 - v. changes to the type of release parameters object generally take effect after completion, except as documented in the following sections.
 - (c) Changes to memory parameters take effect immediately.
 - (d) Changes to processing group parameters take effect as described in "Processing Groups" below.
 - (e) Changes to the scheduler responsible for a schedulable object take effect at completion.

6 Scheduling 89

6.3.2.4 Cost Monitoring and Cost Enforcement

The cost of a schedulable is defined by the value returned by invoking the getCost method of the schedulable's release parameters object. When a schedulable is initially released it's current CPU consumption is zero and as the schedulable executes, the current CPU consumption increases. For cost monitoring, an implementation must conform to the following requirements.

- 1. If, at any time, due to either execution of the schedulable or a change in the schedulable's cost, the current CPU consumption becomes greater than, or equal to, the current cost of the schedulable, then a cost overrun is triggered.
- 2. The implementation is required to document the granularity at which the current CPU consumption is updated.
- 3. When a cost overrun is triggered, the cost overrun handler associated with the Schedulable, if any, is released. No further action is taken.
- 4. The current CPU consumption is reset to zero when the schedulable is next released (i.e. it moves from the blocked-for-release-event state to the eligible-for-execution state).

When cost enforcement is supported, an implementation must conform to the following requirements.

- 1. When a cost overrun is triggered, in addition to releasing any cost overrun handler, the following actions must be performed.
 - (a) When the most recent release of the schedulable is the i^{th} release, and the i+1 release event has not yet occurred, the following must hold.
 - i. When the state of the schedulable is either executing or eligible-for-execution, the schedulable is placed into the state blocked-by-cost-overrun. There may be a bounded delay between the time at which a cost overrun occurs and the time at which the schedulable becomes blocked-by-cost-overrun.
 - ii. Otherwise, the schedulable must have been blocked for a reason other than blocked-by-cost-overrun. In this case, the state change to blocked-by-cost-overrun is left pending; when the blocking condition for the schedulable is removed, then its state changes to blocked-by-cost-overrun. There may be a bounded delay between the time at which the blocking condition is removed and the time at which the schedulable becomes blocked-by-cost-overrun.
 - (b) When the most recent release of the schedulable is the i^{th} release, and the i+1 release event has occurred, the current CPU consumption is set to zero, the schedulable remains in its current state and the cost monitoring system considers the most recent release to now be the i+1 release.
- 2. When the i^{th} release event occurs for a schedulable, the action taken depends on the state of the schedulable.

90 6.3 Semantics

(a) When the schedulable is blocked-by-cost-overrun then the cost monitoring system considers the most recent release to be the i^{th} release, the current CPU consumption is set to zero and the schedulable is made eligible for execution;

- (b) When the schedulable is blocked for a reason other than blocked-by-costoverrun then
 - i. when there is a pending state change to blocked-by-cost-overrun then the pending state change is removed, the cost monitoring system considers the most recent release to be the i^{th} release, the current CPU consumption is set to zero, and the schedulable remains in its current blocked state;
 - ii. otherwise, no cost monitoring action occurs.
- (c) When the schedulable is not blocked, no cost monitoring action occurs.
- 3. When the i^{th} release of a schedulable completes, and the cost monitoring system considers the most recent release to be the i^{th} release, then the current CPU consumption is set to zero and the cost monitoring system considers the most recent release to be the i+1 release. Otherwise, no cost monitoring action occurs.
- 4. Changes to the cost parameter take effect immediately.
 - (a) When the new cost is less than or equal to the current CPU consumption, and the old cost was greater than the current CPU consumption, then a cost overrun is triggered.
 - (b) When the new cost is greater than the current CPU consumption,
 - i. in the case that the schedulable is blocked-by-cost-overrun, the schedulable is made eligible for execution:
 - ii. in the case that the schedulable is blocked for a reason other than blocked-by-cost-overrun and there is a pending state change to blocked-by-cost-overrun, the pending state change is removed;
 - iii. in all other cases, no cost monitoring action occurs.
- 5. The state of the cost monitoring system for a schedulable can be reset by the scheduler (see 6.3.2.5 in the **Release of a Realtime Thread** section, below). When the most recent release of the schedulable is considered to be the m^{th} release and the most recent release event for the schedulable was the n^{th} release event (where n > m), a reset causes the cost monitoring system to consider the most recent release to be the n^{th} release, and to zero the current CPU consumption.

6.3.2.5 Release of a Realtime Thread

The repeated release of a realtime thread is achieved by executing in a loop and invoking the RealtimeThread.waitForNextRelease¹ methods, or its interruptible equivalent RealtimeThread.waitForNextReleaseInterruptible) within that loop. For simplicity, unless otherwise stated, the semantics in this section apply to both forms of this method.

- 1. A realtime thread's release characteristics are determined by the following:
 - (a) the invocation of the realtime thread's **start** method and the value of its phasing policy parameter (if applicable);
 - (b) the action of the RealtimeThread methods waitForNextRelease, wait-ForNextReleaseInterruptible, schedule, and deschedule;
 - (c) the occurrence of deadline misses and whether or not a miss handler is installed; and
 - (d) whether the passing of time generates periodic release events or calls to the release method generates aperiodic release events.
- 2. The *initial release event* depends on the type of release parameters given the realtime thread:
 - (a) for a realtime thread with periodic parameters, the *initial release event* occurs in response to the invocation of its start method in accordance with the start time specified in its release parameters and its assigned phasing policy—see PeriodicParameters and PhasingPolicy;
 - (b) For a realtime thread with aperiodic parameters, the *initial release event* occurs immediately in response to the invocation of its start method.
- 3. Changes to the start time in a realtime thread's PeriodicParameters object only have an effect on its initial release time. Consequently, when a PeriodicParameters object is bound to multiple realtime threads, a change in the start time may affect all, some or none, of those threads, depending on whether or not start has been invoked on them.
- 4. When subsequent release events occur also depends on the type of release parameters given to the realtime thread:
 - (a) for periodic realtime threads, each period (and hence each release) falls due, except as described below (in 6d), at regular intervals such that when the i^{th} release event occurred at a time t_i , the i+1 release event occurs at the time $t_i + T_i$, where T_i is the value of the period stored in the realtime thread's PeriodicParameters object at the time t_i ;
 - (b) for aperiodic realtime threads, a release occurs with each call of the release method, except as described below (in 6d); and
 - (c) for sporadic realtime threads, a release occurs with each call of the release

¹The method RealtimeThread.waitForNextPeriod has been replaced by Realtime-Thread.waitForNextRelease as of RTSJ 2.0. The same goes for its interruptible equivalent.

method, except, as described below (in 6d), when additional regulation is required to enforce MIT as defined in *Sporadic Release Control* below.

- 5. Each release of an aperiodic realtime thread is an arrival.
 - (a) When the thread has release parameters of type AperiodicParameters, then the arrival may become a release event for the thread according to the semantics given in "Aperiodic Release Control" below.
 - (b) When the thread has release parameters of type SporadicParameters, then the arrival may become a release event for the thread according to the semantics given in "Sporadic Release Control" below.
 - (c) When the thread has release parameters of a type other than Sporadic-Parameters then the arrival is a release event, and the arrival-time is the release event time.
- 6. The implementation should behave effectively as if the following state variables were added to a realtime thread's state,

boolean descheduled, integer pendingReleases, integer missCount, and boolean lastReturn;

and manipulated by the actions as described below.

(a) Initially

 $\begin{array}{ll} {\tt descheduled} &= {\tt false}, \\ {\tt pendingReleases} &= 0, \\ {\tt missCount} &= 0, {\tt and} \\ {\tt lastReturn} &= {\tt true}. \end{array}$

- (b) When the realtime thread's deschedule method is invoked: set the value of descheduled to true. When descheduled is true, the realtime thread is said to be descheduled.
- (c) When the realtime thread's schedule method is invoked: set the value of descheduled to false; then when the thread is blocked-for-release-event, set the value of pendingReleases and missCount to zero, and tell the cost monitoring and enforcement system to reset for this thread.
- (d) A realtime thread that has been descheduled and is blocked-for-releaseevent will not receive any further release events until after it has been rescheduled by a call to **schedule**; this means that no deadline misses can occur until the thread has been rescheduled.
- (e) When each release event occurs
 - when the state of the realtime thread is blocked-for-release-event (that is, it is waiting in waitForNextRelease) and the thread is descheduled then do nothing,
 - ii. when the state is blocked-for-release-event and the thread is scheduled, increment the value of pendingReleases, inform cost monitor-

- ing and enforcement that the next release event has occurred, and notify the thread to make it eligible for execution;
- iii. otherwise when the thread is in a relase, increment the value of pendingReleases, and inform cost monitoring and enforcement that the next release event has occurred.
- (f) On each deadline miss, there are two cases:
 - i. When the realtime thread has a deadline miss handler, set the value of descheduled to true, atomically release the handler with its fire—Count increased by the value of missCount + 1, and zero missCount;
 - ii. Otherwise, add one to the missCount value.
- (g) When the waitForNextRelease method is invoked by the current realtime thread there are three possible behaviors depending on the value of missCount and lastReturn.
 - i. When missCount is zero, apply any pending parameter changes, inform cost monitoring and enforcement of completion, and then wait while descheduled is true, or pendingReleases is zero. Then set the lastReturn value to true, decrement pendingReleases, and return true.
 - ii. When missCount is greater than zero and the lastReturn value is false, completion occurs: decrement the missCount value; then apply any pending parameter changes, decrement pendingReleases, inform cost monitoring and enforcement the realtime thread has completed and return false;
 - iii. Otherwise, when missCount is greater than zero and the lastReturn value is true, decrement the missCount value and set the lastReturn value to false and return false.
- 7. An invocation of the waitForNextReleaseInterruptible method behaves as described above with the following additions.
 - (a) When the invocation commences with an instance of Asynchronously-InterruptedException (AIE) is pending on the realtime thread, then the invocation immediately completes abruptly by throwing that pending instance as an InterruptedException. When this occurs, the most recent release has not completed. When the pending instance is the generic AIE instance, then the interrupt state of the realtime thread is cleared.
 - (b) When an instance of AIE becomes pending on the realtime thread while it is blocked-for-release-event, and the realtime thread is descheduled, then the AIE remains pending until the realtime thread is no longer descheduled. The associated reschedule acts as a release event. Execution then continues as in 7d where the time value used as t_{int} is the time at which the schedulable was rescheduled.

(c) When an instance of AIE becomes pending on the realtime thread while it is blocked-for-release-event and it is not descheduled, then this acts as a release event. Execution then continues as in 7d, where the time value used as t_{int} is the time at which the AIE becomes pending.

- (d) i. The realtime thread is made eligible for execution.
 - ii. Upon execution, the invocation completes abruptly by throwing the pending AIE instance as an InterruptedException. When the pending instance is the generic AIE instance then the interrupt state of the realtime thread is cleared.
 - iii. The deadline associated with this release is the time $\mathbf{t}_{int} + \mathbf{D}_{int}$, where \mathbf{D}_{int} is the value of the deadline stored in the realtime thread's release parameters object at the time \mathbf{t}_{int} .
 - iv. The next release time for the realtime thread will be $t_{int}+T_{int}$, where T_{int} is the value of the period stored in the realtime thread's release parameters object at the time t_{int} .
 - v. Cost monitoring and enforcement is informed of the release event.

When the thrown AIE instance is caught, the AIE becomes pending again (as per the usual semantics for AIE) until it is explicitly cleared.

- 8. Changes to release parameter types are treated as a pseudo RESTART of the realtime thread and
 - (a) any old pending releases are cleared
 - (b) any old arrival queue is flushed
 - (c) any outstanding call to deschedule is cleared
 - (d) any outstanding deadline misses are cleared

The effect on the thread falls into one of four main cases.

- (a) When the realtime thread is not waiting for next release event and is not descheduled,
 - i. there is no effect until the end of current release, and
 - ii. when the change occurs, it is a pseudo restart of the thread, i.e., when the new parameters are aperiodic, the release is immediate and when the parameters are periodic, the periodic start time algorithm is used.
- (b) When the realtime thread is not waiting for next release event, but there is an outstanding descheduled,
 - i. there is an immediate "schedule" of the thread,
 - ii. there is no further effect until end of current release, and
 - iii. when change occurs, it is a pseudo restart of the thread, i.e., when new parameters are aperiodic, the release is immediate, and when new parameters are periodic, the periodic start time algorithm is used.

(c) When the realtime thread is waiting for next release event, is not descheduled, and the release parameter type is changed,

- i. from Periodic to Aperiodic, at the next periodic release event occurs, the thread becomes aperiodic with an immediate release, or
- ii. from Aperiodic to Periodic, there is an immediate pseudo restart of the thread using the periodic start time algorithm.
- (d) When the realtime thread is waiting for the next release event and the type of release parameters is changed, but there is an outstanding descheduled,
 - i. the change is from Periodic to Aperiodic, there is an immediate "schedule" of the thread, and when the next periodic release event occurs, the thread becomes aperiodic with an immediate release, or
 - ii. the change is from Aperiodic to Periodic, there is an immediate "schedule" of the thread and there is an immediate pseudo restart of the thread using the periodic start time algorithm.

6.3.2.5.1 UML Diagrams for Realtime Thread Releases The three UML diagrams in Figures 6.1, 6.2, and 6.3, are provided to illustrate the foregoing rules for releasing realtime threads. The first two figures are for a thread without a deadline miss handler. The first is a UML sequence diagram of some example Realtime Thread releases. The second is a UML state chart of the release process for a realtime thread. The third is a UML state chart of the release process for a realtime thread with a deadline miss handler.

In figure 6.1, a yellow background marks the execution of a normal release, an orange background marks the execution of a miss handler, and a red background marks the execution of a missed release. Both the miss handler and all missed releases are eligible to run as soon as the previous release is finish. A normal release, which encounters a deadline miss during its execution is not complete until its miss handler completes.

In the other two figures, a yellow background marks releases and a pink background marks blocked states. There are three release states: normal release, miss handler, and missed release. They can only be left by a call to waitForNextRelease or its equivalent. The miss handler state is part of a normal release that misses its deadline during the release. There are two blocked-for-release-event states: blocked for normal release and blocked for missed release. It is only in these states that descheduling can occur, because only completion occurs upon their entry. In addition, the blocked for missed release is a ephemeral state, since the deadline miss has already occurred before the state is entered, so state is left immediately. It is there to enable all actions that occur on completion.

Figure 6.1: Sequence Diagram of Some Example Realtime Thread Releases




Figure 6.2: A State Chart for a Realtime Thread without a Deadline Miss Handler





Figure 6.3: A State Chart for a Realtime Thread with a Deadline Miss Handler



6.3.2.6 Aperiodic Release Control

Aperiodic schedulables are released in response to events occurring, such as the starting of a realtime thread, the calling of the release method of a realtime thread, or the firing of an associated asynchronous event for an asynchronous event handler. The occurrence of these events, each of which is a potential release event, is termed an arrival, and the time that they occur is termed the arrival time.

The base scheduler behaves effectively as if it maintained a queue, called the arrival time queue, for each aperiodic schedulable object. This queue maintains information related to each release event (including any parameters passed with the release mechanism) from its "arrival" time until the associated release completes, or another release event occurs — whichever is later. When an arrival is accepted into the arrival time queue, then it is a release event and the time of the release event is the arrival time. The initial size of this queue is an attribute of the sched-

ulable's aperiodic parameters, and is set when an aperiodic parameter object is first associated with the schedulable. Over time the queue may become full and its behavior in this situation is determined by the queue overflow policy specified in the schedulable's aperiodic parameters. There are four overflow policies defined:

Policy	Action on Overflow
IGNORE	Silently ignore the arrival. The arrival is not accepted,
	no release event occurs, and, when the arrival was caused
	programmatically (such as by invoking fire on an asyn-
	chronous event), the caller is not informed that the arrival
	has been ignored.
EXCEPT	Throw an ArrivalTimeQueueOverflowException. The
	arrival is not accepted, and no release event occurs, but
	when the arrival was caused programmatically, the caller
	$\label{eq:will-have ArrivalTimeQueueOverflowException} will have {\tt ArrivalTimeQueueOverflowException}\ thrown.$
REPLACE	The arrival is not accepted and no release event occurs.
	When the completion associated with the last release event
	in the queue has not yet occurred, and the deadline has not
	been missed, the release event time for that release event
	is replaced with the arrival time of the new arrival and
	any associated parameters overwritten. This will alter the
	deadline for that release event. When the completion as-
	sociated with the last release event has occurred, or the
	deadline has already been missed, the behavior of the RE-
	PLACE policy is equivalent to the IGNORE policy.
SAVE	Behave effectively as if the queue were expanded as nec-
	essary to accommodate the new arrival. The arrival is ac-
	cepted and a release event occurs.

Under the SAVE policy the queue can grow and shrink over time.

Changes to the queue overflow policy take effect immediately. When an arrival occurs and the queue is full, the policy applied is the policy as defined at that time.

6.3.2.7 Sporadic Release Control

Sporadic parameters include a minimum interarrival time, MIT, that characterizes the expected frequency of releases. When an arrival is accepted implementation behaves as if it calculates the earliest time at which the next arrival could be accepted, by adding the current MIT to the arrival time of this accepted arrival. The scheduler guarantees that each sporadic schedulable it manages, is released at most once in any MIT. It implements two mechanisms for enforcing this rule:

1. Arrival-time regulation controls the work-load by considering the time between arrivals. When a new arrival occurs earlier than the expected next arrival time then a MIT violation has occurred, and the scheduler acts to prevent a release from occurring that would break the "one release per MIT" guarantee. Three arrival-time MIT-violation policies are supported:

Policy	Action on Violation
IGNORE	Silently ignore the violating arrival. The arrival is not ac-
	cepted, no release event occurs, and, when the arrival was
	caused programmatically (such as by invoking fire on an
	asynchronous event), the caller is not informed that the
	arrival has been ignored.
EXCEPT	Throw a MITViolationException. The arrival is not ac-
Little Er i	cepted, and no release event occurs, but when the arrival
	was caused programmatically, the caller will have MITVio-
	lationException thrown.
REPLACE	The arrival is not accepted and no release event occurs.
ILDI LACE	When the completion associated with the last release event
	_
	in the queue has not yet occurred, and the deadline has not
	been missed, then the release event time for that release
	event is replaced with the arrival time of the new arrival
	and any associated parameters overwritten. This will alter
	the deadline for that release event. When the completion
	associated with the last release event has occurred, or the
	deadline has already been missed, the behavior of the RE-
	PLACE policy is equivalent to the IGNORE policy.

2. Execution-time regulation occurs when the MIT violation policy SAVE is in effect. Under this policy all arrivals are accepted, but the scheduler behaves effectively as if released schedulable objects were further constrained by a scheduling policy that restricts execution to at most one release per MIT. This policy is only able to delay the effective release of a schedulable. The deadline of each release event is always set relative to its arrival time. This policy may not schedule the effective release of an async event handler until after its deadline has passed. In this case the deadline miss handler is released at the deadline time even though the related async event has not yet reached its effective release.

The SAVE policy makes no direct use of the next expected arrival time, but it maintains the value in case the MIT violation policy is changed from SAVE to one of the arrival-time regulation policies.

The effective release time of a release event i is the earliest time that the handler can be released in response to that release event. It is determined for each release event based on the MIT policy in force at the release event time:

- 1. For IGNORE, EXCEPT and REPLACE the effective release time is the release event time.
- 2. For SAVE the effective release time of release event i is the effective release time of release event i-1 plus the current value of the MIT.

The scheduler will delay the release associated with the release event at the head of the arrival time queue until the current time is greater than or equal to the effective release time of that release event.

Changes to minimum interarrival time and the MIT violation policy take effect immediately, but only affect the next expected arrival time, and effective release time, for release events that occur after the change.

6.3.2.8 Release Control for Asynchronous Event Handlers

Asynchronous event handlers can be associated with one or more asynchronous events. When an asynchronous event is fired, all handlers associated with it are released, according to the semantics below:

- 1. Each firing of an associated asynchronous event is an arrival. If the handler has release parameters of type AperiodicParameters, then the arrival may become a release event for the handler, according to the semantics given in "Aperiodic Release Control" above. When the handler has release parameters of type SporadicParameters, the arrival may become a release event for the handler, according to the semantics given in "Sporadic Release Control" above. When the handler has release parameters of a type other than SporadicParameters, the arrival is a release event, and the arrival-time is the release event time.
- 2. For each release event that occurs for a handler, an entry is made in the arrival-time queue and the handler's fireCount is incremented by one.
- 3. Initially a handler is considered to be blocked-for-release-event and its fire—count is zero.
- 4. Releases of a handler are serialized by having its handleAsyncEvent method invoked repeatedly while its fireCount is greater than zero:
 - (a) Before invoking handleAsyncEvent, the fireCount is decremented and the front entry (when still present) removed from the arrival-time queue.
 - (b) Each invocation of handleAsyncEvent, in this way, is a release.
 - (c) The return from handleAsyncEvent is the completion of a release.
 - (d) Processing of any exceptions thrown by handleAsyncEvent occurs prior to completion.
- 5. The deadline for a release is relative to the release event time and determined

at the release event time according to the value of the deadline contained in the handler's release parameters. This value does not change, except as described previously for handlers using a REPLACE policy for MIT violation or arrival-time queue overflow.

- 6. The application code can directly modify the fireCount as follows:
 - (a) The getAndDecrementPendingFireCount method decreases the fire—Count by one (when it is greater than zero), and returns the old value. This removes the front entry from the arrival-time queue but otherwise has no effect on the scheduling of the current schedulable, nor the handler itself. Any data parameter passed with the associated fire request is lost.
 - (b) The getAndClearPendingFireCount method is functionally equivalent to invoking getAndDecrementPendingFireCount until it returns zero, and returning the original fireCount value. Any data parameters passed with the associated fire requests are lost.
- 7. The scheduler may delay the invocation of handleAsyncEvent to ensure the effective release time honors any restrictions imposed by the MIT violation policy, when applicable, of that release event.
- 8. Cost monitoring and enforcement for an asynchronous event handler interacts with release events and completions as previously defined with the added requirement that at the completion of handleAsyncEvent, when the fireCount is now zero, then the cost monitoring and enforcement system is told to reset for this handler.

6.3.3 The Round-Robin Scheduler

The round-robin scheduler specified by the RTSJ is a fixed-quantum, fixed-priority priority-preemptive scheduler that interacts predictably with the base scheduler. Quantum expiry may be calculated either from task switch or on a heartbeat. It uses the PriorityParameters class for the configuration of schedulable priorities. It may not be present on all systems, but if it is present then it will obey the semantics specified here.

When a schedulable managed by the round-robin scheduler is scheduled, it will run either until it blocks (as on a monitor or for some I/O operation), voluntarily relinquishes the CPU (as for sleep), is priority preempted, or its quantum has elapsed.

The scheduler is not responsible for ensuring that a release, such as an event handler will complete within the quantum. Releases that take longer than with quantum will be rescheduled when another task is ready at the same priority. When this is not the desired behavior, the FirstInFirstOutScheduler should be used instead.

Open issue: If present, can the round-robin scheduler manage any schedulable?

What about asynchronous event handlers used for interrupts? How do we draw this line? **End of open issue**

6.3.3.1 Priorities

Priorities in the round-robin scheduler are as in the base scheduler, and priority values are numerically equivalent between the two. Schedulables managed by the round-robin scheduler behave as if they are scheduled from the same FIFO queue as schedulables managed by the base scheduler of the same numeric priority, except that they will consume no more than one quantum of execution time before being moved to the tail of the queue. Implementations are permitted to use a single, shared queue for this purpose.

If the round-robin scheduler is present, its priorities will have the same properties as the base scheduler, except for the following.

- 1. The round-robin scheduler must support at least one priority, and may support an arbitrarily large number of priorities.
- 2. All round-robin priorities must be greater than 10, and they must include all integers from the round-robin scheduler's getMinPriority() value to its getMaxPriority() value, inclusive.
- 3. The round-robin scheduler does not use the importance value in the ImportanceParameters subclass of PriorityParameters.
- 4. RoundRobinScheduler.getNormPriority() shall be set to

```
1 ((RoundRobinScheduler.getMaxPriority() - 2 RoundRobinScheduler.getMinPriority()) / 3) + 3 RoundRobinScheduler.getMinPriority()
```

The round-robin scheduler may provide priorities strictly lower than the base scheduler or a set of priorities partially or entirely overlapping with the priorities provided by the base scheduler.

6.3.4 Managing Groups of Schedulables

Conventional Java provides the class ThreadGroup to manage groups of threads. Only minimal functionality is provided: limiting priority, setting daemon status, and interrupting a group of threads at once. RTSJ extends this concept in two ways: limiting CPU affinity through the Affinity class and providing subclasses for managing Schedulables.

6.3.4.1 Scheduling Groups

The SchedulingGroup subclass of ThreadGroup provides a means of limiting the importance and scheduler of instance of Schedulable. The setMaxPriority method on ThreadGroup only pertains to tasks scheduled in the conventional Java range (1–10), but not for the realtime schedulers. Ensure this works and that conventional thread groups must not need to be scope aware, several restrictions must be enforces:

- 1. only tasks in a scheduling group may use a realtime scheduler,
- 2. Instances of Schedulable may only be created in a scheduling group,
- 3. the root ThreadGroup instance must be an instance of SchedulingGroup,
- 4. the ThreadGroup instance of the initial thread must be an instance of SchedulingGroup,
- 5. an instance of SchedulingGroup may not have a parent that is not an instance of SchedulingGroup, and
- 6. all ThreadGroup instance children of SchedulingGroup allocated in a Scoped-Memory must be instances of SchedulingGroup.

Furthermore, the enumeration methods on a scheduling group do not return any members in a ScopedMemory; for processing these a visitor must be used.

6.3.4.2 Processing Groups

A processing group is defined by an instance of the ProcessingGroup subclass of SchedulingGroup and each schedulable that is bound to that parameter object is called a *member* of that processing group. Processing groups are only functional in a system that implements processing group enforcement. A processing group instance acts as a proxy for its members, but enforcement does have an effect on the execution of member threads.

6.3.4.2.1 Definitions for Processing Groups The *enforced priority* of a schedulable is a priority with no execution eligibility.

6.3.4.2.2 Semantics for Processing Groups

- 1. The deadline of a processing group is defined by the value returned by invoking the getDeadline method of the processing group object.
- 2. A deadline miss for the processing group is triggered when any member of the processing group consumes CPU time at a time greater than the deadline for the most recent release of the processing group.
- 3. When a processing group misses a deadline:
 - (a) when the processing group has a miss handler, it is released for execution,
 - (b) otherwise, the processing group has no miss handler, no action is taken.

4. The cost of a processing group is defined by the value returned by invoking the getCost method of the processing group object.

- 5. When a processing group is initially released, its current CPU consumption is zero and as the members of the processing group execute, the current CPU consumption increases. The current CPU consumption is set to zero in response to certain actions as described below.
- 6. If at any time, due to either execution of the members of the processing group or a change in the group's cost, the current CPU consumption becomes greater than, or equal to, the current cost of the processing group, then a cost overrun is triggered. The implementation is required to document the granularity at which the current CPU consumption is updated.
- 7. When the affinity of the group contains more than one processor, the granularity enforced is the base granularity times the number of processors in the group's affinity.
- 8. When a cost overrun is triggered, the cost overrun handler associated with the processing group, if any, is released, and the processing group enters the enforced state. For each member of the processing group:
 - (a) the schedulable is placed into the enforced state; and
 - (b) When a schedulable is in the enforced state, the base scheduler schedules that schedulable effectively as if the enforced priority were used in place of the schedulable's base priority.
- 9. When the release event occurs for a processing group, the action taken depends on the state of the processing group.
 - (a) When the processing group is not in the enforced state, the current CPU consumption for the group is set to zero.
 - (b) Otherwise, the processing group is in the enforced state. It is removed from the enforced state, the current CPU consumption of the group is set to zero, and each member of the group is removed from the enforced state.
- 10. Changes to the cost take effect immediately.
 - (a) When the new cost is less than or equal to the current CPU consumption, and the old cost was greater than the current CPU consumption, a cost overrun is triggered.
 - (b) When the new cost is greater than the current CPU consumption there are two case:
 - i. when the processing group is enforced, then the processing group behaves as defined in semantic 9;
 - ii. otherwise, no cost monitoring and enforcement action occurs.
- 11. Changes to other parameters take place as follows:
 - (a) **start** can only be changed before the parameters group is started, i.e.,

- before the start time or before the parameter object is associated with any schedulable and changes take effect immediately;
- (b) **period** can be change at each release, so the next period is set based on the current value of the processing group's period;
- (c) **deadline** can change at each release, so the next deadline is set based on the current value of the processing group's deadline;
- (d) **OverrunHandler** can change at each release, so the overrunHandler is set based on the current value of the processing group's overrunHandler; and
- (e) **MissHandler** can change at each release, so the missHandler is set based on the current value of the processing group's missHandler.
- 12. Changes to the membership of the processing group take effect immediately.
- 13. The start time for the processing group may be relative or absolute.
 - (a) When the start time is absolute, the processing group behaves effectively as if the initial release time were the start time.
 - (b) When the start time is relative, the initial release time is computed relative to the time start or fire (as appropriate) is first called for a member of the processing group.

Note, until a processing group starts, its budget cannot be replenished, but its members will be enforced if they exceed the initial budget. Also, once a processing group is started, it behaves effectively as if it continued running continuously until the defining ProcessingGroupParameters object is freed.

6.4 Package javax.realtime

6.4.1 Interfaces

6.4.1.1 RealtimeExecutionContext

All RTSJ objects that encapsulate execution. This type includes Schedulable², javax.realtime.device.InterruptServiceRoutine³, and ActiveEventDispatcher⁴. It is used by Affinity⁵ to remove the need to have a reference into the javax.realtime.device package.

Note, java.lang.thread encapsulates execution, but is not part of the RTSJ. Technically, a dispatcher is not a task, but it contains one, so it does encapsulate execution

Available since RTSJ 2.0

6.4.1.2 Schedulable

Handlers and other objects can be dispatched by a Scheduler⁶ when they provide a run() method and the methods defined below. The Scheduler⁷ uses this information to create a suitable context to execute the run() method.

Interfaces

Runnable

Timable

RealtimeExecutionContext

6.4.1.2.1 Methods

getMemoryParameters

²Section 6.4.1.2

³Section ??

⁴Section 8.4.3.3

⁵Section 6.4.2.1

⁶Section 6.4.2.11

 $^{^7}$ Section 6.4.2.11

Gets a reference to the MemoryParameters⁸ object for this schedulable.

```
public
    javax.realtime.MemoryParameters getMemoryParameters()
Returns
    A reference to the current MemoryParameters
9 object.
```

getProcessingGroupParameters

Gets a reference to the ${\tt ProcessingGroupParameters}^{10}$ object for this schedulable.

```
public
    javax.realtime.ProcessingGroupParameters
    getProcessingGroupParameters()
Returns
    A reference to the current ProcessingGroupParameters<sup>11</sup> object.
```

getProcessingGroup

```
Signature
    public
    javax.realtime.ProcessingGroup getProcessingGroup()
```

${\tt getConfigurationParameters}$

Gets a reference to the ${\tt ConfigurationParameters}^{12}$ object for this schedulable. Available since RTSJ 2.0

```
<sup>8</sup>Section 11.4.2.4

<sup>9</sup>Section 11.4.2.4

<sup>10</sup>Section 15.3.3.6

<sup>11</sup>Section 15.3.3.6

<sup>12</sup>Section 5.3.2.1
```

```
Signature

public
 javax.realtime.ConfigurationParameters
 getConfigurationParameters()

Returns

A reference to the associated ConfigurationParameters 13 object.
```

getReleaseParameters

Gets a reference to the ReleaseParameters¹⁴ object for this schedulable.

```
Signature

public
    javax.realtime.ReleaseParameters getReleaseParameters()

Returns

A reference to the current ReleaseParameters<sup>15</sup> object.
```

getScheduler

Gets a reference to the Scheduler¹⁶ object for this schedulable.

```
Signature

public
 javax.realtime.Scheduler getScheduler()

Returns

A reference to the associated Scheduler<sup>17</sup> object.
```

getSchedulingParameters

Gets a reference to the SchedulingParameters¹⁸ object for this schedulable.

```
<sup>13</sup>Section 5.3.2.1

<sup>14</sup>Section 6.4.2.9

<sup>15</sup>Section 6.4.2.9

<sup>16</sup>Section 6.4.2.11

<sup>17</sup>Section 6.4.2.11

<sup>18</sup>Section 6.4.2.13
```

```
Signature

public

javax.realtime.SchedulingParameters getSchedulingParameters()

Returns
```

A reference to the current SchedulingParameters ¹⁹ object.

setMemoryParameters(MemoryParameters)

Sets the memory parameters associated with this instance of Schedulable.

This change becomes effective under conditions determined by the scheduler controlling the schedulable. For instance, the change may be immediate or it may be delayed until the next release of the schedulable object. See the documentation for the scheduler for details.

```
Signature

public

void setMemoryParameters(MemoryParameters memory)

Parameters
```

memory A MemoryParameters²⁰ object which will become the memory parameters associated with this after the method call. When null, the default value is governed by the associated scheduler (a new object is created when the default value is not null). (See PriorityScheduler²¹.)

Throws

IllegalArgumentException when memory is not compatible with the schedulable's scheduler. Also when this schedulable is no-heap and memory is located in heap memory.

Illegal Assignment Error when the schedulable cannot hold a reference to memory, or when memory cannot hold a reference to this schedulable instance. Illegal Thread State Exception when the schedulable's scheduler prohibits this parameter change at this time due to the state of the schedulable.

setProcessingGroupParameters(ProcessingGroupParameters)

¹⁹Section 6.4.2.13

 $^{^{20}}$ Section 11.4.2.4

 $^{^{21}}$ Section 6.4.2.7

Sets the ProcessingGroupParameters²² of this.

This change becomes effective under conditions determined by the scheduler controlling the schedulable. For instance, the change may be immediate or it may be delayed until the next release of the schedulable. See the documentation for the scheduler for details.

Signature

```
public
void setProcessingGroupParameters(ProcessingGroupParameters
group)
```

Parameters

group A ProcessingGroupParameters²³ object which will take effect as determined by the associated scheduler. When null, the default value is governed by the associated scheduler (a new object is created when the default value is not null). (See PriorityScheduler²⁴.)

Throws

IllegalArgumentException Thrown when group is not compatible with the scheduler for this schedulable object. Also when this schedulable is no-heap and group is located in heap memory.

IllegalAssignmentError when this object cannot hold a reference to group or group cannot hold a reference to this.

IllegalThreadStateException when the schedulable's scheduler prohibits the changing of the processing group parameter at this time due to the state of the schedulable object.

setReleaseParameters(ReleaseParameters)

Sets the release parameters associated with this instance of Schedulable.

This change becomes effective under conditions determined by the scheduler controlling the schedulable. For instance, the change may be immediate or it may be delayed until the next release of the schedulable. The different properties of the release parameters may take effect at different times. See the documentation for the scheduler for details.

Signature

²²Section 15.3.3.6

 $^{^{23}}$ Section 15.3.3.6

 $^{^{24}}$ Section 6.4.2.7

public void setReleaseParameters(ReleaseParameters release)

Parameters

release A ReleaseParameters²⁵ object which will become the release parameters associated with this after the method call, and take effect as determined by the associated scheduler. When null, the default value is governed by the associated scheduler (a new object is created when the default value is not null). (See PriorityScheduler²⁶.)

Throws

IllegalArgumentException Thrown when release is not compatible with the associated scheduler. Also when this schedulable is no-heap and release is located in heap memory.

IllegalAssignmentError when this object cannot hold a reference to release or release cannot hold a reference to this.

IllegalThreadStateException when the schedulable's scheduler prohibits the changing of the release parameter at this time due to the state of the schedulable.

setScheduler(Scheduler)

Sets the reference to the Scheduler object. The timing of the change must be agreed between the scheduler currently associated with this schedulable, and scheduler.

Signature

```
public
void setScheduler(Scheduler scheduler)
```

Parameters 5 4 1

scheduler A reference to the scheduler that will manage execution of this schedulable. Null is not a permissible value.

Throws

IllegalArgumentException Thrown when scheduler is null, or the schedulable's existing parameter values are not compatible with scheduler. Also when this schedulable is no-heap and scheduler is located in heap memory. IllegalAssignmentError when the schedulable cannot hold a reference to scheduler.

SecurityException when the caller is not permitted to set the scheduler for this schedulable.

 $^{^{25}}$ Section 6.4.2.9

 $^{^{26}}$ Section 6.4.2.7

IllegalThreadStateException when scheduler refuses to accept this schedulable at this time due to the state of the schedulable.

setScheduler(Scheduler, SchedulingParameters, ReleaseParameters, MemoryParameters, ProcessingGroupParameters)

Sets the scheduler and associated parameter objects. The timing of the change must be agreed between the scheduler currently associated with this schedulable, and scheduler.

Signature

```
public
void setScheduler(Scheduler scheduler, SchedulingParameters
scheduling, ReleaseParameters release, MemoryParameters
memoryParameters, ProcessingGroupParameters group)
```

Parameters

scheduler A reference to the scheduler that will manage the execution of this schedulable. Null is not a permissible value.

scheduling A reference to the SchedulingParameters²⁷ which will be associated with this. When null, the default value is governed by scheduler (a new object is created when the default value is not null). (See PriorityScheduler²⁸.)

release A reference to the ReleaseParameters²⁹ which will be associated with this. When null, the default value is governed by scheduler (a new object is created when the default value is not null). (See PriorityScheduler³⁰.) memoryParameters A reference to the MemoryParameters³¹ which will be associated with this. When null, the default value is governed by scheduler (a new object is created when the default value is not null). (See PriorityScheduler³².)

group A reference to the ProcessingGroupParameters³³ which will be associated with this. When null, the default value is governed by scheduler (a

 $^{^{27}}$ Section 6.4.2.13

 $^{^{28}}$ Section 6.4.2.7

 $^{^{29}}$ Section 6.4.2.9

 $^{^{30}}$ Section 6.4.2.7

³¹Section 11.4.2.4

³²Section 6.4.2.7

 $^{^{33}}$ Section 15.3.3.6

new object is created). (See PriorityScheduler³⁴.)

Throws

IllegalArgumentException Thrown when scheduler is null or the parameter values are not compatible with scheduler. Also thrown when this schedulable is no-heap and scheduler, scheduling release, memoryParameters, or group is located in heap memory.

IllegalAssignmentError when this object cannot hold references to all the parameter objects or the parameters cannot hold references to this.

IllegalThreadStateException when scheduler prohibits the changing of the scheduler or a parameter at this time due to the state of the schedulable.

Security Exception when the caller is not permitted to set the scheduler for this schedulable.

setSchedulingParameters(SchedulingParameters)

Sets the scheduling parameters associated with this instance of Schedulable.

This change becomes effective under conditions determined by the scheduler controlling the schedulable. For instance, the change may be immediate or it may be delayed until the next release of the schedulable. See the documentation for the scheduler for details.

Signature

public

void setSchedulingParameters(SchedulingParameters scheduling)

Parameters

scheduling A reference to the SchedulingParameters³⁵ object. When null, the default value is governed by the associated scheduler (a new object is created when the default value is not null). (See PriorityScheduler³⁶.)

Throws

IllegalArgumentException Thrown when scheduling is not compatible with the associated scheduler. Also when this schedulable is no-heap and scheduling is located in heap memory.

IllegalAssignmentError when this object cannot hold a reference to scheduling or scheduling cannot hold a reference to this.

IllegalThreadStateException when the schedulable's scheduler prohibits the changing of the scheduling parameter at this time due to the state of the schedulable

 $^{^{34}}$ Section 6.4.2.7

 $^{^{35}}$ Section 6.4.2.13

 $^{^{36}}$ Section 6.4.2.7

object.

getMinConsumption(RelativeTime)

Available since RTSJ 2.0

```
Signature \\ \text{public} \\ \text{javax.realtime.RelativeTime getMinConsumption(RelativeTime dest)} \\ Returns
```

The minimum CPU consumption for this schedulable in any single release. When this method is called on the current schedulable, the CPU consumption of the current release is not considered. When dest is null, return the minimum consumption in a RelativeTime³⁷ instance from the current allocation context. When dest is not null, return the minimum consumption in dest

getMinConsumption

```
Equivalent to getMinConsumption(null). Available since RTSJ 2.0
```

```
Signature

public

javax.realtime.RelativeTime getMinConsumption()
```

getMaxConsumption(RelativeTime)

Available since RTSJ 2.0

```
Signature public javax.realtime.RelativeTime getMaxConsumption(RelativeTime dest) \frac{Returns}{^{37}{\rm Section}~9.4.1.3}
```

^{2.0 (}Draft 20)

The maximum CPU consumption for this schedulable in any single release. When this method is called on the current schedulable, the CPU consumption of the current release is not considered. When dest is null, return the maximum consumption in a RelativeTime³⁸ instance from the current allocation context. When dest is not null, return the maximum consumption in dest

getMaxConsumption

Equivalent to getMaxConsumption(null). Available since RTSJ 2.0

```
Signature

public

javax.realtime.RelativeTime getMaxConsumption()
```

mayUseHeap

Determine whether or not this schedulable may use the heap.

Available since RTSJ 2.0

```
Signature public boolean mayUseHeap()
```

true only when this Schedulable may allocate on the heap and may enter the Heap.

awaken

Provides a means for a Clock³⁹ to end a sleep.

Available since RTSJ 2.0

³⁸Section 9.4.1.3 ³⁹Section 10.4.2.1

```
Signature

public

void awaken()

Throws

IllegalStateException when called from user code.
```

6.4.2 Classes

6.4.2.1 Affinity

This class is the API for all processor-affinity-related aspects of the RTSJ. It includes a factory that generates Affinity objects, and methods that control the default affinity sets used when affinity set inheritance does not apply.

An affinity is a set of processors that can be associated with certain types of tasks. Each java.lang.Thread and RealtimeExecutionContext⁴⁰ can be associated with an affinity. Groups of these can be assigned an affinity through a java.lang.ThreadGroup.

Each implementation supports an array of predefined affinity sets. They can be used either to reflect the scheduling arrangement of the underlying OS or they can be used by the system designer to impose defaults for groups of task. A program is only allowed to dynamically create new affinity sets with cardinality of one. This restriction reflects the concern that not all operating systems will support multiprocessor affinity sets.

The processor membership of an affinity set is immutable. The tasks associations of an affinity set are mutable. The processor affinity of a task can be changed by static methods in this class. The internal representation of a set of processors in an Affinity instance is not specified, but the representation that is used to communicate with this class is a BitSet where each bit corresponds to a logical processor ID. The relationship between logical and physical processors is beyond the scope of this specification, and may change.

The affinity set factory only generates usable Affinity instances; i.e., affinity sets that (at least when they are created) can be used with set(Affinity, Real-timeExecutionContext)⁴¹, set(Affinity, Thread)⁴², and set(Affinity, Thread-Group)⁴³. The factory cannot create an affinity set with more than one processor member, but such affinity sets are supported. They may be internally created by the RTSJ runtime at startup time.

 $^{^{40}}$ Section 6.4.1.1

⁴¹Section 6.4.2.1.1

⁴²Section 6.4.2.1.1

⁴³Section 6.4.2.1.1

The set of affinity sets created at startup (the predefined set) is visible through the getPredefinedAffinities(Affinity[])⁴⁴ method. The affinity set factory may be used to create affinity sets with a single processor member at any time. This operation only supports processor members that are available to the JVM at the time of creation.

External changes to the set of processors available to the RTSJ runtime is likely to cause serious trouble ranging from violation of assumptions underlying schedulability analysis to freezing the entire RTSJ runtime, so when a system is capable of such manipulation it should not exercise it on RTSJ processes.

Tasks are subject to both their own processor affinity and that of their thread group. Their processor affinity is governed by the intersection of the thread group's affinity and the schedulable's affinity. The intersection of a thread group's affinity set with the schedulable's affinity set must contain at least one entry. Trying to set a tasks affinity outside its thread group always fails. Trying to setting the affinity of a thread group that does not intersect with the thread group of its tasks will also fail.

Ordinarily, an execution context inherits its creator's affinity set, but

- Java threads do not inherit affinity from Schedulable⁴⁵,
- instance of AbstractAsyncEventHandler⁴⁶ that are not bound are not affected, and
- a Schedulable does not inherit affinity from Java threads.

When a task does not inherit its creator's affinity set, its initial affinity set is set to all processors and is thus only limited by its thread group.

There is no public constructor for this class. All instances must be created by the factory method (generate).

Available since RTSJ 2.0

Inheritance

java.lang.Object javax.realtime.Affinity

6.4.2.1.1 Methods

getPredefinedAffinitiesCount

⁴⁴Section 6.4.2.1.1

⁴⁵Section 6.4.1.2

Return the minimum array size required to store references to all the predefined processor affinity sets.

```
Signature
```

```
public static final
int getPredefinedAffinitiesCount()
```

Returns

The minimum array size required to store references to all the predefined affinity sets.

getPredefinedAffinities

Equivalent to invoking getPredefinedAffinitySets(null).

```
Signature
```

```
public static final
javax.realtime.Affinity[] getPredefinedAffinities()
```

Returns

an array of the pre-defined affinity sets.

getPredefinedAffinities(javax.realtime.Affinity[])

Return an array containing all affinity sets that were predefined by the Java runtime.

```
Signature
```

```
public static final
javax.realtime.Affinity[]
getPredefinedAffinities(javax.realtime.Affinity[] dest)
```

Parameters

dest The destination array, or null.

Throws

IllegalArgumentException when dest is not large enough.

Returns

dest or a newly created array when dest is null, populated with references to the pre-defined affinity sets.

When dest has excess entries, they are filled with null.

isSetAffinitySupported

Determine whether or not affinity control is supported.

```
Signature
```

```
public static final
boolean isSetAffinitySupported()
```

Returns

true when the set(Affinity, Thread)⁴⁷ family of methods is supported.

generate(BitSet)

Returns an Affinity set with the affinity BitSet bitSet and no associations.

Platforms that support specific affinity sets will register those Affinity instances with Affinity⁴⁸. They appear in the arrays returned by getPredefinedAffinities()⁴⁹ and getPredefinedAffinities(Affinity[])⁵⁰.

Signature

```
public static final
javax.realtime.Affinity generate(BitSet bitSet)
```

Parameters

bitSet The BitSet associated with the generated Affinity.

Throws

NullPointerException when bitSet is null.

IllegalArgumentException when bitSet does not refer to a valid set of processors, where "valid" is defined as the bitset from a pre-defined affinity set, or a bitset of cardinality one containing a processor from the set returned by getAvailableProcessors(). The definition of "valid set of processors" is system dependent; however, every set consisting of one valid processor makes up a valid bit set, and every bit set correspond to a pre-defined affinity set is valid.

Returns

The resulting Affinity.

```
^{47}Section 6.4.2.1.1
```

⁴⁸Section 6.4.2.1

⁴⁹Section 6.4.2.1.1

 $^{^{50}}$ Section 6.4.2.1.1

getAvailableProcessors

This method is equivalent to getAvailableProcessors(BitSet)⁵¹ with a null argument.

```
Signature

public static final
 java.util.BitSet getAvailableProcessors()

Returns

the set of processors available to the program.
```

getAvailableProcessors(BitSet)

In systems where the set of processors available to a process is dynamic (e.g., because of system management operations or because of fault tolerance capabilities), the set of available processors shall reflect the processors that are allocated to the RTSJ runtime and are currently available to execute tasks.

```
Signature
```

```
public static final
java.util.BitSet getAvailableProcessors(BitSet dest)
```

Parameters

dest When dest is non-null, use dest as the returned value. When it is null, create a new BitSet.

Returns

A BitSet representing the set of processors currently valid for use in the bitset argument to generate(BitSet)⁵².

get(RealtimeExecutionContext)

Return the affinity set instance associated with task.

```
Signature
```

```
public static final
javax.realtime.Affinity get(RealtimeExecutionContext task)
```

⁵¹Section 6.4.2.1.1 ⁵²Section 6.4.2.1.1

Parameters

task is the execution context to query.

Returns

The associated affinity.

set(Affinity, RealtimeExecutionContext)

Set the processor affinity of a task.

Signature

```
public static final
void set(Affinity set, RealtimeExecutionContext task)
throws ProcessorAffinityException
```


set is the processor affinity

task is the execution context whose affinity will be set.

Throws

ProcessorAffinityException is thrown when the runtime fails to set the affinity for platform-specific reasons.

NullPointerException when set or task is null.

get(Thread)

Return the affinity set instance associated with thread.

Signature

```
public static final
javax.realtime.Affinity get(Thread thread)
```

Parameters

thread a Java thread, or one of its subclasses (including RealtimeThread⁵³).

Returns

The associated affinity set.

set(Affinity, Thread)

Set the processor affinity of a Java thread or RealtimeThread⁵⁴ to set.

⁵³Section 5.3.2.2

 $^{^{54}}$ Section 5.3.2.2

Signature

public static final
void set(Affinity set, Thread thread)
throws ProcessorAffinityException

set The processor affinity set

thread The thread or real-time thread.

Throws 1

Processor Affinity Exception when the runtime fails to set the affinity for platform-specific reasons.

NullPointerException when set or thread is null.

get(ThreadGroup)

Return the affinity set instance associated with group.

Signature

```
public static final
javax.realtime.Affinity get(ThreadGroup group)
```

Parameters

group An instance of java.lang.ThreadGroup

Returns

The associated affinity set.

set(Affinity, ThreadGroup)

Set the processor affinity of pgp to set.

Signature

```
public static final
void set(Affinity set, ThreadGroup group)
throws ProcessorAffinityException
```

Parameters

set The processor affinity set pgp The processing group parameters instance.

Throws

ProcessorAffinityException when the runtime fails to set the affinity for platform-specific reasons or pgp contains more than one processor.

NullPointerException when set or pgp is null.

getProcessors

Return a BitSet representing the processor affinity set for this Affinity.

```
Signature
    public final
    java.util.BitSet getProcessors()
```

A newly created BitSet representing this Affinity.

getProcessors(BitSet)

Return a BitSet representing the processor affinity set of this Affinity. Available since RTSJ 2.0

```
Signature
```

```
public final
java.util.BitSet getProcessors(BitSet dest)
```

Parameters

dest Set dest to the BitSet value. When dest is null, create a new BitSet in the current allocation context.

Returns

A BitSet representing the processor affinity set of this Affinity.

isProcessorInSet(int)

Ask whether a processor is included in this affinity set.

Available since RTSJ 2.0

```
Signature public final
```

```
boolean isProcessorInSet(int processorNumber)
```

Parameters

processorNumber

Returns

True when and only when processorNumber is represented in this affinity set.

applyTo(BoundAsyncEventHandler)

Set the processor affinity of a bound AEH to this.

Signature

```
public final
void applyTo(BoundAsyncEventHandler aeh)
throws ProcessorAffinityException
```

Parameters

aeh The bound async event handler

Throws

ProcessorAffinityException Thrown when the runtime fails to set the affinity for platform-specific reasons.

NullPointerException when aeh is null.

applyTo(Thread)

Set the processor affinity of a Java thread or RealtimeThread⁵⁵ to this.

Signature

```
public final
void applyTo(Thread thread)
throws ProcessorAffinityException
```

Parameters

thread The thread or realtime thread.

Throws

Processor Affinity Exception when the runtime fails to set the affinity for platform-specific reasons.

NullPointerException when thread is null.

⁵⁵Section 5.3.2.2

applyTo(ProcessingGroupParameters)

Set the processor affinity of pgp to this.

```
Signature
```

```
public final
void applyTo(ProcessingGroupParameters pgp)
throws ProcessorAffinityException
```

Parameters 1

pgp The processing group parameters instance.

Throws

Processor Affinity Exception when the runtime fails to set the affinity for platform-specific reasons or pgp contains more than one processor.

NullPointerException when pgp is null.

applyTo(javax.realtime.ActiveEventDispatcher<?,?>)

Set the processor affinity of dispatcher to this.

Signature

```
public final
void applyTo(javax.realtime.ActiveEventDispatcher<?, ?>
dispatcher)
throws ProcessorAffinityException
```

Parameters 1 4 1

dispatcher is the dispatcher instance.

Throws

ProcessorAffinityException when the runtime fails to set the affinity for platform-specific reasons.

NullPointerException when dispatcher is null.

6.4.2.2 AperiodicParameters

When a reference to an Aperiodic Parameters object is given as a parameter to a schedulable's constructor or passed as an argument to one of the schedulable's setter methods, the Aperiodic Parameters object becomes the release parameters object

bound to that schedulable. Changes to the values in the AperiodicParameters object affect that schedulable. When bound to more than one schedulable, changes to the values in the AperiodicParameters object affect *all* of the associated objects. Note that this is a one-to-many relationship and *not* a many-to-many.

Only changes to an AperiodicParameters object caused by methods on that object cause the change to propagate to all schedulables using the object. For instance, calling setCost on an AperiodicParameters object will make the change, then notify that the scheduler that the parameter object has changed. At that point the object is reconsidered for every schedulable that uses it. Invoking a method on the RelativeTime object that is the cost for this object may change the cost but it does not pass the change to the scheduler at that time. That change must not change the behavior of the schedulable's that use the parameter object until a setter method on the AperiodicParameters object is invoked, or the parameter object is used in setReleaseParameters() or a constructor for a schedulable.

The implementation must use modified copy semantics for each HighResolutionTime⁵⁶ parameter value. The value of each time object should be treated as if it were copied at the time it is passed to the parameter object, but the object reference must also be retained. For instance, the value returned by getCost() must be the same object passed in by setCost(), but any changes made to the time value of the cost must not take effect in the associated AperiodicParameters instance unless they are passed to the parameter object again, e.g. with a new invocation of setCost.

Correct initiation of the deadline miss and cost overrun handlers requires that the underlying system know the arrival time of each sporadic task. For an instance of RealtimeThread⁵⁷ the arrival time is the time at which the start() is invoked. For other instances of Schedulable⁵⁸, the required behaviors may require the implementation to behave effectively as if it maintained a queue of arrival times.

The following tables gives the default values for the constructors parameters.

Attribute	Value
cost	new RelativeTime(0,0)
deadline	new RelativeTime(Long.MAX_VALUE, 999999)
overrunHandler	None
missHandler	None
Arrival time queue size	0
Queue overflow policy	SAVE

⁵⁶Section 9.4.1.2

⁵⁷Section 5.3.2.2

 $^{^{58}}$ Section 6.4.1.2

Caution: This class is explicitly unsafe for multithreading when being changed. Code that mutates instances of this class should synchronize at a higher level.

Inheritance

java.lang.Object javax.realtime.ReleaseParameters javax.realtime.AperiodicParameters

6.4.2.2.1 Fields

arrival Time Queue Over flow Except

public static final arrivalTimeQueueOverflowExcept

Represents the "EXCEPT" policy for dealing with arrival time queue overflow. Under this policy, when an arrival occurs and its time should be queued but the queue already holds a number of times equal to the initial queue length defined by this then the fire() method shall throw a ArrivalTimeQueueOverflowException⁵⁹. Any other associated semantics are governed by the schedulers for the schedulables using these aperiodic parameters. When the arrival is a result of a happening to which the instance of AsyncEventHandler⁶⁰ is bound then the arrival time is ignored.

Available since RTSJ 1.0.1 Moved here from SporadicParameters.

arrival Time Queue Overflow Ignore

public static final arrivalTimeQueueOverflowIgnore

Represents the "IGNORE" policy for dealing with arrival time queue overflow. Under this policy, when an arrival occurs and its time should be queued, but the queue already holds a number of times equal to the initial queue length defined by this then the arrival is ignored. Any other associated semantics are governed by the schedulers for the schedulables using these aperiodic parameters.

Available since RTSJ 1.0.1 Moved here from SporadicParameters.

⁵⁹Section 14.2.2.1

 $^{^{60}{\}rm Section}~8.4.3.5$

arrival Time Queue Overflow Replace

public static final arrivalTimeQueueOverflowReplace

Represents the "REPLACE" policy for dealing with arrival time queue overflow. Under this policy, when an arrival occurs and should be queued but the queue already holds a number of times equal to the initial queue length defined by this then the information for this arrival replaces a previous arrival. Any other associated semantics are governed by the schedulers for the schedulables using these aperiodic parameters.

Available since RTSJ 1.0.1 Moved here from SporadicParameters.

arrivalTimeQueueOverflowSave

public static final arrivalTimeQueueOverflowSave

Represents the "SAVE" policy for dealing with arrival time queue overflow. Under this policy, when an arrival occurs and should be queued but the queue is full, then the queue is lengthened and the arrival time is saved. Any other associated semantics are governed by the schedulers for the schedulables using these aperiodic parameters. This policy does not update the "initial queue length" as it alters the actual queue length. Since the SAVE policy grows the arrival time queue as necessary, for the SAVE policy the initial queue length is only an optimization.

Available since RTSJ 1.0.1 Moved here from SporadicParameters.

6.4.2.2.2 Constructors

AperiodicParameters

Create an Aperiodic Parameters object. This constructor is equivalent to

AperiodicParameters(null, null, null, null)
Available since RTSJ 1.0.1

Signature

2.0 (Draft 20)

```
public
   AperiodicParameters()
```

AperiodicParameters(RelativeTime)

Create an AperiodicParameters object. This constructor is equivalent to

```
AperiodicParameters(null, deadline, null, null)
Available since RTSJ 2.0
```

```
Signature
```

```
public
   AperiodicParameters(RelativeTime deadline)
```

Parameters deadline

AperiodicParameters(RelativeTime, AsyncEventHandler)

Create an AperiodicParameters object. This constructor is equivalent to:

```
AperiodicParameters(null, deadline, null, missHandler)
Available since RTSJ 2.0
```

Signature

```
public
```

AperiodicParameters(RelativeTime deadline, AsyncEventHandler missHandler)

AperiodicParameters(RelativeTime, RelativeTime, AsyncEvent-Handler, AsyncEventHandler)

Create an AperiodicParameters object.

Available since RTSJ 2.0

Signature

public

AperiodicParameters(RelativeTime cost, RelativeTime deadline, AsyncEventHandl

Parameters

cost Processing time per invocation. On implementations which can measure the amount of time a schedulable object is executed, this value is the maximum amount of time a schedulable receives. On implementations which cannot measure execution time, it is not possible to determine when any particular object exceeds cost. When null, the default value is a new instance of RelativeTime(0,0).

deadline The latest permissible completion time measured from the release time of the associated invocation of the schedulable. When null, the default value is a new instance of RelativeTime(Long.MAX_VALUE, 999999).

overrunHandler This handler is invoked when an invocation of the schedulable exceeds cost. Not required for minimum implementation. When null, the default value is no overrun handler.

missHandler This handler is invoked when the run() method of the schedulable object is still executing after the deadline has passed. When null, the default value is no miss handler.

Throws

IllegalArgumentException when the time value of cost is less than zero, or the time value of deadline is less than or equal to zero.

IllegalAssignmentError when cost, deadline, overrunHandler or missHandler cannot be stored in this.

6.4.2.2.3 Methods

get Arrival Time Queue Overflow Behavior

Gets the behavior of the arrival time queue in the event of an overflow.

2.0 (Draft 20)

Available since RTSJ 1.0.1 Moved from SporadicParameters

```
Signature

public

java.lang.String getArrivalTimeQueueOverflowBehavior()

Returns

The behavior of the arrival time queue as a string.
```

getInitialArrivalTimeQueueLength

Gets the initial number of elements the arrival time queue can hold. This returns the initial queue length currently associated with this parameter object. When the overflow policy is SAVE the initial queue length may not be related to the current queue lengths of schedulables associated with this parameter object.

Available since RTSJ 1.0.1 Moved here from SporadicParameters.

```
Signature

public

int getInitialArrivalTimeQueueLength()

Returns

The initial length of the queue.
```

setDeadline(RelativeTime)

Sets the deadline value.

When this parameter object is associated with any schedulable object (by being passed through the schedulable's constructor or set with a method such as Real-timeThread.setReleaseParameters(ReleaseParameters)⁶¹) the deadline of those schedulables is altered as specified by each schedulable's respective scheduler.

```
Signature

public

void setDeadline(RelativeTime deadline)

Parameters

61 Section 5.3.2.2.2
```

deadline The latest permissible completion time measured from the release time of the associated invocation of the schedulable. When deadline is null, the deadline is set to a new instance of RelativeTime(Long.MAX_VALUE, 999999).

Throws

IllegalArgumentException when the time value of deadline is less than or equal to zero, or when the new value of this deadline is incompatible with the scheduler for any associated schedulable.

IllegalAssignmentError @inheritDoc

setArrivalTimeQueueOverflowBehavior(String)

Sets the behavior of the arrival time queue in the case where the insertion of a new element would make the queue size greater than the initial size given in this.

Values of behavior are compared using reference equality (==) not value equality (equals()).

Available since RTSJ 1.0.1 Moved here from SporadicParameters.

Signature

public

void setArrivalTimeQueueOverflowBehavior(String behavior)

Parameters 5

behavior A string representing the behavior.

Throws

IllegalArgumentException when **behavior** is not one of the **final** queue over-flow behavior values defined in this class.

setInitialArrivalTimeQueueLength(int)

Sets the initial number of elements the arrival time queue can hold without lengthening the queue. The initial length of an arrival queue is set when the schedulable using the queue is constructed, after that time changes in the initial queue length are ignored.

Available since RTSJ 1.0.1 Moved here from SporadicParameters.

Signature

public

void setInitialArrivalTimeQueueLength(int initial)

Parameters

initial The initial length of the queue.

Throws

IllegalArgumentException when initial is less than zero.

6.4.2.3 FirstInFirstOutScheduler

A version of PriorityScheduler⁶² where once a thread is scheduled at a given priority, it runs until it is blocked or is preempted by a higher priority thread. When preempted, it remains the next thread ready for its priority. This is the default scheduler for realtime tasks. It represents the required (by the RTSJ) priority-based scheduler. The default instance is the base scheduler which does fixed priority, preemptive scheduling.

This scheduler, like all schedulers, governs the default values for scheduling-related parameters in its client schedulables. The defaults are as follows:

	Attribute		Default Value
Priority parameters			
Priority		norm priority	

The system contains one instance of the FirstInFirstOutScheduler which is the system's base scheduler and is returned by FirstInFirstOutScheduler.instance(). The instance returned by the instance()⁶³ method is the *base scheduler* and is returned by Scheduler.getDefaultScheduler()⁶⁴ unless the default scheduler is reset with Scheduler.setDefaultScheduler(Scheduler)⁶⁵.

Available since RTSJ 2.0

Inheritance

java.lang.Object javax.realtime.Scheduler javax.realtime.PriorityScheduler javax.realtime.FirstInFirstOutScheduler

 $^{^{62}}$ Section 6.4.2.7

⁶³Section 6.4.2.3.1

 $^{^{64}}$ Section 6.4.2.11.2

 $^{^{65}}$ Section 6.4.2.11.2

6.4.2.3.1 Methods

instance

Return a reference to the distinguished instance of PriorityScheduler which is the system's base scheduler.

```
Signature

public static
javax.realtime.PriorityScheduler instance()

Returns

A reference to the distinguished instance PriorityScheduler.
```

getMaxPriority

Gets the maximum priority available for a schedulable managed by this scheduler.

```
Signature

public
int getMaxPriority()

Returns

The value of the maximum priority.
```

getMinPriority

Gets the minimum priority available for a schedulable managed by this scheduler.

```
Signature

public
int getMinPriority()

Returns

The minimum priority used by this scheduler.
```

2.0 (Draft 20)

getNormPriority

Gets the normal priority available for a schedulable managed by this scheduler.

```
Signature
    public
    int getNormPriority()
Returns
    The value of the normal priority.
```

getPolicyName

Gets the policy name of this.

```
Signature

public
 java.lang.String getPolicyName()

Returns

The policy name (Fixed Priority First In First Out) as a string.
```

reschedule(Thread, int)

Promotes a java.lang.Thread to realtime priority under this scheduler. The affected thread will be scheduled as if it were a RealtimeThread⁶⁶ of the given priority. This does not make the affected thread a RealtimeThread, however, and it will not have access to facilities reserved for instances of RealtimeThread.

```
public
void reschedule(Thread thread, int priority)

Parameters
thread The thread to promote to realtime scheduling.
priority An integer priority equivalent to a priority set via PriorityParameters

eters<sup>67</sup> on a RealtimeThread.
```

⁶⁶Section 5.3.2.2 ⁶⁷Section 6.4.2.6

pgp The processing group to which this thread should belong. If null, the affected thread will not be associated with any processing group.

Throws

IllegalArgumentException when priority is not between getMinPriority()⁶⁸ and getMaxPriority()⁶⁹, inclusive.

6.4.2.4 ImportanceParameters

Importance is an additional scheduling metric that may be used by some priority-based scheduling algorithms during overload conditions to differentiate execution order among threads of the same priority.

In some realtime systems an external physical process determines the period of many threads. When rate-monotonic priority assignment is used to assign priorities, many of the threads in the system may have the same priority because their periods are the same. However, it is conceivable that some threads may be more important than others and in an overload situation importance can help the scheduler decide which threads to execute first. The base scheduling algorithm represented by PriorityScheduler⁷⁰ must not consider importance.

Inheritance

```
java.lang.Object
javax.realtime.SchedulingParameters
javax.realtime.PriorityParameters
javax.realtime.ImportanceParameters
```

6.4.2.4.1 Constructors

ImportanceParameters(int, int)

Create an instance of ImportanceParameters.

Signature

```
<sup>68</sup>Section 6.4.2.3.1

<sup>69</sup>Section 6.4.2.3.1

<sup>70</sup>Section 6.4.2.7
```

```
public
   ImportanceParameters(int priority, int importance)
```

Parameters

priority The priority value assigned to schedulables that use this parameter instance. This value is used in place of the value passed to Thread.setPriority. importance The importance value assigned to schedulable objects that use this parameter instance.

6.4.2.4.2 Methods

getImportance

Gets the importance value.

```
Signature
    public
    int getImportance()
Returns
```

The value of importance for the associated instances of Schedulable⁷¹.

setImportance(int)

Set the importance value. When this parameter object is associated with any schedulable (by being passed through the schedulable's constructor or set with a method such as RealtimeThread.setSchedulingParameters(SchedulingParameters)⁷²) the importance of those schedulables is altered at a moment controlled by the schedulers for the respective schedulables.

```
Signature
public
void setImportance(int importance)

Parameters

71Section 6.4.1.2
72Section 5.3.2.2.2
```

importance The value to which importance is set.

Throws

IllegalArgumentException when the given importance value is incompatible with the scheduler for any of the schedulables which are presently using this parameter object.

toString

Print the value of the priority and importance values of the associated instance of Schedulable⁷³

```
Signature

public

java.lang.String toString()
```

6.4.2.5 PeriodicParameters

This release parameter indicates that the schedulable is released on a regular basis. For an AsyncEventHandler⁷⁴, this means that the handler is either released by a periodic timer, or the associated event occurs periodically. For a Realtime-Thread⁷⁵, this means that the RealtimeThread.waitForNextRelease⁷⁶ or RealtimeThread.waitForNextReleaseInterruptible⁷⁷ method will unblock the associated realtime thread at the start of each period.

When a reference to a PeriodicParameters object is given as a parameter to a schedulable's constructor or passed as an argument to one of the schedulable's setter methods, the PeriodicParameters object becomes the release parameters object bound to that schedulable. Changes to the values in the PeriodicParameters object affect that schedulable object. When bound to more than one schedulable then changes to the values in the PeriodicParameters object affect all of the associated objects. Note that this is a one-to-many relationship and not a many-to-many.

Only changes to a PeriodicParameters object caused by methods on that object cause the change to propagate to all schedulable objects using the object. For

```
^{73}Section 6.4.1.2
```

 $^{^{74}}$ Section 8.4.3.5

⁷⁵Section 5.3.2.2

⁷⁶Section 5.3.2.2.2

⁷⁷Section 5.3.2.2.2

instance, calling setCost on an PeriodicParameters object will make the change, then notify that the scheduler that the parameter object has changed. At that point the object is reconsidered for every SO that uses it. Invoking a method on the RelativeTime object that is the cost for this object may change the cost but it does not pass the change to the scheduler at that time. That change must not change the behavior of the SOs that use the parameter object until a setter method on the PeriodicParameters object is invoked, or the parameter object is used in setReleaseParameters() or a constructor for an SO.

Periodic parameters use HighResolutionTime⁷⁸ values for period and start time. Since these times are expressed as a HighResolutionTime⁷⁹ values, these values use accurate timers with nanosecond granularity. The actual resolution available and even the quantity the timers measure depend on the clock associated with each time value.

The implementation must use modified copy semantics for each HighResolutionTime⁸⁰ parameter value. The value of each time object should be treated as if it were copied at the time it is passed to the parameter object, but the object reference must also be retained. For instance, the value returned by getCost() must be the same object passed in by setCost(), but any changes made to the time value of the cost must not take effect in the associated PeriodicParameters instance unless they are passed to the parameter object again, e.g. with a new invocation of setCost.

The following table gives the default parameter values for the constructors.

Attribute	Default Value
start	new RelativeTime(0,0)
period	No default. A value must be sup-
	plied
cost	new RelativeTime(0,0)
deadline	new RelativeTime(period)
overrunHandler	None
missHandler	None

Periodic release parameters are strictly informational when they are applied to async event handlers. They must be used for any feasibility analysis, but release of the async event handler is not entirely controlled by the scheduler.

Caution: This class is explicitly unsafe for multithreading when being changed. Code that mutates instances of this class should synchronize at a higher level.

⁷⁸Section 9.4.1.2

 $^{^{79}}$ Section 9.4.1.2

 $^{^{80}}$ Section 9.4.1.2

Inheritance

```
javax.realtime.ReleaseParameters
javax.realtime.PeriodicParameters
```

6.4.2.5.1 Constructors

PeriodicParameters(RelativeTime)

Create a PeriodicParameters object with the specified period and all other attributes set to their default values. This constructor has the same effect as invoking PeriodicParameters(null, period, null, null, null, null)

Available since RTSJ 1.0.1

Signature

public

PeriodicParameters(RelativeTime period)

PeriodicParameters(javax.realtime.HighResolutionTime<?>, RelativeTime)

Create a PeriodicParameters object with the specified period and start times, and all other attributes set to their default values. This constructor has the same effect as invoking PeriodicParameters(start, period, null, null, null, null) Available since RTSJ 1.0.1

Signature

public

PeriodicParameters(javax.realtime.HighResolutionTime<?> start, RelativeTime p

PeriodicParameters(javax.realtime.HighResolutionTime<?>, RelativeTime, RelativeTime)

Create a PeriodicParameters object with the specified deadline, period and start times, and all other attributes set to their default values. This constructor has the same effect as invoking PeriodicParameters(start, period, null, deadline, null, null, null)

Available since RTSJ 2.0

Signature

public

PeriodicParameters(javax.realtime.HighResolutionTime<?> start, RelativeTime periodicParameters(javax.realtime.HighResolutionTime<?> start, RelativeTime</ start, RelativeTime</ start, RelativeTime</br>

PeriodicParameters(javax.realtime.HighResolutionTime<?>, RelativeTime, RelativeTime, AsyncEventHandler, AsyncEventHandler)

Create a PeriodicParameters object with attributes set to the specified values.

Signature

public

PeriodicParameters(javax.realtime.HighResolutionTime<?> start, RelativeTime periodicParameters(javax.realtime.HighResolutionTime<?> start, RelativeTime</ start, RelativeTime</ start, RelativeTime</br>

Parameters

start Time at which the first release begins (i.e. the real-time thread becomes eligible for execution.) When a RelativeTime, this time is relative to the first time the thread becomes activated (that is, when start() is called). When an AbsoluteTime, then the first release is the maximum of the start parameter and the time of the call to the associated RealtimeThread.start() method (modified according to any phasing policy). When null, the default value is a new instance of RelativeTime(0,0).

period The period is the interval between successive unblocks of the Realtime-Thread.waitForNextRelease⁸¹ and RealtimeThread.waitForNextReleaseInterruptible⁸²

 $^{^{81}}$ Section 5.3.2.2.2

⁸²Section 5.3.2.2.2

methods. There is no default value. When **period** is null an exception is thrown.

cost Processing time per release. On implementations which can measure the amount of time a schedulable is executed, this value is the maximum amount of time a schedulable receives per release. When null, the default value is a new instance of RelativeTime(0,0).

deadline The latest permissible completion time measured from the release time of the associated invocation of the schedulable. When null, the default value is new instance of RelativeTime(period).

overrunHandler This handler is invoked when an invocation of the schedulable exceeds cost in the given release. Implementations may ignore this parameter. When null, the default value is no overrun handler.

missHandler This handler is invoked when the run() method of the schedulable is still executing after the deadline has passed. When null, the default value is no deadline miss handler.

Throws

IllegalArgumentException when the period is null or its time value is not greater than zero, or when the time value of cost is less than zero, or when the time value of deadline is not greater than zero, or when the clock associated with the cost is not the realtime clock, or when the clock associated with the start, deadline and period parameters are not the same.

IllegalAssignmentError when start period, cost, deadline, overrunHandler or missHandler cannot be stored in this.

6.4.2.5.2 Methods

getPeriod

Gets the period.

```
Signature
```

public javax.realtime.RelativeTime getPeriod()

Returns

The current value in period.

getStart

Gets the start time.

```
Signature
```

```
public
javax.realtime.HighResolutionTime<?> getStart()
```

Returns

The current value in start. This is the value that was specified in the constructor or by setStart(), not the actual absolute time corresponding to the start of one of the schedulable objects associated with this PeriodicParameters object.

setDeadline(RelativeTime)

Sets the deadline value.

When this parameter object is associated with any schedulable object (by being passed through the schedulable's constructor or set with a method such as Real-timeThread.setReleaseParameters(ReleaseParameters)⁸³) the deadline of those schedulables is altered as specified by each schedulable's respective scheduler.

Signature

```
public
void setDeadline(RelativeTime deadline)
```

Parameters 1

deadline The latest permissible completion time measured from the release time of the associated invocation of the schedulable. When deadline is null, the deadline is set to a new instance of RelativeTime equal to period.

Throws

IllegalArgumentException when the time value of deadline is less than or equal to zero, or when the new value of this deadline is incompatible with the scheduler for any associated schedulable.

IllegalAssignmentError @inheritDoc

setPeriod(RelativeTime)

Sets the period.

⁸³Section 5.3.2.2.2

```
Signature
```

```
public
void setPeriod(RelativeTime period)
```

Parameters 1 4 1

period The value to which period is set.

Throws

IllegalArgumentException when the given period is null or its time value is not greater than zero. Also when period is incompatible with the scheduler for any associated schedulable or when an associated AbstractAsyncEventHandler⁸⁴ is associated with a Timer⁸⁵ whose period does not match period.

IllegalAssignmentError when period cannot be stored in this.

setStart(javax.realtime.HighResolutionTime<?>)

Sets the start time.

The effect of changing the start time for any schedulables associated with this parameter object is determined by the scheduler associated with each schedulable.

Note: An instance of PeriodicParameters may be shared by several schedulables. A change to the start time may take effect on a subset of these schedulables. That leaves the start time returned by getStart unreliable as a way to determine the start time of a schedulable.

Signature

```
public
void setStart(javax.realtime.HighResolutionTime<?> start)
```

Parameters 1

start The new start time. When null, the default value is a new instance of RelativeTime(0,0).

Throws

IllegalArgumentException when the given start time is incompatible with the scheduler for any of the schedulable objects which are presently using this parameter object.

IllegalAssignmentError when start cannot be stored in this.

⁸⁴Section 8.4.3.2

 $^{^{85}}$ Section 10.4.2.5

6.4.2.6 PriorityParameters

Instances of this class should be assigned to schedulables that are managed by schedulers which use a single integer to determine execution order. The base scheduler required by this specification and represented by the class PriorityScheduler⁸⁶ is such a scheduler.

Inheritance

```
java.lang.Object
javax.realtime.SchedulingParameters
javax.realtime.PriorityParameters
```

6.4.2.6.1 Constructors

PriorityParameters(int)

Create an instance of PriorityParameters⁸⁷ with the given priority.

Signature

```
public
  PriorityParameters(int priority)
```

Parameters

priority The priority assigned to schedulables that use this parameter instance.

6.4.2.6.2 Methods

getPriority

Gets the priority value.

 ⁸⁶ Section 6.4.2.7
 87 Section 6.4.2.6

```
Signature

public
int getPriority()

Returns
The priority.
```

setPriority(int)

Set the priority value. When this parameter object is associated with any schedulable (by being passed through the schedulable's constructor or set with a method such as RealtimeThread.setSchedulingParameters(SchedulingParameters)⁸⁸) the base priority of those schedulables is altered as specified by each schedulable's scheduler.

```
Signature

public
void setPriority(int priority)

Parameters
priority The value to which priority is set.

Throws
```

IllegalArgumentException when the given priority value is incompatible with the scheduler for any of the schedulables which are presently using this parameter object.

toString

⁸⁸Section 5.3.2.2.2

Converts the priority value to a string.

```
Signature

public
java.lang.String toString()

Returns

A string representing the value of priority.
```

^{2.0 (}Draft 20)

6.4.2.7 PriorityScheduler

Class which represents the required (by the RTSJ) priority-based scheduler. The default instance is the base scheduler which does fixed priority, preemptive scheduling.

This scheduler, like all schedulers, governs the default values for scheduling-related parameters in its client schedulables. The defaults are as follows:

	Attribute		Default Value
Priority parameters			
Priority		norm priority	

Note that the system contains one instance of the PriorityScheduler which is the system's base scheduler and is returned by PriorityScheduler.instance(). It may, however, contain instances of subclasses of PriorityScheduler and even additional instances of PriorityScheduler itself created through this class' protected constructor. The instance returned by the instance()⁸⁹ method is the *base scheduler* and is returned by Scheduler.getDefaultScheduler()⁹⁰ unless the default scheduler is reset with Scheduler.setDefaultScheduler(Scheduler)⁹¹.

Inheritance

javax.realtime.Scheduler javax.realtime.PriorityScheduler

6.4.2.7.1 Fields

MAX_PRIORITY

public static final MAX_PRIORITY

The maximum priority value used by the implementation.

Deprecated since RTSJ version as of RTSJ 1.0.1 Use the getMaxPriority⁹² method instead.

⁸⁹Section ??

 $^{^{90}}$ Section 6.4.2.11.2

⁹¹Section 6.4.2.11.2

 $^{^{92}}$ Section 6.4.2.7.3

MIN_PRIORITY

```
public static final MIN_PRIORITY
```

The minimum priority value used by the implementation.

Deprecated since RTSJ version as of RTSJ 1.0.1 Use the getMinPriority⁹³ method instead.

6.4.2.7.2 Constructors

PriorityScheduler

Construct an instance of PriorityScheduler. Applications will likely not need any instance other than the default instance.

Signature

```
protected
  PriorityScheduler()
```

6.4.2.7.3 Methods

getPolicyName

Gets the policy name of this.

```
Signature

public
java.lang.String getPolicyName()

Returns

The policy name (Fixed Priority) as a string.

93Section 6.4.2.7.3
```

^{2.0 (}Draft 20)

getMaxPriority

Gets the maximum priority available for a schedulable managed by this scheduler.

```
Signature

public abstract
int getMaxPriority()

Returns

The value of the maximum priority.
```

getMinPriority

Gets the minimum priority available for a schedulable managed by this scheduler.

```
Signature

public abstract
int getMinPriority()

Returns

The minimum priority used by this scheduler.
```

getNormPriority

Gets the normal priority available for a schedulable managed by this scheduler.

```
Signature

public abstract
int getNormPriority()

Returns

The value of the normal priority.
```

reschedule(Thread, int)

Promotes a java.lang.Thread to realtime priority under this scheduler. The affected thread will be scheduled as if it were a RealtimeThread⁹⁴ of the given

⁹⁴Section 5.3.2.2

priority. This does not make the affected thread a RealtimeThread, however, and it will not have access to facilities reserved for instances of RealtimeThread.

Available since RTSJ 2.0

```
Signature
```

```
public abstract
void reschedule(Thread thread, int priority)
```

Parameters 2 4 1

thread The thread to promote to realtime scheduling.

priority An integer priority equivalent to a priority set via PriorityParameters⁹⁵ on a RealtimeThread.

Throws

IllegalArgumentException when priority is not between getMinPriority()⁹⁶ and getMaxPriority()⁹⁷, inclusive.

6.4.2.8 ProcessingGroup

A subclass of ThreadGroup for handling tasks, instances of Schedulable⁹⁸ and java.lang.Thread, as a single group. The cost of the group can be both traced and limited over a given period. The motivation for this class is to enable the execution demands of a group of tasks to be bound.

A processing group has an associated affinity. The precision of cost monitoring is dependent on the number of processes in the thread group. In the worst case, it is the base precision times the number of processes in the processing group. The default affinity is that which was inherited from the parent thread group.

For all tasks with a reference to an instance of ProcessingGroup p, no more than p.cost will be allocated to the execution of these schedulables on the processor associated with its processing group in each interval of time given by p.period after the time indicated by p.start. No execution of the schedulables will be allowed on any processor other than this processor. When there is no intersection between the a schedulable objects affinity and its processing group's affinity, then the schedulable execution is constrained by the default processing group's affinity.

 $^{^{95}}$ Section 6.4.2.6

⁹⁶Section 6.4.2.7.3

⁹⁷Section 6.4.2.7.3

 $^{^{98}}$ Section 6.4.1.2

Logically ProcessingGroup represents a virtual server. This server has a start time, a period, a cost (budget) and a deadline. The server can only logically execute when (a) it has not consumed more execution time in its current release than the cost (budget) parameter, (b) one of its associated schedulables is executable and is the most eligible of the executable schedulables. When the server is logically executable, the associated schedulable is executed. When the cost has been consumed, any overrunHandler is released, and the server is not eligible for logical execution until the period is finished. At this point, its allocated cost (budget) is replenished. When the server is logically executing when its deadline expires, any associated missHandler is released. The deadline and cost parameters of all the associated schedulable objects have the same impact as they would if the objects were not bound to a processing group.

Processing group parameters use HighResolutionTime⁹⁹ values for cost, deadline, period and start time. Since those times are expressed as a HighResolution-Time¹⁰⁰, the values use accurate timers with nanosecond granularity. The actual resolution available and even the quantity it measures depends on the clock associated with each time value.

When a reference to a ProcessingGroup object is given as a parameter to a schedulable's constructor or passed as an argument to one of the schedulable's setter methods, the ProcessingGroup object becomes the processing group parameters object bound to that schedulable object. Changes to the values in the ProcessingGroup object affect that schedulable object. When bound to more than one schedulable then changes to the values in the ProcessingGroup object affect all of the associated objects. Note that this is a one-to-many relationship and not a many-to-many.

The implementation must use modified copy semantics for each HighResolutionTime¹⁰¹ parameter value. The value of each time object should be treated as if it were copied at the time it is passed to the parameter object, but the object reference must also be retained. Only changes to a ProcessingGroupParameters object caused by methods on that object are immediately visible to the scheduler. For instance, invoking setPeriod() on a ProcessingGroupParameters object will make the change, then notify that the scheduler that the parameter object has changed. At that point the scheduler's view of the processing group parameters object is updated. Invoking a method on the RelativeTime object that is the period for this object may change the period but it does not pass the change to the scheduler at that time. That new value for period must not change the behavior of the SOs that use the parameter object until a setter method on the ProcessingGroupParameters

⁹⁹Section 9.4.1.2

 $^{^{100}}$ Section 9.4.1.2

 $^{^{101}}$ Section 9.4.1.2

object is invoked, or the parameter object is used in setProcessingGroupParameters() or a constructor for an SO.

The implementation may use copy semantics for each HighResolutionTime parameter value. For instance the value returned by getCost() must be equal to the value passed in by setCost, but it need not be the same object.

The following table gives the default parameter values for the constructors.

Attribute	Default Value
start	new RelativeTime(0,0)
period	No default. A value must be sup-
	plied
cost	No default. A value must be sup-
	plied
deadline	new RelativeTime(period)
overrunHandler	None
missHandler	None

Caution: This class is explicitly unsafe in multithreaded situations when it is being changed. No synchronization is done. It is assumed that users of this class who are mutating instances will be doing their own synchronization at a higher level.

Caution: The cost parameter time should be considered to be measured against the target platform.

Inheritance

```
java.lang.Object
java.lang.ThreadGroup
javax.realtime.SchedulingGroup
javax.realtime.ProcessingGroup
```

6.4.2.8.1 Constructors

ProcessingGroup(String)

Create

Signature

```
public
    ProcessingGroup(String name)

Parameters
    name
```

ProcessingGroup(SchedulingGroup, String)

```
Signature

public

ProcessingGroup(SchedulingGroup parent, String name)
```

6.4.2.8.2 Methods

getStart

Gets the value of start. This is the value that was specified in the constructor or by setStart(), not the actual absolute time the corresponding to the start of the processing group.

```
Signature
    public
    javax.realtime.HighResolutionTime<?> getStart()
Returns
```

A reference to an instance of HighResolutionTime¹⁰² that represents the value of start.

${\tt setStart(javax.realtime.HighResolutionTime} <?>)$

Sets the value of start. When the processing group is already started this method alters the value of this object's start time property, but has no other effect.

 $^{^{102}}$ Section 9.4.1.2

```
Signature

public

void setStart(javax.realtime.HighResolutionTime<?> start)

throws IllegalArgumentException, IllegalAssignmentError

Parameters

start The new value for start. When null, the default value is a new instance of RelativeTime(0,0).

Throws

IllegalAssignmentError when start cannot be stored in this.

IllegalArgumentException when start is a relative time value and less than
```

getPeriod

zero.

Gets the value of period.

```
Signature

public

javax.realtime.RelativeTime getPeriod()
```

Returns

A reference to an instance of RelativeTime¹⁰³ that represents the value of period.

setPeriod(RelativeTime)

Sets the value of period.

```
Signature
```

```
public
void setPeriod(RelativeTime period)
```

throws IllegalArgumentException, IllegalAssignmentError

Parameters

period The new value for period. There is no default value. When period is null an exception is thrown.

Throws

¹⁰³Section 9.4.1.3

IllegalArgumentException when period is null, or its time value is not greater than zero. When the implementation does not support processing group deadline less than period, and period is not equal to the current value of the processing group's deadline, the deadline is set to a clone of period created in the same memory area as period.

IllegalAssignmentError when period cannot be stored in this.

getCost

Gets the value of cost.

```
Signature

public
 javax.realtime.RelativeTime getCost()

Returns

a reference to the value of cost.
```

setCost(RelativeTime)

Sets the value of cost.

```
Signature
```

```
public
void setCost(RelativeTime cost)
throws IllegalArgumentException, IllegalAssignmentError
```

Parameters

cost The new value for cost. When null, an exception is thrown.

Throws

IllegalArgumentException when cost is null or its time value is less than zero. IllegalAssignmentError when cost cannot be stored in this.

set Cost Overrun Handler (Async Event Handler)

Sets the cost overrun handler.

```
Signature public
```

2.0 (Draft 20)

void setCostOverrunHandler(AsyncEventHandler handler) throws IllegalAssignmentError

handler This handler is invoked when the run() method of and of the the schedulables attempt to execute for more than cost time units in any period. When null, no handler is attached, and any previous handler is removed.

Throws

IllegalAssignmentError when handler cannot be stored in this.

getCostOverrunHandler

Gets the cost overrun handler.

```
Signature
```

```
public
javax.realtime.AsyncEventHandler getCostOverrunHandler()
```

Returns

A reference to an instance of AsyncEventHandler¹⁰⁴ that is cost overrun handler of this.

getCurrentCost(RelativeTime)

Get the cost used in the current period so far.

Signature

```
public
```

javax.realtime.RelativeTime getCurrentCost(RelativeTime dest)

dest is the instance to use for returning the time.

Returns

dest containing the cost of the current period

getLastCost(RelativeTime)

Get the total cost used in the last period.

 $^{^{104}}$ Section 8.4.3.5

```
public javax.realtime.RelativeTime getLastCost(RelativeTime dest)

Parameters

dest is the instance to use for returning the time.

Returns

dest containing the cost of the last period
```

getGranularity

Determine the granularity of cost monitoring and cost enforcement.

```
Signature

public

long getGranularity()

Returns

the granularity in nanoseconds.
```

setGranularity(long)

Set the granularity of cost monitoring and cost enforcement. The system provides a lower bounds for this. When set below the lower bound, granularity is set to this lower bound. In general, this is the precision of the realtime clock.

```
Signature

public

void setGranularity(long nanos)

throws IllegalArgumentException

Parameters

nanos the new granularity in nanoseconds.

Throws

IllegalArgumentException when nanos is less than one.
```

6.4.2.9 ReleaseParameters

The top-level class for release characteristics of schedulable objects. When a reference to a ReleaseParameters object is given as a parameter to a constructor of a schedulable, the ReleaseParameters object becomes bound to the object being created. Changes to the values in the ReleaseParameters object affect the constructed object. When given to more than one constructor, then changes to the values in the ReleaseParameters object affect all of the associated objects. Note that this is a one-to-many relationship and not a many-to-many. Only changes to an ReleaseParameters object caused by methods on that object cause the change to propagate to all schedulables using the object. For instance, invoking setDeadline on a ReleaseParameters instance will make the change, and then notify that the scheduler that the object has been changed. At that point the object is reconsidered for every SO that uses it. Invoking a method on the RelativeTime object that is the deadline for this object may change the time value but it does not pass the new time value to the scheduler at that time. Even though the changed time value is referenced by ReleaseParameters objects, it will not change the behavior of the SOs that use the parameter object until a setter method on the ReleaseParameters object is invoked, or the parameter object is used in setReleaseParameters() or a constructor for a schedulable.

Release parameters use HighResolutionTime¹⁰⁵ values for cost, and deadline. Since the times are expressed as a HighResolutionTime¹⁰⁶ values, these values use accurate timers with nanosecond granularity. The actual resolution available and even the quantity the timers measure depend on the clock associated with each time value.

The implementation must use modified copy semantics for each HighResolutionTime¹⁰⁷ parameter value. The value of each time object should be treated as when it were copied at the time it is passed to the parameter object, but the object reference must also be retained. For instance, the value returned by getCost() must be the same object passed in by setCost(), but any changes made to the time value of the cost must not take effect in the associated ReleaseParameters instance unless they are passed to the parameter object again, e.g. with a new invocation of setCost.

The following table gives the default parameter values for the constructors.

 $^{^{105}}$ Section 9.4.1.2

¹⁰⁶Section 9.4.1.2

 $^{^{107}}$ Section 9.4.1.2

Attribute	Default Value
cost	new Relative $Time(0,0)$
deadline	no default
overrunHandler	None
missHandler	None

Caution: This class is explicitly unsafe for multithreading when being changed. Code that mutates instances of this class should synchronize at a higher level.

Inheritance

```
java.lang.Object
javax.realtime.ReleaseParameters
Interfaces
Cloneable
Serializable
```

6.4.2.9.1 Constructors

ReleaseParameters

Create a new instance of ReleaseParameters. This constructor creates a default ReleaseParameters object, i.e., it is equivalent to ReleaseParameters(null, null, null, null).

Signature

```
protected
  ReleaseParameters()
```

ReleaseParameters(RelativeTime, AsyncEventHandler)

Create a new instance of ReleaseParameters with the given parameter values. This constructor is equivalent to ReleaseParameters(null, deadline, null, missHandler).

Available since RTSJ 2.0

Signature

protected

ReleaseParameters (RelativeTime deadline, AsyncEventHandler missHandler)

ReleaseParameters(RelativeTime, RelativeTime, AsyncEvent-Handler, AsyncEventHandler)

Create a new instance of ReleaseParameters with the given parameter values.

Signature

protected

ReleaseParameters(RelativeTime cost, RelativeTime deadline, AsyncEventHandler

Parameters

cost - Processing time units per release. On implementations which can measure the amount of time a schedulable object is executed, When null, the default value is a new instance of RelativeTime(0,0).

deadline - The latest permissible completion time measured from the release time of the associated invocation of the schedulable. There is no default for deadline in this class. The default must be determined by the subclasses.

overrunHandler - This handler is invoked when an invocation of the schedulable exceeds cost. In the minimum implementation overrunHandler is ignored. When null, no application event handler is executed on cost overrun.

missHandler - This handler is invoked when the run() method of the schedulable is still executing after the deadline has passed. When null, no application event handler is executed on the miss deadline condition.

Throws

java.lang.IllegalArgumentException - when the time value of cost is less than zero, or the time value of deadline is less than or equal to zero or the clock associated with the cost parameters is not the real-time clock.

IllegalAssignmentError - when cost, deadline, overrunHandler, or missHandler cannot be stored in this.

6.4.2.9.2 Methods

clone

Return a clone of this. This method should behave effectively as when it constructed a new object with clones of the high-resolution time values of this.

- The new object is in the current allocation context.
- clone does not copy any associations from this and it does not implicitly bind the new object to a SO.
- The new object has clones of all high-resolution time values (deep copy).
- References to event handlers are copied (shallow copy.)

Available since RTSJ 1.0.1

```
Signature
    public    java.lang.Object clone()

getCost

Gets a reference to the cost.

Signature
    public    javax.realtime.RelativeTime getCost()

Returns
    A reference to cost.
```

getCostOverrunHandler

Gets a reference to the cost overrun handler.

```
Signature

public
javax.realtime.AsyncEventHandler getCostOverrunHandler()

2.0 (Draft 20)
```

Returns

A reference to the associated cost overrun handler.

getDeadline

Gets a reference to the deadline.

```
Signature

public
 javax.realtime.RelativeTime getDeadline()

Returns

A reference to deadline.
```

getDeadlineMissHandler

Gets a reference to the deadline miss handler.

```
\begin{tabular}{ll} Signature & public & \\ & javax.realtime. Async Event Handler get Deadline Miss Handler () \\ Returns & \end{tabular}
```

A reference to the deadline miss handler.

setCost(RelativeTime)

Sets the cost value.

When this parameter object is associated with any schedulable object (by being passed through the schedulable's constructor or set with a method such as Real-timeThread.setReleaseParameters(ReleaseParameters)¹⁰⁸) the cost of those schedulables is altered as specified by each schedulable's respective scheduler.

```
Signature

public

void setCost(RelativeTime cost)

Parameters

108 Section 5.3.2.2.2
```

cost Processing time units per release. On implementations which can measure the amount of time a schedulable is executed, this value is the maximum amount of time a schedulable receives per release. On implementations which cannot measure execution time, it is not possible to determine when any particular object exceeds cost. When null, the default value is a new instance of RelativeTime(0,0).

Throws

IllegalArgumentException when the time value of cost is less than zero, or the clock associated with the cost parameters is not the real-time clock.

IllegalAssignmentError when cost cannot be stored in this.

setCostOverrunHandler(AsyncEventHandler)

Sets the cost overrun handler.

When this parameter object is associated with any schedulable object (by being passed through the schedulable's constructor or set with a method such as Real-timeThread.setReleaseParameters(ReleaseParameters)¹⁰⁹) the cost overrun handler of those schedulables is altered as specified by each schedulable's respective scheduler.

Signature

public

void setCostOverrunHandler(AsyncEventHandler handler)

Parameters 1

handler This handler is invoked when an invocation of the schedulable attempts to exceed cost time units in a release. A null value of handler signifies that no cost overrun handler should be used.

Throws

IllegalAssignmentError when handler cannot be stored in this.

setDeadline(RelativeTime)

Sets the deadline value.

When this parameter object is associated with any schedulable object (by being passed through the schedulable's constructor or set with a method such as Real-timeThread.setReleaseParameters(ReleaseParameters)¹¹⁰) the deadline of those schedulables is altered as specified by each schedulable's respective scheduler.

¹⁰⁹Section 5.3.2.2.2

 $^{^{110}}$ Section 5.3.2.2.2

Signature

public

void setDeadline(RelativeTime deadline)

Parameters

deadline The latest permissible completion time measured from the release time of the associated invocation of the schedulable. The default value of the deadline must be controlled by the classes that extend ReleaseParameters.

Throws

IllegalArgumentException when deadline is null, the time value of deadline is less than or equal to zero, or when the new value of this deadline is incompatible with the scheduler for any associated schedulable.

IllegalAssignmentError when deadline cannot be stored in this.

setDeadlineMissHandler(AsyncEventHandler)

Sets the deadline miss handler.

When this parameter object is associated with any schedulable object (by being passed through the schedulable's constructor or set with a method such as Real-timeThread.setReleaseParameters(ReleaseParameters)¹¹¹) the deadline miss handler of those schedulables is altered as specified by each schedulable's respective scheduler.

Signature

public

void setDeadlineMissHandler(AsyncEventHandler handler)

Parameters

handler This handler is invoked when any release of the schedulable fails to complete before the deadline passes. A null value of handler signifies that no deadline miss handler should be used.

Throws

IllegalAssignmentError when handler cannot be stored in this.

6.4.2.10 RoundRobinScheduler

Class which represents a priority-based round-robin scheduler.

¹¹¹Section 5.3.2.2.2

The default instance of this scheduler (returned by instance()¹¹²) represents the RTSJ-specified round-robin scheduler.

Available since RTSJ 2.0

Inheritance

```
java.lang.Object
javax.realtime.Scheduler
javax.realtime.PriorityScheduler
javax.realtime.RoundRobinScheduler
```

6.4.2.10.1 Methods

instance

Return a reference to the distinguished instance of RoundRobinScheduler which is the RTSJ-specified round-robin scheduler.

```
Signature
```

```
public static
javax.realtime.RoundRobinScheduler instance()
```

Throws

 $Unsupported Operation Exception \ if this platform has no default round-robin scheduler.$

Returns

A reference to the distinguished instance of RoundRobinScheduler

setQuantum(RelativeTime)

Set the quantum of this instance of RoundRobinScheduler. This takes effect at the end of the current quantum.

```
Signature
```

```
public
void setQuantum(RelativeTime quantum)
throws UnsupportedOperationException, IllegalArgumentException
```

 $^{^{112}}$ Section 6.4.2.10.1

Parameters

quantum The new quantum to use. Copy semantics are used for this argument, and future changes to quantum will not affect this scheduler unless it is again passed to setQuantum().

Throws

Unsupported Operation Exception if this scheduler's quantum is not configurable at runtime.

IllegalArgumentException if the provided quantum is null, less than zero, or not appropriate for this platform.

getQuantum

Get the quantum of this instance of RoundRobinScheduler.

```
Signature
```

```
public
javax.realtime.RelativeTime getQuantum()
```

Returns

a newly-allocated RelativeTime containing the currently-configured quantum of this scheduler.

getQuantum(RelativeTime)

Get the quantum of this instance of RoundRobinScheduler.

Signature

```
public
javax.realtime.RelativeTime getQuantum(RelativeTime dest)
```

Parameters

dest return the quantum in dest. When dest is null, allocate a new RelativeTime 113 instance to hold the returned value.

Returns

The currently-configured quantum of this scheduler.

getMaxPriority

¹¹³Section 9.4.1.3

Gets the maximum priority available for a schedulable managed by this scheduler.

```
Signature

public
int getMaxPriority()

Returns

The value of the maximum priority.
```

getMinPriority

Gets the minimum priority available for a schedulable managed by this scheduler.

```
Signature

public

int getMinPriority()

Returns

The minimum priority used by this scheduler.
```

getNormPriority

Gets the normal priority available for a schedulable managed by this scheduler.

```
public
    int getNormPriority()

Returns
    The value of the normal priority.
```

getPolicyName

Gets the policy name of this.

```
Signature

public
 java.lang.String getPolicyName()

Returns

2.0 (Draft 20)
```

The policy name (Fixed Priority Round Robin) as a string.

reschedule(Thread, int)

Promotes a java.lang.Thread to realtime priority under this scheduler. The affected thread will be scheduled as if it were a RealtimeThread¹¹⁴ of the given priority. This does not make the affected thread a RealtimeThread, so it will not have access to facilities reserved for instances of RealtimeThread.

The method Thread.setPriority(int) can be used to reschedule back to the conventional Java priority levels.

```
Signature

public

void reschedule(Thread thread, int priority)

Parameters

thread The thread to promote to realtime scheduling.

priority An integer priority equivalent to a priority set via PriorityParameters<sup>115</sup> on a RealtimeThread.

Throws

IllegalArgumentException when thread is null or priority is not between getMinPriority()<sup>116</sup> and getMaxPriority()<sup>117</sup>, inclusive.
```

6.4.2.11 Scheduler

An instance of Scheduler manages the execution of schedulables.

Subclasses of Scheduler are used for alternative scheduling policies and should define an instance() class method to return the default instance of the subclass. The name of the subclass should be descriptive of the policy, allowing applications to deduce the policy available for the scheduler obtained via Scheduler.getDefaultScheduler¹¹⁸ (e.g., EDFScheduler).

Inheritance

```
java.lang.Object
javax.realtime.Scheduler
```

```
114 Section 5.3.2.2

115 Section 6.4.2.6

116 Section 6.4.2.10.1

117 Section 6.4.2.10.1

118 Section 6.4.2.11.2
```

6.4.2.11.1 Constructors

Scheduler

Create an instance of Scheduler.

Signature

```
protected
  Scheduler()
```

6.4.2.11.2 Methods

getDefaultScheduler

Gets a reference to the default scheduler.

Signature

```
public static
  javax.realtime.Scheduler getDefaultScheduler()
Returns
```

A reference to the default scheduler.

${\bf setDefaultScheduler}({\bf Scheduler})$

Sets the default scheduler. This is the scheduler given to instances of schedulables when they are constructed by a Java thread. The default scheduler is set to the required PriorityScheduler¹¹⁹ at startup.

Signature

¹¹⁹Section 6.4.2.7

```
public static
void setDefaultScheduler(Scheduler scheduler)
```

Parameters

scheduler The Scheduler that becomes the default scheduler assigned to new schedulables created by Java threads. When null nothing happens.

Throws

SecurityException when the caller is not permitted to set the default scheduler.

getPolicyName

Gets a string representing the policy of this. The string value need not be interned, but it must be created in a memory area that does not cause an illegal assignment error when stored in the current allocation context and does not cause a MemoryAccessError¹²⁰ when accessed.

```
Signature

public abstract
    java.lang.String getPolicyName()
```

A name object which is the name of the scheduling policy used by this.

inSchedulableExecutionContext

Determine whether the current calling context is a Schedulable 121 : Realtime-Thread 122 or AbstractAsyncEventHandler 123 .

Available since RTSJ 2.0

```
Signature

public static
boolean inSchedulableExecutionContext()

Returns
```

true when yes and false otherwise.

```
<sup>120</sup>Section 14.2.3.4

<sup>121</sup>Section 6.4.1.2

<sup>122</sup>Section 5.3.2.2

<sup>123</sup>Section 8.4.3.2
```

getCurrentSchedulable

Get the current execution context when called from a $Schedulable^{124}$ execution context.

Available since RTSJ 2.0

```
Signature public static javax.realtime.Schedulable getCurrentSchedulable() Throws ClassCastException when the caller is not a Schedulable ^{125} Returns the current Schedulable ^{126}.
```

6.4.2.12 SchedulingGroup

Inheritance

```
java.lang.Object
java.lang.ThreadGroup
javax.realtime.SchedulingGroup
```

6.4.2.12.1 Constructors

SchedulingGroup(String)

Create a new group with the current ThreadGroup instance as its parent, so long as it is an instance of SchedulingGroup.

Signature

124 Section 6.4.1.2 125 Section 6.4.1.2 126 Section 6.4.1.2

```
public
   SchedulingGroup(String name)
```

throws IllegalStateException, IllegalAssignmentError

Parameters

name is the name of the new group

Throws

IllegalStateException when the parent ThreadGroup instance is not an instance of SchedulingGroup.

 ${\it IllegalAssignmentError}$ when the parent ThreadGroup instance is not assignable to this.

SchedulingGroup(SchedulingGroup, String)

Create a new scheduling group.

Signature

```
public
```

SchedulingGroup(SchedulingGroup parent, String name)

parent

name is the name of the new group

Throws

IllegalStateException when the parent ThreadGroup instance is not an instance of SchedulingGroup.

 ${\it IllegalAssignmentError}$ when the parent ThreadGroup instance is not assignable to this.

6.4.2.12.2 Methods

getMaxSchedulingParameters

Find the upper bound on scheduling importance that tasks in this group may have. For example, when it is an instance of PriorityParameters, it gives the maximum priority any thread in the group may have.

Signature

```
{\tt public} \\ {\tt javax.realtime.SchedulingParameters} \ {\tt getMaxSchedulingParameters} () \\ Returns
```

the scheduling parameter instance denoting the upper bound on the scheduling importance of threads in this group.

setMaxSchedulingParameters(SchedulingParameters)

Set the upper bound on scheduling importance that tasks in this group may have. For example, when it is an instance of PriorityParameters, it sets the maximum priority any thread in the group may have.

Signature

```
public
void setMaxSchedulingParameters(SchedulingParameters parameters)
throws IllegalStateException
```

Parameters 1 4 1

the scheduling parameter instance denoting the new upper bound on the scheduling importance of threads in this group.

Throws

IllegalStateException when parameters are not consistent with the scheduler type.

getScheduler

Find the type of scheduler tasks in this group may use. The scheduler of each thread must be an instance of the type returned. The default is class<Scheduler>, but it may be set to any subtype.

```
public
    java.lang.Class<javax.realtime.Scheduler> getScheduler()
Returns
    the scheduler type
```

setScheduler(java.lang.Class<javax.realtime.Scheduler>)

Limit the schedulers that may be used for tasks in this group.

Signature

```
public
void setScheduler(java.lang.Class<javax.realtime.Scheduler>
type)
```

Parameters

type is the type of scheduler of which the schedulers of all tasks must be instances.

Throws

IllegalStateException when a thread in the group has a scheduler that is not an instance of type or getMaxSchedulingParameters¹²⁷ returns parameters that are inconsistent with the scheduler type.

6.4.2.13 SchedulingParameters

Subclasses of SchedulingParameters (PriorityParameters¹²⁸, ImportanceParameters¹²⁹, and any others defined for particular schedulers) provide the parameters to be used by the Scheduler¹³⁰. Changes to the values in a parameters object affects the scheduling behavior of all the Schedulable¹³¹ objects to which it is bound.

Caution: This class is explicitly unsafe for multithreading when being changed. Code that mutates instances of this class should synchronize at a higher level.

Inheritance

```
java.lang.Object
javax.realtime.SchedulingParameters
Interfaces
Cloneable
Serializable
```

 $^{^{127}}$ Section 6.4.2.12.2

 $^{^{128}}$ Section 6.4.2.6

 $^{^{129}}$ Section 6.4.2.4

 $^{^{130}}$ Section 6.4.2.11

 $^{^{131}}$ Section 6.4.1.2

6.4.2.13.1 Constructors

SchedulingParameters

Create a new instance of SchedulingParameters.

Available since RTSJ 1.0.1

```
Signature
```

```
protected
   SchedulingParameters()
```

6.4.2.13.2 Methods

clone

Return a clone of this. This method should behave effectively as if it constructed a new object with clones of the high-resolution time values of this.

- The new object is in the current allocation context.
- clone does not copy any associations from this and it does not implicitly bind the new object to a SO.
- The new object has clones of all high-resolution time values (deep copy).
- References to event handlers are copied (shallow copy.)

Available since RTSJ 1.0.1

```
Signature
    public
    java.lang.Object clone()
```

2.0 (Draft 20)

6.4.2.14 SporadicParameters

A notice to the scheduler that the associated schedulable's run method will be released aperiodically but with a minimum time between releases.

SporadicParameters

When a reference to a SporadicParameters object is given as a parameter to a schedulable's constructor or passed as an argument to one of the schedulable's setter methods, the SporadicParameters object becomes the release parameters object bound to that schedulable. Changes to the values in the SporadicParameters object affect that schedulable object. When bound to more than one schedulable then changes to the values in the SporadicParameters object affect all of the associated objects. Note that this is a one-to-many relationship and not a many-to-many.

The implementation must use modified copy semantics for each HighResolutionTime¹³² parameter value. The value of each time object should be treated as when it were copied at the time it is passed to the parameter object, but the object reference must also be retained. Only changes to a SporadicParameters object caused by methods on that object cause the change to propagate to all schedulables using the parameter object. For instance, calling setCost on a SporadicParameters object will make the change, then notify that the scheduler that the parameter object has changed. At that point the object is reconsidered for every SO that uses it. Invoking a method on the RelativeTime object that is the cost for this object may change the cost but it does not pass the change to the scheduler at that time. That change must not change the behavior of the SOs that use the parameter object until a setter method on the SporadicParameters object is invoked, or the parameter object is used in setReleaseParameters() or a constructor for an SO.

The following table gives the default parameter values for the constructors.

Attribute	Value
minInterarrival time	No default. A value must be sup-
	plied
cost	new RelativeTime(0,0)
deadline	new RelativeTime(mit)
overrunHandler	None
missHandler	None
MIT violation policy	SAVE
Arrival queue overflow policy	SAVE
Initial arrival queue length	0

 $^{^{132}}$ Section 9.4.1.2

Caution: This class is explicitly unsafe for multithreading when being changed. Code that mutates instances of this class should synchronize at a higher level.

Inheritance

```
java.lang.Object
javax.realtime.ReleaseParameters
javax.realtime.AperiodicParameters
javax.realtime.SporadicParameters
```

6.4.2.14.1 Fields

mitViolationExcept

```
public static final mitViolationExcept
```

Represents the "EXCEPT" policy for dealing with minimum interarrival time violations. Under this policy, when an arrival time for any instance of Schedulable¹³³ which has this as its instance of ReleaseParameters¹³⁴ occurs at a time less then the minimum interarrival time defined here then the fire() method shall throw MITViolationException¹³⁵. Any other associated semantics are governed by the schedulers for the schedulables using these sporadic parameters. When the arrival time is a result of a happening to which the instance of AsyncEventHandler¹³⁶ is bound then the arrival time is ignored.

mitViolationIgnore

```
public static final mitViolationIgnore
```

Represents the "IGNORE" policy for dealing with minimum interarrival time violations. Under this policy, when an arrival time for any instance of Schedulable 137 which has this as its instance of ReleaseParameters 38 occurs at a time less then the minimum interarrival time defined here then the new arrival time is ignored. Any other associated semantics are governed by the schedulers for the schedulables using these sporadic parameters.

```
133 Section 6.4.1.2

134 Section 6.4.2.9

135 Section 14.2.2.6

136 Section 8.4.3.5

137 Section 6.4.1.2

138 Section 6.4.2.9
```

mitViolationSave

public static final mitViolationSave

Represents the "SAVE" policy for dealing with minimum interarrival time violations. Under this policy the arrival time for any instance of Schedulable¹³⁹ which has this as its instance of ReleaseParameters¹⁴⁰ is not compared to the specified minimum interarrival time. Any other associated semantics are governed by the schedulers for the schedulable objects using these sporadic parameters.

mitViolationReplace

public static final mitViolationReplace

Represents the "REPLACE" policy for dealing with minimum interarrival time violations. Under this policy when an arrival time for any instance of Schedulable which has this as its instance of ReleaseParameters occurs at a time less then the minimum interarrival time defined here then the information for this arrival replaces a previous arrival. Any other associated semantics are governed by the schedulers for the schedulables using these sporadic parameters.

6.4.2.14.2 Constructors

SporadicParameters(RelativeTime)

Create a SporadicParameters object. This constructor is equivalent to: SporadicParameters(minInterarrival, null, null, null, null)

Available since RTSJ 1.0.1

Signature

public

SporadicParameters(RelativeTime minInterarrival)

```
<sup>139</sup>Section 6.4.1.2

<sup>140</sup>Section 6.4.2.9

<sup>141</sup>Section 6.4.1.2
```

 $^{^{142}}$ Section 6.4.2.9

SporadicParameters(RelativeTime, RelativeTime)

Create a SporadicParameters object. This constructor is equivalent to: SporadicParameters(minInterarrival, null, deadline, null, null)

Available since RTSJ 2.0

Signature

public

SporadicParameters(RelativeTime minInterarrival, RelativeTime deadline)

SporadicParameters(RelativeTime, RelativeTime, AsyncEvent-Handler)

Create a SporadicParameters object. This constructor is equivalent to: SporadicParameters(minInterarrival, null, deadline, null, missHandler) Available since RTSJ 2.0

Signature

public

SporadicParameters(RelativeTime minInterarrival, RelativeTime deadline, AsyncEvent

SporadicParameters(RelativeTime, RelativeTime, RelativeTime, AsyncEventHandler, AsyncEventHandler)

Create a SporadicParameters object.

Available since RTSJ 2.0

Signature

public

SporadicParameters(RelativeTime minInterarrival, RelativeTime cost, RelativeTime c

2.0 (Draft 20)

minInterarrival The release times of the schedulable will occur no closer than this interval. This time object is treated as if it were copied. Changes to minInterarrival will not effect the SporadicParameters object. There is no default value. When minInterarrival is null an illegal argument exception is thrown.

cost Processing time per release. On implementations which can measure the amount of time a schedulable is executed, this value is the maximum amount of time a schedulable receives per release. When null, the default value is a new instance of RelativeTime(0,0).

deadline The latest permissible completion time measured from the release time of the associated invocation of the schedulable. When null, the default value is a new instance of RelativeTime(mit).

overrunHandler This handler is invoked when an invocation of the schedulable exceeds cost. Not required for minimum implementation. When null no overrun handler will be used.

missHandler This handler is invoked when the run() method of the schedulable is still executing after the deadline has passed. When null, no deadline miss handler will be used.

Throws

IllegalArgumentException when minInterarrival is null or its time value is not greater than zero, or the time value of cost is less than zero, or the time value of deadline is not greater than zero, or when the clocks associated with deadline and minInterarrival parameters are not identical.

IllegalAssignmentError when minInterarrival, cost, deadline, overrun-Handler or missHandler cannot be stored in this.

6.4.2.14.3 Methods

setMitViolationBehavior(String)

Sets the behavior of the arrival time queue in the case where the new arrival time is closer to the previous arrival time than the minimum interarrival time given in this.

Values of behavior are compared using reference equality (==) not value equality (equals()).

```
Signature

public

void setMitViolationBehavior(String behavior)

Parameters

behavior A string representing the behavior.
```

Throws

IllegalArgumentException when behavior is not one of the final MIT violation behavior values defined in this class.

getMitViolationBehavior

Gets the arrival time queue behavior in the event of a minimum interarrival time violation.

```
Signature

public

java.lang.String getMitViolationBehavior()

Returns
```

The minimum interarrival time violation behavior as a string.

getMinimumInterarrival

Gets the minimum interarrival time.

```
public
    javax.realtime.RelativeTime getMinimumInterarrival()
Returns
The minimum interarrival time.
```

setMinimumInterarrival(RelativeTime)

Set the minimum interarrival time.

```
Signature
public
void setMinimumInterarrival(RelativeTime minimum)

2.0 (Draft 20)
```

6 Scheduling 183

Parameters

minimum The release times of the schedulable will occur no closer than this interval.

Throws

IllegalArgumentException when minimum is null or its time value is not greater than zero.

IllegalAssignmentError when minimum cannot be stored in this.

6.5 Rationale

As specified, the required semantics of this section establish a scheduling policy that is very similar to the scheduling policies found on the vast majority of realtime operating systems and kernels in commercial use today. The semantics for the base scheduler accommodate existing practice, which is a stated goal of the effort.

There is an important division between priority schedulers that force periodic context switching between tasks at the same priority, and those that do not cause these context switches. By not specifying time slicing[1] behavior this specification calls for the latter type of priority scheduler. In POSIX terms, SCHED_FIFO meets the RTSJ requirements for the base scheduler, but SCHED_RR does not meet those requirements.

Although a system may not implement the first release (start) of a schedulable as unblocking that schedulable, under the base scheduler those semantics apply; i.e., the schedulable is added to the tail of the queue for its active priority.

Some research shows that, given a set of reasonable common assumptions, 32 distinct priority levels are a reasonable choice for close-to-optimal scheduling efficiency when using the rate-monotonic priority assignment algorithm on a single processor system (256 priority levels provide better efficiency). This specification requires at least 28 distinct priority levels as a compromise noting that implementations of this specification will exist on systems with logic executing outside of the Java Virtual Machine and may need priorities above, below, or both for system activities.

The default behavior for implementations that support cost monitoring and enforcement is that a schedulable receives no more than cost units of CPU time during each release. The programmer must explicitly change the cost attribute to override the scheduler. The RTSJ allows schedulables to self suspend during a release, in addition to that which might be necessary to acquire a lock. These self suspensions must be time bounded. Any self suspension which is not time bounded may undermine the cost enforcement model specified in this document, as it may result in a schedulable suspending beyond its next release event. This can result in more time being allocated than any associated schedulability analysis might assume. See Dos Santos and Wellings for a full discussion on the problem [4].

184 6.5 Rationale

Cost enforcement may be deferred while the overrun schedulable holds locks that are out of application control, such as locks used to protect garbage collection. Applications should include the resulting jitter in any analysis that depends on cost enforcement.

When a schedulable is enforced because of cost overrun in a processing group the enforced priority is used for scheduling instead of the schedulable's base priority. The enforced priority's application is limited. The enforced priority is not returned as the schedulable's priority from methods such as getPriority(), and the semantics of the active priority continue to operate when a schedulable is enforced.

6.5.1 Multiprocessor Support

The support that the RTSJ provides for multiprocessor systems is primarily constrained by the support it can expect from the underlying operating system. The following have had the most impact on the level of support that has been specified.

- The notion of processor affinity is common across operating systems and has become the accepted way to specify the constraints on which processor a thread can execute. In some sense, processor affinities can be viewed as additional release or scheduling parameters. However, to add them to the parameter classes requires the support to be distributed throughout the specification with a proliferation of new constructor methods. To avoid this, support is grouped together within the Affinity class. The class also provides the addition of processor affinity support to Java threads without modifying the thread object's visible API.
- The range of processors on which global scheduling is possible is dictated by the operating system. For SMP architectures, global scheduling across all the processors in the system is typically supported. However, an application and an operator can constrain threads and processes to execute only within a subset of the processors. As the number of processors increase, the scalability of global scheduling is called into question. Hence, for NUMA architectures some partitioning of the processors is likely to performed by the OS. Hence, global scheduling across all processors will not be possible in these systems. For these reasons, the RTSJ supports an array of predefined affinities. These are implementation-defined. They can be used either to reflect the scheduling arrangement of the underlying OS or they can be used by the system designer to impose defaults for, say, Java threads, non-heap realtime schedulables etc. A program is only allowed to dynamically create new affinities with cardinality of one. This restriction reflects the concern that not all operating systems will support multiprocessor affinities.
- Many OSs give system operators command-level dynamic control over the set of processors allocated to a processes. Consequently, the realtime JVM has

6 Scheduling 185

no control over whether processors are dynamically added or removed from its OS process. Predictability is a prime concern of the RTSJ. Clearly, dynamic changes to the allocated processors will have a dramatic, and possibly catastrophic, effect on the ability of the program to meet timing requirements. Hence, the RTSJ assumes that the processor set allocated to the RTSJ process does not change during its execution. A system that is capable of such manipulations should not exercise it on RTSJ processes.

• The reason the expert group decided not to add affinities to scheduling parameters is that ASEH do not have a single server thread, hence forcing a particular affinity would complicate the implementation.

6.5.2 Impact of Clock Granularity

All time-triggered computation can suffer from release jitter. This is defined to be the variation in the actual time the computation becomes available for execution from its scheduled release time. The amount of release jitter depends on two factors. The first is the granularity of the clock/timer used to trigger the release. For example, a periodic event handler that is due to be released at absolute time T will actually be release at time $T + \delta$. δ is the difference between T and the first time the timer clock advances to T0, where T0 >= T. The upper bound of δ is the value returned from calling the getResolution method of the associated clock. It is for this reason that the implementation of release times for periodic activities must use absolute rather than relative time values, in order to avoid the drift accumulating.

The second contribution to release jitter is also related to the clock/timer. It is the duration of interval between T0 being signaled by the clock/timer and the time this event is noticed by the underlying operating system or platform (perhaps because interrupts have been disabled). A compliant implementation of SCJ should document the maximum value of δ for the realtime clock.

6.5.3 Deadline Miss Detection

Although RTSJ supports deadline miss detection, it is important to understand the intrinsic limitations of the facility. The SCJ facility is supported using a time-triggered event. All time-triggered computation can suffer from release jitter. Hence, any deadline miss handler may not be released until sometime after the deadline has expired. The handlers actual execution will depend on its priority relative to other schedulables.

A related limitation is that a deadline can be missed but not detected. This can occur when the deadline has been set at a smaller granularity than the detecting timer. Consider an absolute deadline of D. Suppose that the next absolute time that the timer can recognize is $D + \delta$. When the associate thread finishes after

186 6.5 Rationale

D but before $D + \delta$, it will have missed its deadline, but this miss will have been undetected.

A third limitation is due to the inherent race condition that is present when checking for deadline misses. A deadline miss is defined to occur when a schedulable has not completed the computation associated with its release before its deadline. This completion event is signalled in the application code by the return of the handleAsyncEvent method or a call to waitForNextRelease etc. When this occurs, the infrastructure reschedules/cancels the timing event that signals the miss of a deadline. This is clearly a race condition. The timer event could fire between the last statement the completion event and the rescheduling/canceling of the timer event. Hence a deadline miss could be signalled when arguably the application had performed all of its computation.

Chapter 7

Synchronization

7.1 Overview

One of the strength of Java is its language support for multithreading. This requires synchronization. In a realtime system, there are additional requirement on this synchronization. Therefore this specification not only tightens the semantics of the synchronization declarations in just, but it also provides addition classes that specifically manage synchronization.

This specification strengthens the semantics of Java synchronized code by mandating monitor execution eligibility control, commonly referred to as priority inversion control. The MonitorControl class is defined as the superclass of all such execution eligibility control algorithms. Its subclasses PriorityInheritance and PriorityCeilingEmulation avoid unbounded priority inversions, which would be unacceptable in realtime systems.

The classes described below provide two main services.

- They enable the setting of a priority inversion control policy either as the default or for specific objects.
- They also provide wait-free communication between schedulables (especially instances of Schedulable, whose mayUseHeap is false) and regular Java threads.

These classes establish a framework for priority inversion management that applies to priority-oriented schedulers in general, and a specific set of requirements for the base priority scheduler. The wait-free queue classes provide safe, concurrent access to data shared between instances of NoHeapRealtimeThread and schedulable objects subject to garbage collection delays.

7.3 Definitions

7.2 Definitions

Scheduling Inversion is when a more important task is blocked by a less important task. This is usually caused by synchronization, where a more important task must wait for a less important task to release a required resource, which can in turn be blocked by a task of intermediate importance. The classical example in priority inversion in a system with a priority-based scheduler.

An object A, that has been assigned (either by default or via an explicit method call) to the MonitorControlPolicy α , then A is said to be *governed by* α .

7.3 Semantics

Synchronization semantics has two main aspects: the monitor control and scheduling. The first determins which inversion avoidance is to use. The second determines how it is done. Since, only priority-based schedulers are defined in the RTSJ, the semantics is only completely defined for priority-based schedulers.

7.3.1 Monitor Control

The specification provides for two monitor control policies with the following semantics.

- 1. The initial default monitor control policy shall be PriorityInheritance. The default policy can be altered by using the setMonitorControl() method.
- 2. Notwithstanding the preceding rule, an RTSJ implementation may allow the program to establish a different initial default monitor control policy at JVM startup. The program can query the initial default monitor control policy via the method RealtimeSystem.getInitialMonitorControl.
- 3. The PriorityCeilingEmulation monitor control policy is also required.
- 4. An implementation that provides any additional MonitorControl subclasses must document their effects, particularly with respect to priority inversion control.
- 5. An object's monitor control policy affects *each* entity that attempts to lock the object; i.e., regular Java threads as well as schedulables.
- 6. When a task, thread or schedulable, enters synchronized code, the target object's monitor control policy must be supported by the thread or schedulable's scheduler; otherwise an IllegalThreadStateException is thrown. An implementation that defines a new MonitorControl subclass must document which (if any) schedulers do not support this policy.

7 Synchronization 189

7.3.2 Priority Schedulers

The two schedulers provided by the RTSJ must both handle synchronization in the same way. All tasks governed by these schedulers are subject to the following semantics when they synchronize on objects governed by monitor control policies defined in this section.

- 1. Each thread or schedulable has a base priority and an active priority. A thread or schedulable that holds a lock on a PCE-governed object also has a ceiling priority.
- 2. The base priority for a thread or schedulable t is initially the priority that t has when it is created. The base priority is updated (immediately) as an effect of invoking any of the following methods:
 - (a) pparam.setPriority(prio), where t is a schedulable with pparams as its SchedulingParameters and pparams is an instance of PriorityParameters or one of its sublclasses; the new base priority is prio
 - (b) t.setSchedulingParameters(pparams), where t is a schedulable and pparams is an instance of PriorityParameters; the new base priority is pparams.getPriority()
 - (c) t.setPriority(prio), when t is a schedulable object, the new base priority is prio and when it is a Java thread, the new base priority is the lesser of prio, and the maximum priority for t's thread group.
- 3. When the task t does not hold any locks, its active priority is the same as its base priority. In such a situation, modification of the priority of t through an invocation of any of the above priority-setting methods for t causes t to be placed at the tail of its relevant queue (ready, blocked on a particular object, etc.) at its new priority, when the new priority is higher than the old priority, and at the beginning otherwise.
- 4. When task t holds one or more locks, then t has a set of *priority sources*. The *active priority* for t at any point in time is the maximum of the priorities associated with all of these sources. The priority sources resulting from the monitor control policies defined in this section, and their associated priorities for a schedulable t, are as follows:
 - (a) Source t itself
 Associated Priority The base priority for t

 Note This may have been changed (either synchronously or asynchronously) while t has been holding its lock(s).
 - (b) 2.0 (Draft 20)

190 7.3 Semantics

Source Each object locked by t and governed by a Prior-

ityCeilingEmulation policy

Associated Priority The maximum value ceil, where ceil is the ceiling

of a PriorityCeilingEmulation policy governing

an object locked by t.

Note This value is also referred to as the ceiling priority

for t.

(c) Source Each task attempting to synchronize on an object

locked by t and governed by a PriorityInheri-

tance policy

Associated Priority The maximum active priority over all such threads

and schedulables

Note This rule accounts for recursive priority inheritance.

(d) Source Each task attempting to synchronize on an ob-

ject locked by t and governed by a Priority-

CeilingEmulation policy.

Associated Priority The maximum active priority over all such threads

and schedulables

Note This rule, which in effect allows a Priority-

CeilingEmulation lock to behave like a Priority-Inheritance lock, helps avoid unbounded priority inversions that could otherwise occur in the presence of nested synchronizations involving a mix of PriorityCeilingEmulation and PriorityInher-

itance policies.

5. The addition of a priority source for t either leaves t's active priority unchanged, or increases it. When t's active priority is unchanged, t's status in its relevant queue(s), e.g., blocked waiting for some object, is not affected. When t's active priority is increased, t is placed at the tail of the relevant queue(s) at its new active priority level.

6. The removal of a priority source for T either leaves T's active priority unchanged, or decreases it. When T's active priority is unchanged, then T's status in its relevant queue, e.g., blocked waiting for some object, is not affected. When T's active priority is decreased and T is either ready or running, then T must be placed at the head of the ready queue at its new active priority level, When T's active priority is decreased and T is blocked, then T is queued at the end of the queue for the new priority when it become unblocked.

The above rules have four main consequences.

1. A thread or schedulable t's priority sources from 4b are added and removed synchronously; i.e., they are established based on t's entering or leaving synchronized code. However, priority sources from 4a, refsync:inherit, and 4d may

7 Synchronization 191

be added and removed asynchronously, as an effect of actions by other threads or schedulables.

- 2. A task holding only one lock, when it releases this lock, has its active priority set to its base priority.
- 3. A task's active priority is never less than its base priority.
- 4. When a task blocks at a call of obj.wait(), it releases the lock on obj and hence relinquishes the priority source(s) based on obj's monitor control policy. The task will be queued at a new active priority that reflects the loss of these priority sources.

Since base priorities may be shared (i.e., the same PriorityParameters object may be associated with multiple schedulables), a given base priority may be the active priority for some but not all of its associated schedulables. It is a consequence of other rules that, when a thread or schedulable t attempts to synchronize on an object obj governed by a PriorityCeilingEmulation policy with ceiling ceil, then t's active priority may exceed ceil but t's base priority must not. In contrast, once t has successfully synchronized on obj, then t's base priority may also exceed obj's monitor control policy's ceiling. Note that either or both of t's base priority and obj's monitor control policy may have been dynamically modified.

7.3.3 Additional Schedulers

Schedulers based on criteria other than priority, for example, deadline in a deadline first scheduler, must consider how synchronization is handled to avoid scheduling inversion. Such a scheduler must conform to the following semantics for tasks managed by that scheduler when they synchronize on objects with the monitor control policies defined above.

- 1. An implementation that defines a new Scheduler subclass must document which (if any) monitor control policies the new scheduler does not support.
- 2. An implementation must document how, if at all, the semantics of synchronization differ from the rules defined for the default PriorityInheritance instance and for the PriorityCeilingEmulation policy. It must supply documentation for the behavior of the new scheduler with priority inheritance and priority ceiling emulation protocol equivalent to the semantics for the default priority scheduler found in the previous section.

7.4 Package javax.realtime

7.4.1 Classes

7.4.1.1 MonitorControl

Abstract superclass for all monitor control policy objects.

Inheritance

```
java.lang.Object
javax.realtime.MonitorControl
```

7.4.1.1.1 Constructors

MonitorControl

Invoked from subclass constructors.

Signature

```
protected
  MonitorControl()
```

7.4.1.1.2 Methods

getMonitorControl(Object)

Gets the monitor control policy of the given instance of Object.

```
Signature

public static

javax.realtime.MonitorControl getMonitorControl(Object obj)

Parameters
```

2.0 (Draft 20)

obj The object being queried.

Throws

IllegalArgumentException when obj is null.

Returns

The monitor control policy of the obj parameter.

getMonitorControl

Gets the current default monitor control policy.

```
Signature

public static
 javax.realtime.MonitorControl getMonitorControl()

Returns
```

The default monitor control policy object.

setMonitorControl(MonitorControl)

Sets the *default monitor control policy*. This policy does not affect the monitor control policy of any already created object, it will, however, govern any object subsequently constructed, until either:

- 1. a new "per-object" policy is set for that object. This will alter the monitor control policy for a single object without changing the default policy.
- 2. a new default policy is set.

Like the per-object method (see setMonitorControl(Object, MonitorControl)¹, the setting of the default monitor control policy occurs immediately.

Available since RTSJ 1.0.1 The return type is changed from void to MonitorControl.

```
Signature

public static
javax.realtime.MonitorControl setMonitorControl(MonitorControl
policy)

Parameters
policy The new monitor control policy. When null nothing happens.

Throws

1 Section 7.4.1.1.2
```

SecurityException when the caller is not permitted to alter the default monitor control policy.

IllegalArgumentException when policy is not in immortal memory.

Unsupported Operation Exception when policy is not a supported monitor control policy.

Returns

The default MonitorControl policy that was replaced.

setMonitorControl(Object, MonitorControl)

Immediately sets policy as the monitor control policy for obj.

A thread or schedulable that is queued for the lock associated with obj, or is in obj's wait set, is not rechecked (e.g., for a CeilingViolationException) under policy, either as part of the execution of setMonitorControl or when it is awakened to (re)acquire the lock.

The thread or schedulable invoking **setMonitorControl** must already hold the lock on obj.

Available since RTSJ 1.0.1 The return type is changed from void to MonitorControl.

Signature

```
public static
javax.realtime.MonitorControl setMonitorControl(Object obj,
MonitorControl policy)
```

Parameters

obj The object that will be governed by the new policy.

policy The new policy for the object. When null nothing will happen.

Throws

IllegalArgumentException Thrown when obj is null or policy is not in immortal memory.

Unsupported Operation Exception when policy is not a supported monitor control policy.

IllegalMonitorStateException when the caller does not hold a lock on obj.

Returns

The current MonitorControl policy for obj, which will be replaced.

2.0 (Draft 20)

7.4.1.2 PriorityCeilingEmulation

Monitor control class specifying the use of the priority ceiling emulation protocol (also known as the "highest lockers" protocol). Each PriorityCeilingEmulation instance is immutable; it has an associated *ceiling*, initialized at construction and queryable but not updatable thereafter.

When a thread or schedulable synchronizes on a target object governed by a PriorityCeilingEmulation policy, then the target object becomes a priority source for the thread or schedulable object. When the object is unlocked, it ceases serving as a priority source for the thread or schedulable. The practical effect of this rule is that the thread or schedulable's active priority is boosted to the policy's ceiling when the object is locked, and is reset when the object is unlocked. The value that it is reset to may or may not be the same as the active priority it held when the object was locked; this depends on other factors (e.g. whether the thread or schedulable's base priority was changed in the interim).

The implementation must perform the following checks when a thread or schedulable t attempts to synchronize on a target object governed by a PriorityCeilingEmulation policy with ceiling ceil:

- t's base priority does not exceed ceil
- t's ceiling priority (when t is holding any other PriorityCeilingEmulation locks) does not exceed ceil.

Thus for any object targetObj that will be governed by priority ceiling emulation, the programmer needs to provide (via MonitorControl.setMonitorControl(Object, MonitorControl)²) a PriorityCeilingEmulation policy whose ceiling is at least as high as the maximum of the following values:

- the highest base priority of any thread or schedulable that could synchronize on targetObj
- the maximum ceiling priority value that any thread or schedulable object could have when it attempts to synchronize on targetObj.

More formally:

• When a thread or schedulable t whose base priority is p1 attempts to synchronize on an object governed by a PriorityCeilingEmulation policy with ceiling p2, where p1>p2, then a CeilingViolationException is thrown in t. A CeilingViolationException is likewise thrown in t when t is holding a PriorityCeilingEmulation lock and has a ceiling priority exceeding p2.

The values of p1 and p2 are passed to the constructor for the exception and may be queried by an exception handler.

²Section 7.4.1.1.2

A consequence of the above rule is that a thread or schedulable may nest synchronizations on PriorityCeilingEmulation-governed objects as long as the ceiling for the inner lock is not less than the ceiling for the outer lock.

The possibility of nested synchronizations on objects governed by a mix of PriorityInheritance and PriorityCeilingEmulation policies requires one other piece of behavior in order to avoid unbounded priority inversions. When a thread or schedulable holds a PriorityInheritance lock, then any PriorityCeilingEmulation lock that it either holds or attempts to acquire will exhibit priority inheritance characteristics. This rule is captured above in the definition of priority sources (4.d).

When a thread or schedulable t attempts to synchronize on a PriorityCeilingEmulation-governed object with ceiling ceil, then ceil must be within the priority range allowed by t's scheduler; otherwise, an IllegalThreadStateException is thrown. Note that this does not prevent a regular Java thread from synchronizing on an object governed by a PriorityCeilingEmulation policy with a ceiling higher than 10.

The priority ceiling for an object obj can be modified by invoking MonitorControl.setMonitorControl(obj, newPCE) where newPCE's ceiling has the desired value.

See also ${\tt MonitorControl^3\ PriorityInheritance^4},$ and ${\tt CeilingViolationException^5}.$

Inheritance

java.lang.Object javax.realtime.MonitorControl javax.realtime.PriorityCeilingEmulation

7.4.1.2.1 Methods

instance(int)

Return a PriorityCeilingEmulation object with the specified ceiling. This object is in ImmortalMemory. All invocations with the same ceiling value return a reference to the same object.

Available since RTSJ 1.0.1

³Section 7.4.1.1

⁴Section 7.4.1.3

 $^{^5}$ Section 14.2.2.2

```
Signature

public static
    javax.realtime.PriorityCeilingEmulation instance(int ceiling)

Parameters
    ceiling Priority ceiling value.

Throws

IllegalArgumentException when ceiling is outside of the range of permitted priority values (e.g., less than PriorityScheduler.instance().getMinPriority() or greater than PriorityScheduler.instance().getMaxPriority() for the base scheduler).
```

getCeiling

Gets the priority ceiling for this PriorityCeilingEmulation object.

Available since RTSJ 1.0.1

```
Signature

public

int getCeiling()

Returns

The priority ceiling.
```

getMaxCeiling

Gets a PriorityCeilingEmulation object whose ceiling is PriorityScheduler.instance().get This method returns a reference to a PriorityCeilingEmulation object allocated in immortal memory. All invocations of this method return a reference to the same object.

Available since RTSJ 1.0.1

```
Signature \\ \text{public static} \\ \text{javax.realtime.PriorityCeilingEmulation getMaxCeiling()} \\ Returns
```

A PriorityCeilingEmulation object whose ceiling is PriorityScheduler.instance().getMaxPri

7.4.1.3 PriorityInheritance

Singleton class specifying use of the priority inheritance protocol. When a thread or schedulable t1 attempts to enter code that is synchronized on an object obj governed by this protocol, and obj is currently locked by a lower-priority thread or schedulable t2, then

- 1. When t1's active priority does not exceed the maximum priority allowed by t2's scheduler, then t1 becomes a priority source for t2; t1 ceases to serve as a priority source for t2 when either t2 releases the lock on obj, or t1 ceases attempting to synchronize on obj (e.g., when t1 incurs an ATC).
- 2. Otherwise (i.e., t1's active priority exceeds the maximum priority allowed by t2's scheduler), an IllegalThreadStateException is thrown in t1.

Note on the 2nd rule: throwing the exception in t1, rather than in t2, ensures that the exception is synchronous.

See also MonitorControl⁶ and PriorityCeilingEmulation⁷

Inheritance

```
javax.realtime.MonitorControl
javax.realtime.PriorityInheritance
```

7.4.1.3.1 Methods

instance

Return a reference to the singleton PriorityInheritance.

This is the default MonitorControl policy in effect at system startup.

The PriorityInheritance instance shall be allocated in ImmortalMemory.

```
Signature
```

```
public static
javax.realtime.PriorityInheritance instance()
```

 $^{^6}$ Section 7.4.1.1

 $^{^7}$ Section 7.4.1.2

7.4.1.4 WaitFreeDequeue

A WaitFreeDequeue encapsulates a WaitFreeWriteQueue and a WaitFreeRead-Queue. Each method on a WaitFreeDequeue corresponds to an equivalent operation on the underlying WaitFreeWriteQueue or WaitFreeReadQueue.

Incompatibility with V1.0: Three exceptions previously thrown by the constructor have been deleted from the throws clause. These are:

- java.lang.IllegalAccessException,
- java.lang.ClassNotFoundException, and
- java.lang.InstantiationException.

Including these exceptions on the throws clause was an error. Their deletion may cause compile-time errors in code using the previous constructor. The repair is to remove the exceptions from the catch clause around the constructor invocation.

WaitFreeDequeue is one of the classes allowing NoHeapRealtimeThreads and regular Java threads to synchronize on an object without the risk of a NoHeapRealtimeThread incurring Garbage Collector latency due to priority inversion avoidance management.

Deprecated since RTSJ version as of RTSJ 1.0.1

Inheritance

java.lang.Object javax.realtime.WaitFreeDequeue

7.4.1.5 WaitFreeReadQueue

A queue that can be non-blocking for consumers. The WaitFreeReadQueue class is intended for single-reader multiple-writer communication, although it may also be used (with care) for multiple readers. A reader is generally an instance of NoHeap-RealtimeThread⁸, and the writers are generally regular Java threads or heap-using realtime threads or schedulables. Communication is through a bounded buffer of Objects that is managed first-in-first-out. The principal methods for this class are write and read

• The write method appends a new element onto the queue. It is synchronized, and blocks when the queue is full. It may be called by more than one writer, in which case, the different callers will write to different elements of the queue.

 $^{^8}$ Section 15.3.3.3

• The read method removes the oldest element from the queue. It is not synchronized and does not block; it will return null when the queue is empty. Multiple reader threads or schedulables are permitted, but when two or more intend to read from the same WaitFreeWriteQueue they will need to arrange explicit synchronization.

For convenience, and to avoid requiring a reader to poll until the queue is non-empty, this class also supports instances that can be accessed by a reader that blocks on queue empty. To obtain this behavior, the reader needs to invoke the waitForData() method on a queue that has been constructed with a notify parameter set to true.

WaitFreeReadQueue is one of the classes allowing NoHeapRealtimeThreads and regular Java threads to synchronize on an object without the risk of a NoHeapRealtimeThread incurring Garbage Collector latency due to priority inversion avoidance management. *Incompatibility with V1.0:* Three exceptions previously thrown by the constructor have been deleted. These are

- java.lang.IllegalAccessException,
- java.lang.ClassNotFoundException, and
- java.lang.InstantiationException.

These exceptions were in error. Their deletion may cause compile-time errors in code using the previous constructor. The repair is to remove the exceptions from the catch clause around the constructor invocation.

Inheritance

```
java.lang.Object
javax.realtime.WaitFreeReadQueue
```

7.4.1.5.1 Constructors

WaitFreeReadQueue(Runnable, Runnable, int, MemoryArea, boolean)

Constructs a queue containing up to maximum elements in memory. The queue has an unsynchronized and nonblocking read() method and a synchronized and blocking write() method.

The writer and reader parameters, when non-null, are checked to insure that they are compatible with the MemoryArea specified by memory (when non-null.) When memory is null and both Runnables are non-null, the constructor will select the nearest common scoped parent memory area, or when there is no such scope it will use immortal memory. When all three parameters are null, the queue will be allocated in immortal memory.

reader and writer are not necessarily the only threads or schedulable objects that will access the queue; moreover, there is no check that they actually access the queue at all.

Note: that the wait free queue's internal queue is allocated in memory, but the memory area of the wait free queue instance itself is determined by the current allocation context.

Signature

public

WaitFreeReadQueue(Runnable writer, Runnable reader, int maximum, MemoryArea m

throws IllegalArgumentException, MemoryScopeException, InaccessibleAreaException

Parameters

writer An instance of Runnable or null.

reader An instance of Runnable or null.

maximum The maximum number of elements in the queue.

memory The MemoryArea⁹ in which internal elements are allocated.

notify A flag that establishes whether a reader is notified when the queue becomes non-empty.

Throws

IllegalArgumentException when an argument holds an invalid value. The writer argument must be null, a reference to a Thread, or a reference to a schedulable (a RealtimeThread, or an AsyncEventHandler.) The reader argument must be null, a reference to a Thread, or a reference to a schedulable. The maximum argument must be greater than zero.

Inaccessible Area Exception when memory is a scoped memory that is not on the caller's scope stack.

MemoryScopeException when either reader or writer is non-null and the memory argument is not compatible with reader and writer with respect to the assignment and access rules for memory areas.

Wait Free Read Queue (Runnable, Runnable, int, Memory Area)

⁹Section 11.4.2.3

Constructs a queue containing up to maximum elements in memory. The queue has an unsynchronized and nonblocking read() method and a synchronized and blocking write() method.

The writer and reader parameters, when non-null, are checked to insure that they are compatible with the MemoryArea specified by memory (when non-null.) When memory is null and both Runnables are non-null, the constructor will select the nearest common scoped parent memory area, or when there is no such scope it will use immortal memory. When all three parameters are null, the queue will be allocated in immortal memory.

reader and writer are not necessarily the only threads or schedulables that will access the queue; moreover, there is no check that they actually access the queue at all.

Note: that the wait free queue's internal queue is allocated in memory, but the memory area of the wait free queue instance itself is determined by the current allocation context.

Signature

public

WaitFreeReadQueue(Runnable writer, Runnable reader, int maximum, MemoryArea memory

throws IllegalArgumentException, MemoryScopeException, InaccessibleAreaException

Parameters

writer An instance of Runnable or null.

reader An instance of Runnable or null.

maximum The maximum number of elements in the queue.

memory The MemoryArea¹⁰ in which this object and internal elements are allocated.

Throws

IllegalArgumentException when an argument holds an invalid value. The writer argument must be null, a reference to a Thread, or a reference to a schedulable (a RealtimeThread, or an AsyncEventHandler.) The reader argument must be null, a reference to a Thread, or a reference to a schedulable. The maximum argument must be greater than zero.

MemoryScopeException when either reader or writer is non-null and the memory argument is not compatible with reader and writer with respect to the assignment and access rules for memory areas.

 $^{^{10}}$ Section 11.4.2.3

Inaccessible Area Exception when memory is a scoped memory that is not on the caller's scope stack.

WaitFreeReadQueue(int, MemoryArea, boolean)

Constructs a queue containing up to maximum elements in memory. The queue has an unsynchronized and nonblocking read() method and a synchronized and blocking write() method.

Note: that the wait free queue's internal queue is allocated in memory, but the memory area of the wait free queue instance itself is determined by the current allocation context.

Available since RTSJ 1.0.1

Signature

public

WaitFreeReadQueue(int maximum, MemoryArea memory, boolean notify)

throws IllegalArgumentException, InaccessibleAreaException

Parameters

maximum The maximum number of elements in the queue.

memory The MemoryArea¹¹ in which this object and internal elements are allocated.

notify A flag that establishes whether a reader is notified when the queue becomes non-empty.

Throws

IllegalArgumentException when the maximum argument is less than or equal to zero, or memory is null.

InaccessibleAreaException when memory is a scoped memory that is not on the caller's scope stack.

WaitFreeReadQueue(int, boolean)

Constructs a queue containing up to maximum elements in immortal memory. The queue has an unsynchronized and nonblocking read() method and a synchronized and blocking write() method.

¹¹Section 11.4.2.3

Available since RTSJ 1.0.1

Signature

```
public
```

WaitFreeReadQueue(int maximum, boolean notify)

throws IllegalArgumentException

Parameters

maximum The maximum number of elements in the queue.

notify A flag that establishes whether a reader is notified when the queue becomes non-empty.

Throws

IllegalArgumentException when the maximum argument is less than or equal to zero.

7.4.1.5.2 Methods

clear

Sets this to empty.

Note: This method needs to be used with care. Invoking clear concurrently with read or write can lead to unexpected results.

Signature

```
public
void clear()
```

isEmpty

Queries the queue to determine if this is empty.

Note: This method needs to be used with care since the state of the queue may change while the method is in progress or after it has returned.

```
Signature

public
boolean isEmpty()

Returns

true when this is empty; false when this is not empty.
```

isFull

Queries the system to determine if this is full.

Note: This method needs to be used with care since the state of the queue may change while the method is in progress or after it has returned.

```
Signature

public
boolean isFull()

Returns

true when this is full; false when this is not full.
```

read

Reads the least recently inserted element from the queue and returns it as the result, unless the queue is empty. When the queue is empty, null is returned.

```
public
    java.lang.Object read()
Returns
The java.lang.Object read, or else null when this is empty.
```

size

Queries the queue to determine the number of elements in this.

Note: This method needs to be used with care since the state of the queue may change while the method is in progress or after it has returned.

```
Signature public
```

int size()

Returns

The number of positions in this occupied by elements that have been written but not yet read.

waitForData

When this is empty block until a writer inserts an element.

Note: When there is a single reader and no asynchronous invocation of clear, then it is safe to invoke read after waitForData and know that read will find the queue non-empty.

Implementation note: To avoid reader and writer synchronizing on the same object, the reader should not be notified directly by a writer. (This is the issue that the non-wait queue classes are intended to solve).

Available since RTSJ 1.0.1 InterruptedException was added to the throws clause.

Signature

public
void waitForData()

throws UnsupportedOperationException, InterruptedException

Throws

UnsupportedOperationException when this has not been constructed with notify set to true.

InterruptedException when the thread is interrupted by interrupt() or AsynchronouslyInterruptedException.fire()¹² during the time between calling this method and returning from it.

write(Object)

A synchronized and blocking write. This call blocks on queue full and will wait until there is space in the queue.

Available since RTSJ 1.0.1 The return type is changed to void since it *always* returned true, and InterruptedException was added to the throws clause.

 $^{^{12}}$ Section 8.4.2.1.2

```
Signature
```

```
public synchronized
void write(Object object)
throws MemoryScopeException, InterruptedException
```

Parameters 5 4 1

object The java.lang.Object that is placed in the queue.

Throws

InterruptedException when the thread is interrupted by interrupt() or AsynchronouslyInterruptedException.fire()¹³ during the time between calling this method and returning from it.

MemoryScopeException when a memory access error or illegal assignment error would occur while storing object in the queue.

7.4.1.6 WaitFreeWriteQueue

A queue that can be non-blocking for producers. The WaitFreeWriteQueue class is intended for single-writer multiple-reader communication, although it may also be used (with care) for multiple writers. A writer is generally an instance of NoHeap-RealtimeThread¹⁴, and the readers are generally regular Java threads or heap-using realtime threads or schedulables. Communication is through a bounded buffer of Objects that is managed first-in-first-out. The principal methods for this class are write and read.

- The write method appends a new element onto the queue. It is not synchronized, and does not block when the queue is full (it returns false instead). Multiple writer threads or schedulables are permitted, but when two or more threads intend to write to the same WaitFreeWriteQueue they will need to arrange explicit synchronization.
- The read method removes the oldest element from the queue. It is synchronized, and will block when the queue is empty. It may be called by more than one reader, in which case the different callers will read different elements from the queue.

WaitFreeWriteQueue is one of the classes allowing NoHeapRealtimeThreads and regular Java threads to synchronize on an object without the risk of a NoHeapRealtimeThread incurring Garbage Collector latency due to priority inversion avoidance management.

 $^{^{13}}$ Section 8.4.2.1.2

 $^{^{14}}$ Section 15.3.3.3

Incompatibility with V1.0: Three exceptions previously thrown by the constructor have been deleted from the throws clause. These are

- java.lang.IllegalAccessException,
- java.lang.ClassNotFoundException, and
- java.lang.InstantiationException.

Including these exceptions on the throws clause was an error. Their deletion may cause compile-time errors in code using the previous constructor. The repair is to remove the exceptions from the catch clause around the constructor invocation.

Inheritance

```
java.lang.Object
javax.realtime.WaitFreeWriteQueue
```

7.4.1.6.1 Constructors

WaitFreeWriteQueue(Runnable, Runnable, int, MemoryArea)

Constructs a queue in memory with an unsynchronized and nonblocking write() method and a synchronized and blocking read() method.

The writer and reader parameters, when non-null, are checked to insure that they are compatible with the MemoryArea specified by memory (when non-null.) When memory is null and both Runnables are non-null, the constructor will select the nearest common scoped parent memory area, or when there is no such scope it will use immortal memory. When all three parameters are null, the queue will be allocated in immortal memory.

reader and writer are not necessarily the only threads or schedulables that will access the queues; moreover, there is no check that they actually access the queue at all.

Note: that the wait free queue's internal queue is allocated in memory, but the memory area of the wait free queue instance itself is determined by the current allocation context.

Signature

public

WaitFreeWriteQueue(Runnable writer, Runnable reader, int maximum, MemoryArea memor

throws IllegalArgumentException, MemoryScopeException, InaccessibleAreaException

Parameters 1 4 1

 $writer \ {\rm An} \ {\rm instance} \ {\rm of} \ {\rm Thread}, \ {\rm a} \ {\rm schedulable} \ {\rm object}, \ {\rm or} \ {\tt null}.$

reader An instance of Thread, a schedulable object, or null.

maximum The maximum number of elements in the queue.

memory The MemoryArea¹⁵ in which this object and internal elements are allocated.

Throws

IllegalArgumentException when an argument holds an invalid value. The writer argument must be null, a reference to a Thread, or a reference to a schedulable (a RealtimeThread, or an AsyncEventHandler.) The reader argument must be null, a reference to a Thread, or a reference to a schedulable. The maximum argument must be greater than zero.

MemoryScopeException when either reader or writer is non-null and the memory argument is not compatible with reader and writer with respect to the assignment and access rules for memory areas.

InaccessibleAreaException when memory is a scoped memory that is not on the caller's scope stack.

WaitFreeWriteQueue(int, MemoryArea)

Constructs a queue containing up to maximum elements in memory. The queue has an unsynchronized and nonblocking write() method and a synchronized and blocking read() method.

Note: that the wait free queue's internal queue is allocated in memory, but the memory area of the wait free queue instance itself is determined by the current allocation context.

Available since RTSJ 1.0.1

```
public
WaitFreeWriteQueue(int maximum, MemoryArea memory)

throws IllegalArgumentException, InaccessibleAreaException

Parameters

15 Section 11.4.2.3
```

maximum The maximum number of elements in the queue.

memory The MemoryArea¹⁶ in which this object and internal elements are allocated.

Throws

IllegalArgumentException when the maximum argument is less than or equal to zero, or memory is null.

InaccessibleAreaException when memory is a scoped memory that is not on the caller's scope stack.

WaitFreeWriteQueue(int)

Constructs a queue containing up to maximum elements in immortal memory. The queue has an unsynchronized and nonblocking write() method and a synchronized and blocking read() method.

Available since RTSJ 1.0.1

Signature

public

WaitFreeWriteQueue(int maximum)

throws IllegalArgumentException

Parameters

maximum The maximum number of elements in the queue.

Throws

IllegalArgumentException when the maximum argument is less than or equal to zero.

7.4.1.6.2 Methods

clear

Sets this to empty.

 $^{^{16}}$ Section 11.4.2.3

```
Signature
public
void clear()
```

isEmpty

Queries the system to determine if this is empty.

Note: This method needs to be used with care since the state of the queue may change while the method is in progress or after it has returned.

```
Signature

public
boolean isEmpty()

Returns

True, when this is empty. False, when this is not empty.
```

isFull

Queries the system to determine if this is full.

Note: This method needs to be used with care since the state of the queue may change while the method is in progress or after it has returned.

```
Signature

public
boolean isFull()

Returns

True, when this is full. False, when this is not full.
```

read

A synchronized and possibly blocking operation on the queue. Available since RTSJ 1.0.1 Throws InterruptedException

Signature

```
public synchronized
java.lang.Object read()
throws InterruptedException
```

Throws

InterruptedException when the thread is interrupted by interrupt() or AsynchronouslyInterruptedException.fire()¹⁷ during the time between calling this method and returning from it.

Returns

The Object least recently written to the queue. When this is empty, the calling thread or schedulable objects blocks until an element is inserted; when it is resumed, read removes and returns the element.

size

Queries the queue to determine the number of elements in this.

Note: This method needs to be used with care since the state of the queue may change while the method is in progress or after it has returned.

```
Signature public int size()
```

Returns

The number of positions in this occupied by elements that have been written but not yet read.

force(Object)

Unconditionally insert object into this, either in a vacant position or else overwriting the most recently inserted element. The boolean result reflects whether, at the time that force() returns, the position at which object was inserted was vacant (false) or occupied (true).

```
Signature
```

```
public
boolean force(Object object)
throws MemoryScopeException, IllegalArgumentException
```

Parameters

¹⁷Section 8.4.2.1.2

7 Synchronization 213

object A non-null java.lang.Object to insert.

Throws

MemoryScopeException when a memory access error or illegal assignment error would occur while storing object in the queue.

IllegalArgumentException when object is null.

Returns

true when object has overwritten an element that was occupied when the function returns; false otherwise (it has been inserted into a position that was vacant when the function returns)

write(Object)

Inserts object into this when this is non-full and otherwise has no effect on this; the boolean result reflects whether object has been inserted. When the queue was empty and one or more threads or schedulables were waiting to read, then one will be awakened after the write. The choice of which to awaken depends on the involved scheduler(s).

Signature

public
boolean write(Object object)

throws MemoryScopeException, IllegalArgumentException

Parameters

object A non-null java.lang.Object to insert.

Throws

MemoryScopeException when a memory access error or illegal assignment error would occur while storing object in the queue.

IllegalArgumentException when object is null.

Returns

true when the queue was non-full; false otherwise.

7.5 Rationale

Java's rules for **synchronized** code provide a means for mutual exclusion but do not prevent unbounded priority inversions and thus are insufficient for realtime applications. This specification strengthens the semantics for **synchronized** code by mandating priority inversion control, in particular by furnishing classes for priority

7.5 Rationale

inheritance and priority ceiling emulation. Priority inheritance is more widely implemented in realtime operating systems and thus is the initial default mechanism in this specification.

Priority ceiling emulation is also a useful protocol. It is necessary for blocking out interrupts in interrupt service routines and simplifies scheduling analysis for single core systems. Since it can easily be implemented in user space, it is required as well.

Since the same object may be accessed from synchronized code by both a No-HeapRealtimeThread and an arbitrary thread or schedulable object, unwanted dependencies may result. To avoid this problem, this specification provides three wait-free queue classes as an alternative means for safe, concurrent data accesses without priority inversion.

Chapter 8

Asynchrony

8.1 Overview

One of the most important aspects of this specification is the support for asynchronous control flow. Mechanisms are provided for both starting a task asynchronously and interrupting the execution of a thread or other task. This specifications provides mechanisms that

- bind the execution of program logic to the occurrence of internal and external events;
- enable asynchronous transfer of control; and
- facilitate the asynchronous termination of realtime threads.

The RTSJ provides several facilities for arranging asynchronous control of execution. These facilities fall into two main categories: asynchronous event handling and asynchronous transfer of control, which includes realtime thread termination.

Asynchronous event handling is captured by the classes and subclasses of AbstractAsyncEvent(AE), AbstractAsyncEventHandler (AEH) and AbstractBound-AsyncEventHandler. An AE is an object used to direct event occurrences to asynchronous event handlers. An event occurrence may be initiated by application logic, by mechanisms internal to the RTSJ implementation (see the handlers in Periodic-Parameters), or by some external input such as a clock, a signal, or an interrupt.

An asynchronous event occurrence is initiated in program logic by the invocation of the fire method of an AE. The fire method dispatches all handlers associated with its event. This means that dispatching occurs in the execution context of the caller.

An asynchronous events that is initiated from an external source has additional requirements and hence additional API features. These features are captured by the ActiveEvent interface. Since external events do not have a full execution context of their own, this category of events must provide an alternate execution context.

216 8.2 Overview

In order to give the programmer control over this execution context, the specification defines abstract class ActiveEventDispatcher to provide execution context for dispatching. Subclasses provide a trigger method for initiating dispatching. Triggering simply informs this execution context to start dispatching. The trigger method is not defined in ActiveEventDispatcher, since some classes need a trigger methods with an argument and others do not. The types of ActiveEvent supported are described in subsequent chapters.

An AEH is a schedulable embodying code that is released for execution in response to the occurrence of an associated event. Each AEH behaves as if it is executed by a RealtimeThread except that it is not permitted to use the wait-ForNextRelease() or waitForNextReleaseInterruptible() methods, and it is treated as having a null thread group in all cases. There is not necessarily a separate realtime thread for each AEH, but the server realtime thread (returned by currentRealtimeThread()) remains constant during each execution of the run() method. The class AbstractBoundAsyncEventHandler extends AbstractAsync-EventHandler and ensures that a handler has a dedicated server realtime thread (a server thread is associated with one and only one bound AEH for the lifetime of that AEH). An event count (called fireCount) is maintained so that a handler can cope with event bursts—situations where an event occurs more frequently than its handler can respond.

The interrupt() method in java.lang.Thread provides rudimentary asynchronous communication by setting a pollable/resettable flag in the target thread, and by throwing a synchronous exception when the target thread is blocked at an invocation of wait(), sleep(), or join(). This specification extends the effect of Thread.interrupt() by adding an overridden version in RealtimeThread, offering a more comprehensive and non-polling asynchronous execution control facility. It is based on throwing and propagating exceptions that, though asynchronous, are deferred where necessary in order to avoid data structure corruption. The main elements of ATC are embodied in the class AsynchronouslyInterruptedException, its subclass Timed, the interface Interruptible, and in the semantics of the interrupt method in RealtimeThread.

A method indicates its eligibility to be asynchronously interrupted by including the checked exception AsynchronouslyInterruptedException in its throws clause. If a schedulable is asynchronously interrupted while executing such a method, then an AIE will be delivered as soon as the schedulable is outside of a section in which ATC is deferred. Several idioms are available for handling an AIE, giving the programmer the choice of using catch clauses and a low-level mechanism with specific control over propagation, or a higher-level facility that allows specifying the interruptible code, the handler, and the result retrieval as separate methods.

8 Asynchrony 217

8.2 Definitions

The following terms and abbreviations will be used.

AE—Asynchronous Event. An instance of one of the subclasses of the javax.realtime.Abstract class.

AEH—Asynchronous Event Handler. An instance of one of the subclasses of the AbstractAsyncEventHandler class.

Bound AEH — Bound Asynchronous Event Handler. An instance of one of the subclasses of the AbstractBoundAsyncEventHandler class.

ATC — Asynchronous Transfer of Control.

AIE — Asynchronously Interrupted Exception. An instance of the javax.realtime.Asynchronouclass (a subclass of java.lang.InterruptedException).

AI-method - Asynchronously Interruptible method. A method or constructor that includes AsynchronouslyInterruptedException explicitly (that is not a subclass of AsynchronouslyInterruptedException) in its throws clause.

Lexical Scope [of a method, constructor, or statement]. The textual region within the constructor, method, or statement, excluding the code within any class declarations, and the code within any class instance creation expressions for anonymous classes, contained therein. The lexical scope of a construct does not include the bodies of any methods or constructors that this code invokes.

ATC-deferred section. A synchronized statement, a static initializer or any method or constructor without AsynchronouslyInterruptedException in its throws clause. As specified in the introduction to Chapter 8 in Java Language Specification, a synchronized method is equivalent to a non-synchronized method with the body of the method contained in a synchronized statement. Thus, a synchronized AI method behaves like an AI method containing only an ATC-deferred statement.

Interruptible blocking methods. The RTSJ and standard Java methods that are explicitly interruptible by an AIE. The interruptible blocking methods comprise

- HighResolutionTime.waitForObject(),
- Object.wait(),
- Thread.sleep(),
- RealtimeThread.sleep(),
- Thread.join(),
- ScopedMemory.join(),
- ScopedMemory.joinAndEnter(),
- RealtimeThread.waitForNextReleaseInterruptible(),
- WaitFreeWriteQueue.read(),
- WaitFreeReadQueue.waitForData(),
- WaitFreeReadQueue.write(),
- WaitFreeDequeue.blockingRead(),
- WaitFreeDequeue.blockingWrite()

218 8.3 Semantics

and their overloaded forms.

8.3 Semantics

Asynchronous events and event handlers are required in the base module, whereas asynchronous transfere of control is optional. Basic event types are passive: they are not directly associated with a thread of control. They are intended to be fired programmatically. Handelling external events, such as clocks (see Chapter 10) and happening (see Chapter 12), requires execution support. The ActiveEvent interface is provided to mark these and provide additional execution semantics. Figure 8.1 illustrates the event hierarchy.




Figure 8.1: The Event Class Hierarchy

8.3.1 Asynchronous Events and their Handlers

This following list establishes the semantics that are applicable to asynchronous events and their handlers. Semantics that apply to particular classes, constructors, methods, and fields will be found in the class description and the constructor, method, and field detail sections.

1. When an asynchronous event occurs (by either program logic or by the triggering of a happening), its attached handlers (that is, AEHs that have been

8 Asynchrony 219

added to the AE by the execution of addHandler()) are released for execution. Every occurrence of an event increments the fireCount in each attached handler. Handlers may elect to execute logic for each occurrence of the event or not

- 2. The release of attached handlers occurs in execution eligibility order (priority order, from highest to lowest, with the default PriorityScheduler) and at the active priority of the schedulable that invoked the fire method. The release of handlers resulting from a happening or a timer must begin within a bounded time (ignoring time consumed by unrelated activities in the system). This worst-case response interval must be documented for some reference architecture.
- 3. The release of attached handlers is an atomic operation with respect to adding and removing handlers.
- 4. The logical release of an attached handler may occur before the previous release has completed.
- 5. A deadline may be associated with each logical release of an attached handler. The deadline is relative to the occurrence of the associated event.
- 6. AEs and AEHs may be created and used by any program logic within the constraints of the memory assignment rules.
- 7. More than one AEH may be added to an AE. However, adding an AEH to an AE has no effect if the AEH is already attached to the AE.
- 8. The same AEH may be added to more than one AE.
- 9. By default all AEHs are considered to be daemons (the daemon status being set by their constructors). An AEH can be set to have a non daemon status after it has been created and before it has been attached to an AE.
- 10. The object returned by currentRealtimeThread() while an AEH is running shall behave with respect to memory access and assignment rules as if it were allocated in the same memory area as the AEH.
- 11. System-related termination activity (such as execution of finalizers for scoped objects in scopes that become unreferenced) triggered when an AEH becomes unfireable is not subject to cost enforcement or deadline miss detection.
- 12. AEs and AEHs behave effectively as if changes to an AEH's fireability are contained in synchronized blocks, and the AEH holds that lock while it is in the process of becoming non-fireable.

An RTSJ program terminates when and only when

- all non-daemon threads (either regular Java threads or realtime threads) are terminated,
- the fireCounts of all nondaemon bound AEHs or nondaemon AEHs are zero and all releases are completed, and
- there are no nondaemon Bound AEHs or AEHs attached to timers or async


220 8.3 Semantics

events associated with happenings.

Though dispatchers have a thread, this thread is a daemon thread and does itself not hinder termination.

AbstractAsyncEvent provides two basic states: enabled and disabled. In the enabled state, fire causes all associated handlers to be dispatched, whereas fire does nothing when the event is disabled. Figure 8.2 illustrates this state space.

Figure 8.2: States of a Simple AbstractAsyncEvent



8.3.2 Active Events and Dispatching

Active events refine the semantics of AbstractAsyncEventHandler with the addition of execution semantics to support second level interrupt handling. The fire method of an event runs in the Java execution context of the caller. For events that represent external signals, whether a certain time is reached or something has occurred, there may not be a Java execution context, or at least that context is of necessity limited and often of needs to have a very short duration; dispatching an unlimited number of handlers is not acceptable. They require an additional execution context for releasing handlers.

In order to be able to distinguish between events that are caused to be fired by an outside mechanism from those that are fired from another thread, the former extend the ActiveEvent interface. Since the trigger methods may vary in the number of their arguments depending on the type of event, each class implementing ActiveEvent must provide its own trigger method for initiating the handler release by releasing another execution context. Each method must act as if it calls the fire

8 Asynchrony 221

method on its event and then terminates. Hence trigger has the same functional behavior as fire but runs in this other execution context.

This extra execution context is exposed to the user as an ActiveEventDispatcher. There is a active event dispatcher for each kind of active event. The programmer does not need to write a dispatcher, but just creates the one of the corresponding type. The programmer does determine the priority and the affinity of a dispatcher, as well as determine the mapping between dispatchers and events.

Each event has a single dispatcher, but a dispatcher may serve many events. As with fire, the dispatcher releases handlers in reverse priority order, i.e., from highest to lowest. This enables the programmer to control the number of these execution contexts and still optimize how handlers are released.

The state space of an ActiveEvent is an extention of the state space for an AbstractAsyncEvent depicted in Figure 8.2. ActiveEvent adds the notion of active and inactive on top of enabled and disabled, as depicted in Figure 8.3. Note the enabled-disabled distinction is only splits the active state. The inactive state is by definition disabled.

stop -> false

startDisabled

stop
-> true

disable

Active
Enabled
Active
Disabled

Active
Disabled

Active
Disabled

Active
Disabled

start

-> IllegalStateException startDisabled-> IllegalStateException

start

stop

-> false

Figure 8.3: States of an ActiveEvent

222 8.3 Semantics

8.3.3 Asynchronous Transfer of Control

Asynchronously interrupting a schedulable consists of the following activities.

- Generation of an asynchronous interrupt exception this is the event in the underlying system that makes the AIE available to the program.
- **Delivery** of the asynchronous interrupt exception to the target schedulable—this is the action that invokes the search for and execution of an appropriate handler.

Between the generation and delivery, the asynchronous interrupt exception is held *pending*. After delivery, the AIE remains pending until it is **cleared** by the program logic using clear() or doInterruptible().

This following list establishes the semantics that are applicable to ATC. Semantics that apply to particular classes, constructors, methods, and fields will be found in the class description and the constructor, method, and field detail sections.

- 1. An AIE is generated for a given schedulable, when the fire() method is called on an AIE for which the schedulable object is executing within the doInterruptible() method, or the RealtimeThread.interrupt() method is called; the latter is effectively called when an AIE is generated by internal virtual machine mechanisms (such as an interrupt I/O protocol) that are asynchronous to the execution of program logic which is the target of the AIE. A generated AIE becomes pending upon generation and remains pending until explicitly cleared or replaced by another AIE.
- 2. The RealtimeThread.interrupt() method throws the generic AIE at the target realtime thread and has the behaviors defined for Thread.interrupt(). This is the only interaction between the ATC mechanism and the conventional interrupt() mechanism.
- 3. An AIE is delivered to a schedulable when it is executing in an AI-method except as indicated below.
- 4. The generation of an AIE through the fire() mechanism behaves as if it set an asynchronously-interrupted status in the schedulable. If the schedulable is blocked within an interruptible blocking method, or invokes an interruptible blocking method, when this asynchronously-interrupted status is set, then the invocation immediately completes by throwing the pending AIE and clearing the asynchronously-interrupted status. When a pending AIE is explicitly cleared then the asynchronously-interrupted status is also cleared.
- 5. Methods which block through mechanisms other than the interruptible blocking methods, (for example, blocking methods in java.io.*) must be prevented from blocking indefinitely when invoked from a method with Asynchronously-InterruptedException in its throws clause. When an AIE is generated and the target schedulable's control is blocked inside one of these methods invoked from an AI-method, the implementation may either unblock the blocked call,

8 Asynchrony 223

raise an InterruptedIOException on behalf of the call, or allow the call to complete normally if the implementation determines that the call would eventually unblock.

- 6. If an AI-method is attempting to acquire an object lock when an associated AIE is generated, the attempt to acquire the lock is abandoned.
- 7. If control is in the lexical scope of an ATC-deferred section when an AIE (targeted at the executing schedulable) is generated, the AIE is not delivered until the first subsequent attempt to transfer control to code that is not ATC deferred. At that point, control is transferred to the catch or finally clause of the nearest dynamically-enclosing a try statement that has a handler for the generated AIE's (that is a handler naming the AIE's class or any of its superclasses, or a finally clause) and which is in an ATC-deferred section. Intervening handlers and finally clauses that are not in ATC-deferred sections are not executed, but object locks are released.
 - See section 11.3 of *The Java Language Specification* second edition for an explanation of the terms, *dynamically enclosing* and *handler*. The RTSJ uses those JLS definitions unaltered. Note, if synchronized code is abandoned as a result of this control transfer, the associated locks are released.
- 8. Constructors are allowed to include AsynchronouslyInterruptedException in their throws clause and if they do will be asynchronously interruptible under the same conditions as AI methods.
- 9. Native methods that include AsynchronouslyInterruptedException in their throws clause have implementation-specific behavior.
- 10. An implementation must deliver the transfer of control in a schedulable that is subject to asynchronous interruption (in an AI-method but not in a synchronized block) within a bounded execution time of that schedulable. This worst-case response interval must be documented for some reference architecture.
- 11. Instances of the Timed class logically have an associated timer. When the timer fires, the schedulable executing the instance's doInterruptible method must have the AIE generated within a bounded execution time of the schedulable. This worst-case response interval must be documented for some reference architecture.
- 12. An AIE only has the semantics defined here if it originates with the AsynchronouslyInterruptedException.fire() method, the RealtimeThread.interrupt() method or from within the realtime VM. If an AIE is thrown from program logic using the Java throw statement, it acts the same as throwing any other instance of a subclass of Exception, it is processed as a normal exception, and has no affect on the pending state of any AIE, and no affect on the firing of the AIE concerned.

224 8.3 Semantics

8.3.3.1 Summary of ATC Operation

The RTSJ's approach to ATC is designed to follow the above principles. It is based on exceptions and is an extension of the current Java language rules for java.lang.Thread.interrupt(). In summary, ATC works as follows:

If so is an instance of a schedulable and the interrupt() method is called on the realtime thread associated with that object (in this context, the associated realtime thread of an AEH is the realtime thread returned by a call of the RealtimeThread.currentRealtimeThread() method by that AEH) then:

- If control is in an ATC-deferred section, then the AIE remains in a pending state.
- If control is not in an ATC-deferred section, then control is transferred to the catch or finally clause of the nearest dynamically-enclosing a try statement that has a handler for the generated AIE's (that is a handler naming the AIE's class or any of its superclasses, or a finally clause) and which is in an ATC-deferred section. Intervening handlers and finally clauses that are not in ATC-deferred sections are not executed, but objects locks are released. See section 11.3 of The Java Language Specification second edition for an explanation of the terms, dynamically enclosing and handles. The RTSJ uses those definitions unaltered.
- If control is in an interruptible blocking method the schedulable object is awakened and the generated AIE (which is a subclass of InterruptedException) is thrown with regular Java semantics (the AIE is still marked as pending). Then ATC follows option 1, or 2 as appropriate.
- If control is in an ATC-deferred section, control continues normally until the first attempt to return to an AI method or invoke an AI method or exit a synchronized block within an AI method. Then ATC follows option 1, or 2 as appropriate.
- If control is transferred from an ATC-deferred section to an AI method through the action of propagating an exception and if an AIE is pending then when the transition to the AI-method occurs, the thrown exception is discarded and replaced by the AIE.

An AIE may be generated while another AIE is pending. Because AI code blocks are nested by method invocation (a stack-based nesting) there is a natural precedence among active instances of AIE. Let AIE_0 be the AIE raised when the RealtimeThread.interrupt() method is invoked and AIE_i (i=1,...,n, for n unique instances of AIE) be the AIE generated when AIE. fire() is invoked. In the following, the phrase "a frame deeper on the stack than this frame" refers to a method nearer to the current stack frame. The phrase "a frame shallower on the stack than this frame" refers to a method further from the current stack frame.

• If the current AIE is an AIE_0 and the new AIE is an AIE_x associated with

8 Asynchrony 225

any frame on the stack then the new AIE (AIE_x) is discarded.

• If the current AIE is an AIE_x and the new AIE is an AIE_0 , then the current AIE (AIE_x) is replaced by the new AIE (AIE_0) .

- If the current AIE is an AIE_x and the new AIE is an AIE_y from a frame deeper on the stack, then the new AIE (AIE_y) discarded.
- If the current AIE is an AIE_x and the new AIE is an AIE_y from a frame shallower on the stack, the current AIE (AIE_x) is replaced by the new AIE (AIE_y) .
- If the current AIE is an AIE_0 and the new AIE is an AIE_0 , or if the current AIE is an AIE_x and the new AIE is an AIE_x , the new AIE is discarded.

When clear() or happened() is called on a pending AIE or that AIE is superseded by another, the first AIE's pending state is cleared. If the happened() method is called on a non-pending AIE the result depends on the value of the propagate parameter, as indicated in the "No Match" column of the table below. Clearing a non-pending AIE (with the clear() method) has no effect.

propagate	Match	No Match
true	clear the pending AIE,	the AIE remains pending,
	return true	propagate
false	clear the pending AIE,	the AIE remains pending,
	return true	return false

8.4 Package javax.realtime

8.4.1 Interfaces

8.4.1.1 ActiveEvent

This is the interface for defining the active event system. Classes implementing ActiveEvent are used to connect events that take place outside the Java virtual machine to RTSJ activities.

When an event takes place outside the Java virtual machine, some event-specific code within the Java virtual machine executes. That code notifies the ActiveEvent infrastructure of this event by calling a trigger method in the event.

Interfaces

Releasable

8.4.1.1.1 Methods

isActive

Determine the activation state of this event, i.e., it has been started but not yet stopped again.

```
Signature

public
boolean isActive()

Returns

true when active, false otherwise.
```

isRunning

Determine the running state of this event, i.e., it is both active and enabled.

```
\begin{array}{c} Signature \\ \text{public} \end{array}
```

```
boolean isRunning()
Returns
     true when active and enabled, false otherwise.
start
   Start this active event.
Signature
     public
     void start()
     throws IllegalStateException
Throws
     IllegalStateException when this event has already been started.
start(boolean)
   Start this active event.
Signature
     public
     void start(boolean disabled)
     throws IllegalStateException
Parameters
     disabled true for starting in a disabled state.
Throws
     IllegalStateException when this event has already been started.
stop
   Stop this active event.
Signature
```

public

Throws

boolean stop()

throws IllegalStateException

IllegalStateException when this event is not running.

Returns

the previous enabled state.

enable

Change the state of the event so that associated handlers are release on fire. Each subclass provides a means of dispatching its handlers when requested. This method enables that request mechanism.

```
Signature

public

void enable()
```

disable

Change the state of the event so that associated handlers are skipped on fire. Each subclass provides a fire method as means of dispatching its handlers when requested. This method disables that request mechanism.

```
Signature
public
void disable()
```

8.4.1.2 AsyncTimable

A common type for Timer¹ and RealtimeThread² to indicate that they can be associated with a Clock³ and be suspended waiting for time events based on that clock.

Available since RTSJ 2.0

```
Interfaces
Timable

Section 10.4.2.5

Section 5.3.2.2

Section 10.4.2.1
```

8.4.1.2.1 Methods

fire

Inform the dispatcher associated with this Timable that a time event has occurred.

Available since RTSJ 2.0

```
Signature

public

void fire()
```

8.4.1.3 BoundAbstractAsyncEventHandler

An marker interface for all schedulables that are bound to a single thread of control. It is required to enable references to all bound handlers.

Interfaces

BoundSchedulable

8.4.1.4 Interruptible

Interruptible is an interface implemented by classes that will be used as arguments on the method doInterruptible() of AsynchronouslyInterruptedException⁴ and its subclasses. doInterruptible() invokes the implementation of the method in this interface.

8.4.1.4.1 Methods

⁴Section 8.4.2.1

run(AsynchronouslyInterruptedException)

The main piece of code that is executed when an implementation is given to doInterruptible(). When a class is created that implements this interface (for example through an anonymous inner class) it must include the throws clause to make the method interruptible. When the throws clause is omitted the run() method will not be interruptible.

```
Signature

public

void run(AsynchronouslyInterruptedException exception)

throws AsynchronouslyInterruptedException
```

Parameters

exception The AIE object whose doInterruptible method is calling the run method. Used to invoke methods on AsynchronouslyInterruptedException⁵ from within the run() method.

interruptAction(AsynchronouslyInterruptedException)

This method is called by the system when the run() method is interrupted. Using this, the program logic can determine when the run() method completed normally or had its control asynchronously transferred to its caller.

```
Signature
    public
    void interruptAction(AsynchronouslyInterruptedException
        exception)
```

Parameters 1

exception The currently pending AIE. Used to invoke methods on AsynchronouslyInterruptedException⁶ from within the interruptAction() method.

8.4.1.5 Releasable

⁵Section 8.4.2.1 ⁶Section 8.4.2.1

8.4.1.5.1 Methods

getDispatcher

```
Signature
    public
    D extends javax.realtime.ActiveEventDispatcher<D, T>
    getDispatcher()
```

8.4.2 Exceptions

8.4.2.1 AsynchronouslyInterruptedException

A special exception that is thrown in response to an attempt to asynchronously transfer the locus of control of a schedulable.

A schedulable that is executing a method or constructor, which is declared with an AsynchronouslyInterruptedException⁷ in its throws clause, can be asynchronously interrupted except when it is executing in the lexical scope of a synchronized statement within that method/constructor. As soon as the schedulable object leaves the lexical scope of the method by calling another method/constructor it may be asynchronously interrupted when the called method/constructor is asynchronously interruptible. (See this chapter's introduction section for the detailed semantics).

The asynchronous interrupt is generated for a realtime thread, t, when the t.interrupt() method is called or the fire⁸ method is called of an AIE for which t has a doInterruptible method call in progress.

The interrupt is generated for an AEH (or BAEH), h, when the fire method is called of an AIE for which h has a doInterruptible method call in progress.

When an asynchronous interrupt is generated when the target realtime thread/schedulable is executing within an ATC-deferred section, the asynchronous interrupt becomes pending. A pending asynchronous interrupt is delivered when the target realtime thread/schedulable next attempts to enter asynchronously interruptible code.

⁷Section 8.4.2.1

⁸Section 8.4.2.1.2

⁹Section 8.4.2.1.2

Asynchronous transfers of control (ATCs) are intended to allow long-running computations to be terminated without the overhead or latency of polling with name.

When RealtimeThread.interrupt¹⁰, or AsynchronouslyInterruptedException is compared against any currently pending AsynchronouslyInterruptedException on the schedulable. When there is none, or when the depth of the AsynchronouslyInterruptedException is less than the currently pending AsynchronouslyInterruptedException; (i.e., it is targeted at a less deeply nested method call), the new AsynchronouslyInterruptedException is less than the previously pending AsynchronouslyInterruptedException and the previously pending AsynchronouslyInterruptedException is discarded. Otherwise, the new AsynchronouslyInterruptedException is discarded.

When an AsynchronouslyInterruptedException is caught, the catch clause may invoke the clear() method on the AsynchronouslyInterruptedException in which it is interested to see if the exception matches the pending Asynchronously-InterruptedException. When so, the pending AsynchronouslyInterruptedException is cleared for the schedulable and clear returns true. Otherwise, the current AIE remains pending and clear returns false.

RealtimeThread.interrupt() generates a system-wide generic Asynchronously-InterruptedException which will always propagate outward through interruptible methods until the generic AsynchronouslyInterruptedException is identified and handled. The pending state of the generic AIE is per-schedulable object.

Other sources (e.g., AsynchronouslyInterruptedException.fire() and Timed¹¹) will generate specific instances of AsynchronouslyInterruptedException which applications can identify and thus limit propagation.

AsyncEventHandler¹² objects should interact with the ATC mechanisms via the Interruptible¹³ interface.

Inheritance

```
java.lang.Object
    java.lang.Throwable
    java.lang.Exception
    java.lang.InterruptedException
    javax.realtime.AsynchronouslyInterruptedException
```

8.4.2.1.1 Constructors

 $^{^{10}}$ Section 5.3.2.2.2

¹¹Section 8.4.2.2

 $^{^{12}}$ Section 8.4.3.5

 $^{^{13}}$ Section 8.4.1.4

AsynchronouslyInterruptedException

Create an instance of AsynchronouslyInterruptedException.

Signature

public

AsynchronouslyInterruptedException()

8.4.2.1.2 Methods

getGeneric

Gets the singleton system generic AsynchronouslyInterruptedException that is generated when RealtimeThread.interrupt()¹⁴is invoked.

Signature

```
public static
javax.realtime.AsynchronouslyInterruptedException getGeneric()
```

 ${\it IllegalThreadStateException} \ \ {\it when the current thread is a Java thread}.$ ${\it Returns}$

The generic AsynchronouslyInterruptedException.

enable

Enable the throwing of this exception. This method is valid only when the caller has a call to doInterruptible() in progress. When invoked when no call to doInterruptible() is in progress, enable returns false and does nothing.

Signature

¹⁴Section 5.3.2.2.2

```
public
boolean enable()
```

Returns

True when this was disabled before the method was called and the call was invoked whilst the associated doInterruptible() is in progress. False: otherwise.

disable

Disable the throwing of this exception. When the fire¹⁵ method is called on this AIE whilst it is disabled, the fire is held pending and delivered as soon as the AIE is enabled and the interruptible code is within an AI-method. When an AIE is pending when the associated disable method is called, the AIE remains pending, and is delivered as soon as the AIE is enabled and the interruptible code is within an AI-method.

This method is valid only when the caller has a call to doInterruptible() in progress. If invoked when no call to doInterruptible() is in progress, disable returns false and does nothing.

Note: disabling the genericAIE associated with a realtime thread only affects the firing of that AIE. When the genericAIE is generated by the RealtimeThread.interrupt()¹⁶ mechanism, the AIE is delivered (unless the Interruptible code is in an AI-deferred region, in which case it is marked as pending and handled in the usual way).

Signature

public synchronized
boolean disable()

Returns

True when this was enabled before the method was called and the call was invoked with the associated doInterruptible() in progress. False: otherwise.

isEnabled

Query the enabled status of this exception.

This method is valid only when the caller has a call to doInterruptible() in progress. If invoked when no call to doInterruptible() is in progress, enable returns false and does nothing.

 $^{^{15}}$ Section 8.4.2.1.2

 $^{^{16}}$ Section 5.3.2.2.2

```
Signature
public
boolean isEnabled()
```

Returns

True when this is enabled and the method call was invoked in the context of the associated doInterruptible(). False otherwise.

fire

Generate this exception when its doInterruptible() has been invoked and not completed. When this is the only outstanding AIE on the schedulable object that invoked this AIE's doInterruptible(Interruptible)¹⁷ method, this AIE becomes that schedulable's current AIE. Otherwise, it only becomes the current AIE when it is at a less deep level of nesting compared with the current outstanding AIE.

```
Signature
public
boolean fire()
Returns
```

True when this is not disabled and it has an invocation of a doInterrupt-ible() in progress and there is no outstanding fire request. False otherwise.

doInterruptible(Interruptible)

Executes the run() method of the given Interruptible¹⁸. This method may be on the stack in exactly one Schedulable¹⁹ object. An attempt to invoke this method in a schedulable while it is on the stack of another or the same schedulable will cause an immediate return with a value of false.

The run method of given Interruptible is always entered with the exception in the enabled state, but that state can be modified with enable()²⁰ and disable()²¹ and the state can be observed with isEnabled()²².

This AIE is cleared on return from doInterruptible().

```
<sup>17</sup>Section 8.4.2.1.2

<sup>18</sup>Section 8.4.1.4

<sup>19</sup>Section 6.4.1.2

<sup>20</sup>Section 8.4.2.1.2

<sup>21</sup>Section 8.4.2.1.2

<sup>22</sup>Section 8.4.2.1.2
```

```
Signature
```

public

boolean doInterruptible(Interruptible logic)

Parameters 5 4 1

logic An instance of an Interruptible²³ whose run() method will be called. Throws

IllegalThreadStateException when called from a Java thread.

IllegalArgumentException when logic is null.

Returns

True when the method call completed normally. False when another call to doInterruptible has not completed.

clear

Atomically see if this is pending on the currently executing schedulable, and when so, make it non-pending.

Available since RTSJ 1.0.1

Signature

public

boolean clear()

Throws

IllegalThreadStateException when called from a Java thread.

Returns

True when this was pending. False when this was not pending.

8.4.2.2 Timed

Open issue: The fact that Timed extends AIE confuses the javadoc. It prints an Exceptions heading

Create a scope in a Schedulable²⁴ object which will be asynchronously interrupted at the expiration of a timer. This timer will begin measuring time at some

²³Section 8.4.1.4

 $^{^{24}}$ Section 6.4.1.2

point between the time doInterruptible() is invoked and the time the run() method of the Interruptible object is invoked. Each call of doInterruptible() on an instance of Timed will restart the timer for the amount of time given in the constructor or the most recent invocation of resetTime(). The timer is cancelled when it has not expired before the doInterruptible() method has finished.

All memory use of an instance of Timed occurs during construction or the first invocation of doInterruptible(). Subsequent invocations of doInterruptible() do not allocate memory.

When the timer fires, the resulting AIE will be generated for the schedulable within a bounded execution time of the targeted schedulable.

Typical usage: new Timed(T).doInterruptible(interruptible); End of open issue

Inheritance

```
java.lang.Object
    java.lang.Throwable
    java.lang.Exception
    java.lang.InterruptedException
    javax.realtime.AsynchronouslyInterruptedException
    javax.realtime.Timed
```

8.4.2.2.1 Constructors

Timed(javax.realtime.HighResolutionTime<?>)

Create an instance of Timed with a timer set to time. When the time is in the past the AsynchronouslyInterruptedException²⁵ mechanism is activated immediately after or when the doInterruptible() method is called.

```
Signature
```

```
public
   Timed(javax.realtime.HighResolutionTime<?> time)
```

throws Illegal ArgumentException, UnsupportedOperationException Parameters

²⁵Section 8.4.2.1

time When time is a RelativeTime²⁶ value, it is the interval of time between the invocation of doInterruptible() and when the schedulable is asynchronously interrupted. When time is an AbsoluteTime²⁷ value, the timer asynchronously interrupts at this time (assuming the timer has not been cancelled).

Throws

IllegalArgumentException when time is null. UnsupportedOperationException when time is not based on a $Clock^{28}$.

8.4.2.2.2 Methods

doInterruptible(Interruptible)

Execute a time-out method. Starts the timer and executes the run() method of the given Interruptible²⁹ object.

```
Signature

public
boolean doInterruptible(Interruptible logic)

Parameters
logic @inheritDoc

Throws
IllegalArgumentException @inheritDoc
IllegalThreadStateException @inheritDoc

Returns
@inheritDoc
```

resetTime(javax.realtime.HighResolutionTime<?>)

To set the time-out for the next invocation of doInterruptible().

Signature

²⁶Section 9.4.1.3 ²⁷Section 9.4.1.1 ²⁸Section 10.4.2.1 ²⁹Section 8.4.1.4

```
public
  void resetTime(javax.realtime.HighResolutionTime<?> time)
Parameters
```

time This can be an absolute time or a relative time. When null or not based on a $Clock^{30}$, the time-out is not changed.

restart(javax.realtime.HighResolutionTime<?>)

Reset the timeout. When this Timed³¹ instance is executing, adjust the timeout to time and restart the timer. When the instance is not executing, adjust the timeout for the next invocation.

Available since RTSJ 2.0

```
Signature

public
void restart(javax.realtime.HighResolutionTime<?> time)

Parameters
time The new timeout.

Throws

IllegalArgumentException when time is null or a relative time less than zero.
```

Illegal Argument Exception when time is null or a relative time less than zero. Unsupported Operation Exception when time is not based on a $Clock^{32}$

8.4.3 Classes

8.4.3.1 AbstractAsyncEvent

This is the base class for all asynchronous events, where asynchronous is in regards to running code, not external time. This class unifies the original AsyncEvent³³ with AsyncLongEvent³⁴ and AsyncObjectEvent³⁵.

Available since RTSJ 2.0

```
<sup>30</sup>Section 10.4.2.1

<sup>31</sup>Section 8.4.2.2

<sup>32</sup>Section 10.4.2.1

<sup>33</sup>Section 8.4.3.4

<sup>34</sup>Section 8.4.3.6

<sup>35</sup>Section 8.4.3.8
```

Inheritance

```
java.lang.Object
javax.realtime.AbstractAsyncEvent
```

8.4.3.1.1 Methods

isRunning

Determine the firing state (releasing or skipping) of this event, i.e., whether it is enabled or disabled.

```
Signature

public
boolean isRunning()

Returns

true when releasing, false when skipping.
```

handledBy(AbstractAsyncEventHandler)

Test to see if the handler given as the parameter is associated with this.

```
Signature
```

```
public
boolean handledBy(AbstractAsyncEventHandler handler)
```

Parameters

handler The handler to be tested to determine if it is associated with this.

Returns

True when the parameter is associated with this. False when handler is null or the parameters is not associated with this.

enable

Change the state of the event so that associated handlers are release on fire. Each subclass provides a means of dispatching its handlers when requested. This method enables that request mechanism.

```
Signature
public
void enable()
```

disable

Change the state of the event so that associated handlers are skipped on fire. Each subclass provides a fire method as means of dispatching its handlers when requested. This method disables that request mechanism.

```
Signature
public
void disable()
```

addHandler(AbstractAsyncEventHandler)

Add a handler to the set of handlers associated with this event. An instance of AsyncEvent may have more than one associated handler. However, adding a handler to an event has no effect when the handler is already attached to the event.

The execution of this method is atomic with respect to the execution of the fire() method.

Since this affects the constraints expressed in the release parameters of an existing schedulable, this may change the feasibility of the current system. This method does not change feasibility set of any scheduler, and no feasibility test is performed.

Note, there is an implicit reference to the handler stored in this. The assignment must be valid under any applicable memory assignment rules.

```
Signature

public

void addHandler(AbstractAsyncEventHandler handler)

Parameters
```

handler The new handler to add to the list of handlers already associated with this. When handler is already associated with the event, the call has no effect. Throws

IllegalArgumentException when handler is null or the handler has Periodic-Parameters³⁶. Only the subclass PeriodicTimer³⁷ is allowed to have handlers with PeriodicParameters³⁸.

IllegalAssignmentError when this AsyncEvent cannot hold a reference to handler.

setHandler(AbstractAsyncEventHandler)

Associate a new handler with this event and remove all existing handlers. The execution of this method is atomic with respect to the execution of the fire() method.

Since this affects the constraints expressed in the release parameters of the existing schedulables, this may change the feasibility of the current system. This method does not change the feasibility set of any scheduler, and no feasibility test is performed.

```
Signature
```

public

void setHandler(AbstractAsyncEventHandler handler)

Parameters 1

handler The instance of AbstractAsyncEventHandler³⁹ to be associated with this. When handler is null then no handler will be associated with this, i.e., behave effectively as if setHandler(null) invokes removeHandler(AbstractAsyncEventHandler)⁴⁰ for each associated handler.

Throws

IllegalArgumentException when handler has PeriodicParameters⁴¹. Only the subclass PeriodicTimer⁴² is allowed to have handlers with PeriodicParameters⁴³.

IllegalAssignmentError when this AsyncEvent cannot hold a reference to handler.

removeHandler(AbstractAsyncEventHandler)

```
<sup>36</sup>Section 6.4.2.5

<sup>37</sup>Section 10.4.2.3

<sup>38</sup>Section 6.4.2.5

<sup>39</sup>Section 8.4.3.2

<sup>40</sup>Section 8.4.3.1.1

<sup>41</sup>Section 6.4.2.5

<sup>42</sup>Section 10.4.2.3

<sup>43</sup>Section 6.4.2.5
```

Remove a handler from the set associated with this event. The execution of this method is atomic with respect to the execution of the fire() method.

A removed handler continues to execute until its fireCount becomes zero and it completes.

When handler has a scoped non-default initial memory area and execution of this method causes handler to become non-fireable, this method shall not return until all related finalization has completed.

```
Signature \ public \ void remove Handler (Abstract Async Event Handler handler)
```

Parameters

handler The handler to be disassociated from this. When null nothing happens. When the handler is not already associated with this then nothing happens.

hasHandlers

Determine whether or not this event has any handlers

Available since RTSJ 2.0

```
Signature

public
boolean hasHandlers()

Returns
```

true when and only when at least one handler is associated with this event.

createReleaseParameters

Create a ReleaseParameters⁴⁴ object appropriate to the release characteristics of this event. The default is the most pessimistic: AperiodicParameters⁴⁵. This is typically called by code that is setting up a handler for this event that will fill in the parts of the release parameters for which it has values, e.g., cost. The returned

⁴⁴Section 6.4.2.9

 $^{^{45}}$ Section 6.4.2.2

ReleaseParameters⁴⁶ object is not bound to the event. Any changes in the event's release parameters are not reflected in previously returned objects.

When an event returns PeriodicParameters⁴⁷, there is no requirement for an implementation to check that the handler is released periodically.

```
Signature

public
 javax.realtime.ReleaseParameters createReleaseParameters()

Returns

A new ReleaseParameters<sup>48</sup> object.
```

8.4.3.2 AbstractAsyncEventHandler

This is the base class for all asynchronous event handlers, where asynchronous is in regards to running code, not external time. This class unifies the original Async-EventHandler⁴⁹ with AsyncLongEventHandler⁵⁰ and AsyncObjectEventHandler⁵¹.

Available since RTSJ 2.0

Inheritance

```
java.lang.Object
javax.realtime.AbstractAsyncEventHandler
Interfaces
Schedulable
```

8.4.3.2.1 Methods

getCurrentConsumption(RelativeTime)

Available since RTSJ 2.0

```
<sup>46</sup>Section 6.4.2.9

<sup>47</sup>Section 6.4.2.5

<sup>48</sup>Section 6.4.2.9

<sup>49</sup>Section 8.4.3.5

<sup>50</sup>Section 8.4.3.7

<sup>51</sup>Section 8.4.3.9
```

```
Signature
    public static
    javax.realtime.RelativeTime getCurrentConsumption(RelativeTime
    throws IllegalStateException
```

Throws

IllegalStateException when the caller is not a RealtimeThread⁵².

Returns

The CPU consumption for this release. When dest is null, return the CPU consumption in an otherwise unused RelativeTime⁵³ instance in the current execution context, otherwise, when dest is not null, return the CPU consumption in dest

getCurrentConsumption

```
Equivalent to getCurrentConsumption(null).
Available since RTSJ 2.0
```

```
Signature
```

```
public static
javax.realtime.RelativeTime getCurrentConsumption()
```

getPendingFireCount

This is an accessor method for fireCount. The fireCount field nominally holds the number of times associated instances of AsyncEvent⁵⁴ have occurred that have not had the method handleAsyncEvent() invoked. It is incremented and decremented by the implementation of the RTSJ. The application logic may manipulate the value in this field for application-specific reasons.

Signature

protected

 $^{^{52}}$ Section 5.3.2.2 ⁵³Section 9.4.1.3

 $^{^{54}}$ Section 8.4.3.4

```
 \begin{array}{c} \text{int getPendingFireCount()} \\ Returns \\ \text{The value held by fireCount.} \end{array}
```

getAndClearPendingFireCount

This is an accessor method for fireCount. This method atomically sets the value of fireCount to zero and returns the value from before it was set to zero. This may used by handlers for which the logic can accommodate multiple releases in a single execution.

```
The general form for using this is public void handleAsyncEvent() {
  int numberOfReleases = getAndClearPendingFireCount();
  <handle the events>
}
```

The effect of a call to getAndClearPendingFireCount on the scheduling of this AEH depends on the semantics of the scheduler controlling this AEH.

The value held by fireCount prior to setting the value to zero.

${\bf get And Decrement Pending Fire Count}$

This is an accessor method for fireCount. This method atomically decrements, by one, the value of fireCount (when it is greater than zero) and returns the value from before the decrement. This method can be used in the handleAsyncEvent() method to handle multiple releases:

}

This construction is necessary only in the case where a handler wishes to avoid the setup costs since the framework guarantees that handleAsyncEvent() will be invoked whenever the fireCount is greater than zero. The effect of a call to getAnd-DecrementPendingFireCount on the scheduling of this AEH depends on the semantics of the scheduler controlling this AEH.

```
Signature

protected
int getAndDecrementPendingFireCount()

Returns

The value held by fireCount prior to decrementing it by one.
```

getMemoryArea

This is an accessor method for the initial instance of MemoryArea⁵⁵ associated with this.

```
Signature

public

javax.realtime.MemoryArea getMemoryArea()

Returns
```

The instance of MemoryArea⁵⁶ which was passed as the area parameter when this was created (or the default value when area was allowed to default. To determine the current status of the memory area stack associated with this, use the static methods defined in the RealtimeThread⁵⁷ class. That is RealtimeThread.getCurrentMemoryArea⁵⁸, RealtimeThread.getInitialMemoryAreaIndex⁵⁹, RealtimeThread.getMemoryAreaStackDepth⁶⁰.

${\tt getMemoryParameters}$

@inheritDoc

```
<sup>55</sup>Section 11.4.2.3

<sup>56</sup>Section 11.4.2.3

<sup>57</sup>Section 5.3.2.2

<sup>58</sup>Section 5.3.2.2.2

<sup>59</sup>Section 5.3.2.2.2

<sup>60</sup>Section 5.3.2.2.2
```

```
Signature
    javax.realtime.MemoryParameters getMemoryParameters()
Returns
    @inheritDoc
getReleaseParameters
  @inheritDoc
Signature
    public
    javax.realtime.ReleaseParameters getReleaseParameters()
    @inheritDoc
getScheduler
  @inheritDoc
Signature
    public
    javax.realtime.Scheduler getScheduler()
Returns
    @inheritDoc
getSchedulingParameters
  @inheritDoc
Signature
    javax.realtime.SchedulingParameters getSchedulingParameters()
Returns
    @inheritDoc
                             2.0 (Draft 20)
```

getProcessingGroup

```
@inheritDoc
Signature
    javax.realtime.ProcessingGroup getProcessingGroup()
Returns
    @inheritDoc
getProcessingGroupParameters
  @inheritDoc
Signature
    public
    javax.realtime.ProcessingGroupParameters
    getProcessingGroupParameters()
Returns
    @inheritDoc
getConfigurationParameters
  @inheritDoc
Signature
    public
    javax.realtime.ConfigurationParameters
    getConfigurationParameters()
Returns
    @inheritDoc
setMemoryParameters(MemoryParameters)
  @inheritDoc
```

```
Signature
     public
     void setMemoryParameters(MemoryParameters memory)
Parameters
     memory @inheritDoc
Throws
     IllegalArgumentException @inheritDoc
     IllegalAssignmentError @inheritDoc
     IllegalThreadStateException @inheritDoc
setReleaseParameters(ReleaseParameters)
   @inheritDoc
Signature
     public
     void setReleaseParameters(ReleaseParameters release)
Parameters 1  
     release @inheritDoc
Throws
     IllegalArgumentException @inheritDoc
     IllegalAssignmentError @inheritDoc
     IllegalThreadStateException @inheritDoc
setScheduler(Scheduler)
   @inheritDoc
Signature
     public
     void setScheduler(Scheduler scheduler)
Parameters
     scheduler @inheritDoc
Throws
     IllegalArgumentException @inheritDoc
     IllegalAssignmentError @inheritDoc
     SecurityException @inheritDoc
     IllegalThreadStateException @inheritDoc
                               2.0 (Draft 20)
```

setScheduler(Scheduler, SchedulingParameters, ReleaseParameters, MemoryParameters, ProcessingGroupParameters)

@inheritDoc

```
public
    void setScheduler(Scheduler scheduler, SchedulingParameters
    scheduling, ReleaseParameters release, MemoryParameters
    memoryParameters, ProcessingGroupParameters group)

Parameters
    scheduler @inheritDoc
    scheduling @inheritDoc
```

scheduling @inheritDoc release @inheritDoc memoryParameters @inheritDoc

group @inheritDoc

Throws

$$\label{legalArgumentException} \begin{split} & \textit{IllegalArgumentException} \ @inheritDoc \\ & \textit{IllegalAssignmentError} \ @inheritDoc \\ & \textit{IllegalThreadStateException} \ @inheritDoc \\ & \textit{SecurityException} \ @inheritDoc \\ \end{split}$$

setSchedulingParameters(SchedulingParameters)

@inheritDoc

```
Signature
```

public

void setSchedulingParameters(SchedulingParameters scheduling)

Parameters

scheduling @inheritDoc

Throws

$$\label{legalArgumentException} \begin{split} \textit{IllegalArgumentException} & \text{ @inheritDoc} \\ \textit{IllegalAssignmentError} & \text{ @inheritDoc} \\ \textit{IllegalThreadStateException} & \text{ @inheritDoc} \\ \end{split}$$

setProcessingGroupParameters(ProcessingGroupParameters)

@inheritDoc

```
Signature \\ \text{public} \\ \text{void setProcessingGroupParameters(ProcessingGroupParameters group)} \\ Parameters \\ group @inheritDoc \\ Throws \\ IllegalArgumentException @inheritDoc \\ IllegalAssignmentError @inheritDoc \\ IllegalThreadStateException &inheritDoc \\ IllegalThreadStateExcept
```

setDaemon(boolean)

Marks this event handler as either a daemon event handler or a user event handler. A realtime virtual machine exits when the only schedulables and threads running are all daemon. This method must be called before the event handler is attached to any event. Once attached, it cannot be changed.

Available since RTSJ 1.0.1

```
Signature
```

```
public final
void setDaemon(boolean on)
```

Parameters

on When true, marks this event handler as a daemon handler.

Throws

IllegalThreadStateException when this event handler is attached to an AE. SecurityException when the current schedulable cannot modify this event handler.

isDaemon

Tests if this event handler is a daemon handler.

Available since RTSJ 1.0.1

```
Signature
    public final
    boolean isDaemon()
Returns
    True when this event handler is a daemon handler; false otherwise.
getDispatcher
See Section AsyncTimable.getDispatcher()
Available since RTSJ 2.0
Signature
    public
    javax.realtime.TimeDispatcher getDispatcher()
getMinConsumption(RelativeTime)
Available since RTSJ 2.0
Signature
    public
    javax.realtime.RelativeTime getMinConsumption(RelativeTime dest)
getMinConsumption
Available since RTSJ 2.0
Signature
    public
```

javax.realtime.RelativeTime getMinConsumption()

getMaxConsumption(RelativeTime)

Available since RTSJ 2.0

```
Signature

public
    javax.realtime.RelativeTime getMaxConsumption(RelativeTime dest)
```

getMaxConsumption

Available since RTSJ 2.0

```
Signature
    public
    javax.realtime.RelativeTime getMaxConsumption()
```

mayUseHeap

Determine whether or not this schedulable may use the heap.

Available since RTSJ 2.0

```
Signature

public
boolean mayUseHeap()
```

Returns

 ${\tt true}$ only when this ${\tt Schedulable}$ may allocate on the heap and may enter the ${\tt Heap}.$

awaken

Indicate that a sleep has ended.

See Section Schedulable.awaken()

Available since RTSJ 2.0

```
Signature public final void awaken()
```

8.4.3.3 ActiveEventDispatcher

Provides a means of dispatching a set of ActiveEvent⁶¹s. It acts as if it contains a RealtimeThread to perform this task. The priority of this thread can be specified when a dispatcher object is created. The default dispatcher runs at the highest Java realtime priority.

Application code should not extend this class.

Inheritance

```
java.lang.Object
javax.realtime.ActiveEventDispatcher
Interfaces
RealtimeExecutionContext
```

8.4.3.3.1 Constructors

${\bf Active Event Dispatcher (Scheduling Parameters)}$

Create a new dispatcher.

Signature

protected
 ActiveEventDispatcher(SchedulingParameters schedule)

⁶¹Section 8.4.1.1

Parameters

schedule provide scheduling informs to the new object.

8.4.3.3.2 Methods

getSchedulingParameters

```
public
    javax.realtime.SchedulingParameters getSchedulingParameters()
```

register(T)

Register a POSIX signal with this dispatcher.

```
Signature
```

```
public abstract
void register(T event)
throws RegistrationException, IllegalStateException,
IllegalArgumentException
```

Parameters

event to register

Throws

RegistrationException when event is already registered. IllegalStateException when this object has been destroyed. IllegalArgumentException when event is not stopped.

unregister(T)

Deregister a POSIX Signal form this dispatcher. (This is a really naive implementation.)

Signature

public abstract

```
void unregister(T event)
throws DeregistrationException, IllegalStateException,
IllegalArgumentException

Parameters
event to deregister

Throws

DeregistrationException when event is already registered.
IllegalStateException when this object has been destroyed.
IllegalArgumentException when event is not stopped.
```

destroy

Makes the dispatcher unusable.

```
Signature
```

```
public abstract
void destroy()
throws IllegalStateException
```

Throws

IllegalStateException when called on a dispatcher that has one or more registered objects.

8.4.3.4 AsyncEvent

An asynchronous event can have a set of handlers associated with it, and when the event occurs, the fireCount of each handler is incremented, and the handlers are released (see AsyncEventHandler⁶²).

Inheritance

```
javax.realtime.AbstractAsyncEvent
javax.realtime.AsyncEvent
```

8.4.3.4.1 Constructors

 $^{^{62}}$ Section 8.4.3.5

AsyncEvent

Create a new AsyncEvent object.

```
Signature

public

AsyncEvent()
```

8.4.3.4.2 Methods

fire

When enabled, release the asynchronous events associated with this instance of AsyncEvent. When no handlers are attached or this object is disabled the method does nothing, i.e., it skips the release.

- When the instance of AsyncEvent has more than one instance of AsyncEventHandler with release parameters object of type AperiodicParameters attached and the execution of AsyncEvent.fire() introduces the requirement to throw at least one type of exception, then all instances of AsyncEventHandler not affected by the exception are handled normally
- When the instance of AsyncEvent has more than one instance of AsyncEvent-Handler with release parameters object of type SporadicParameters attached and the execution of AsyncEvent.fire() introduces the simultaneous requirement to throw more than one type of exception or error then MITViolationException⁶³ has precedence over ArrivalTimeQueueOverflowException⁶⁴.

```
Signature

public

void fire()

Throws
```

MITViolationException Thrown under the base priority scheduler's semantics when there is a handler associated with this event that has its MIT violated

```
<sup>63</sup>Section 14.2.2.6

<sup>64</sup>Section 14.2.2.1
```

by the call to fire (and it has set the minimum inter-arrival time violation behavior to MITViolationExcept). Only the handlers which do not have their MITs violated are released in this situation.

Arrival Time Queue Overflow Exception when the queue of arrival time information overflows. Only the handlers which do not cause this exception to be thrown are released in this situation.

8.4.3.5 AsyncEventHandler

An asynchronous event handler encapsulates code that is released after an instance of AsyncEvent⁶⁵ to which it is attached occurs.

It is guaranteed that multiple releases of an event handler will be serialized. It is also guaranteed that (unless the handler explicitly chooses otherwise) for each release of the handler, there will be one execution of the AsyncEventHandler.handleAsyncEvent()⁶⁶ method. Control over the number of calls to AsyncEventHandler.handleAsyncEvent()⁶⁷ is given by methods which manipulate a fireCount. These may be called by the application via sub-classing and overriding AsyncEventHandler.handleAsyncEvent()⁶⁸.

Instances of AsyncEventHandler with a release parameter of type Sporadic-Parameters⁶⁹ or AperiodicParameters⁷⁰ have a list of release times which correspond to the occurrence times of instances of AsyncEvent⁷¹ to which they are attached. The minimum interarrival time specified in SporadicParameters⁷² is enforced when a release time is added to the list. Unless the handler explicitly chooses otherwise, there will be one execution of the code in AsyncEventHandler.handleAsyncEvent()⁷³ for each entry in the list.

The deadline and the time each release event causes the AEH to become eligible for execution are properties of the scheduler that controls the AEH. For the base **scheduler** (at ../../sched_overview-summary.html#AperiodicScheduling), the deadline for each release event is relative to its fire time, and the release takes place at fire time but execution eligibility may be deferred when the queue's MIT violation policy is SAVE.

```
65 Section 8.4.3.4

66 Section 8.4.3.5.2

67 Section 8.4.3.5.2

68 Section 8.4.3.5.2

69 Section 6.4.2.14

70 Section 6.4.2.2

71 Section 8.4.3.4

72 Section 6.4.2.14

73 Section 8.4.3.5.2
```

Handlers may do almost anything a realtime thread can do. They may run for a long or short time, and they may block. (Note: blocked handlers may hold system resources.) A handler may not use the RealtimeThread.waitForNextRelease⁷⁴ or RealtimeThread.waitForNextReleaseInterruptible⁷⁵ methods.

Normally, handlers are bound to an execution context dynamically when the instances of AsyncEvent⁷⁶s to which they are bound occur. This can introduce a (small) time penalty. For critical handlers that can not afford the expense, and where this penalty is a problem, BoundAsyncEventHandler⁷⁷s can be used.

The scheduler for an asynchronous event handler is inherited from the thread/schedulable that created it. When it was created from a Java thread, the scheduler is the current default scheduler.

The semantics for memory areas that were defined for realtime threads apply in the same way to instances of AsyncEventHandler They may inherit a scope stack when they are created, and the single parent rule applies to the use of memory scopes for instances of AsyncEventHandler just as it does in realtime threads.

Inheritance

java.lang.Object javax.realtime.AbstractAsyncEventHandler javax.realtime.AsyncEventHandler

8.4.3.5.1 Constructors

AsyncEventHandler(SchedulingParameters, ReleaseParameters, MemoryParameters, ProcessingGroup, ConfigurationParameters, Runnable)

Create a handler with the given scheduling, release, memory, group, and configuration parameters to run the given logic.

Available since RTSJ 2.0

Signature

⁷⁴Section 5.3.2.2.2

 $^{^{75}\}mathrm{Section}\ 5.3.2.2.2$

 $^{^{76}}$ Section 8.4.3.4

⁷⁷Section 8.4.3.10

public

AsyncEventHandler(SchedulingParameters scheduling, ReleaseParameters release,

Parameters

scheduling parameters for scheduling the new handler (and possibly other instances of Schedulable⁷⁸). When scheduling is null and the creator is an instance of Schedulable⁷⁹, SchedulingParameters⁸⁰ is a clone of the creator's value created in the same memory area as this. When scheduling is null and the creator is a Java thread, the contents and type of the new SchedulingParameters object is governed by the associated scheduler.

release parameters for scheduling the new handler (and possibly other instances of Schedulable⁸¹). When release is null the new AsyncEventHandler will use a clone of the default ReleaseParameters⁸² for the associated scheduler created in the memory area that contains the AsyncEventHandler object.

memory parameters for scheduling the new handler (and possibly other instances of Schedulable⁸³). When memory is null, the new AsyncEventHandler receives null value for its memory parameters, and the amount or rate of memory allocation for the new handler is unrestricted.

group parameters for providing CPU cost management on a set of Schedul-able⁸⁴s. When null, this will not be associated with any processing group. initial parameters for reserving space for preallocated exceptions and change implementation specific per Schedulable⁸⁵ memory reservations, such as Java stack size, for the new handler (and possibly other instances of Schedulable⁸⁶. When initial is null, this AsyncEventHandler will reserve no space for preallocated exceptions and implementation-specific values will be set to their implementation-defined defaults.

logic The Runnable object whose run() method will serve as the logic for the new AsyncEventHandler. When logic is null, the handleAsyncEvent() method in the new object will serve as its logic.

⁷⁸Section 6.4.1.2

 $^{^{79}}$ Section 6.4.1.2

⁸⁰Section 6.4.2.13

⁸¹Section 6.4.1.2

 $^{^{82}}$ Section 6.4.2.9

 $^{^{83}}$ Section 6.4.1.2

⁸⁴Section 6.4.1.2

⁸⁵Section 6.4.1.2

 $^{^{86}}$ Section 6.4.1.2

AsyncEventHandler(SchedulingParameters, ReleaseParameters, Runnable)

Calling this constructor is equivalent to calling AsyncEventHandler(SchedulingParameters, ReleaseParameters, MemoryParameters, ProcessingGroupParameters, ConfigurationParameters, Runnable)⁸⁷ with arguments (scheduling, release, null, null, logic).

See Section AsyncEventHandler(SchedulingParameters, ReleaseParameters, MemoryParameters, ProcessingGroupParameters, ConfigurationParameters, Runnable)

Available since RTSJ 2.0

Signature

public

AsyncEventHandler(SchedulingParameters scheduling, ReleaseParameters release, Runr

AsyncEventHandler(SchedulingParameters, ReleaseParameters)

Calling this constructor is equivalent to calling AsyncEventHandler(SchedulingParameters, ReleaseParameters, MemoryParameters, ProcessingGroupParameters, ConfigurationParameters, Runnable) 88 with arguments (scheduling, release, null, null, null, null)

See Section AsyncEventHandler(SchedulingParameters, ReleaseParameters, MemoryParameters, ProcessingGroupParameters, ConfigurationParameters, Runnable)

Available since RTSJ 2.0

Signature

public

AsyncEventHandler(SchedulingParameters scheduling, ReleaseParameters release)

⁸⁷Section ??

⁸⁸Section ??

AsyncEventHandler(Runnable)

Calling this constructor is equivalent to calling AsyncEventHandler(SchedulingParameters, ReleaseParameters, MemoryParameters, ProcessingGroupParameters, ConfigurationParameters, Runnable) with arguments (null, null, null, null, null, logic).

```
Signature

public

AsyncEventHandler(Runnable logic)
```

AsyncEventHandler

Create an instance of AsyncEventHandler with default values for all parameters. See Section AsyncEventHandler(SchedulingParameters, ReleaseParameters, MemoryParameters, ProcessingGroupParameters, ConfigurationParameters, Runnable)

```
Signature

public

AsyncEventHandler()
```

8.4.3.5.2 Methods

handle A sync Event

This method holds the logic which is to be executed when any AsyncEvent⁹⁰ with which this handler is associated is fired. This method will be invoked repeatedly while fireCount is greater than zero.

```
<sup>89</sup>Section ??

<sup>90</sup>Section 8.4.3.4
```

The default implementation of this method invokes the **run** method of any non-null **logic** instance passed to the constructor of this handler.

This AEH acts as a source of "reference" for its initial memory area while it is released.

All throwables from (or propagated through) handleAsyncEvent are caught, a stack trace is printed and execution continues as if handleAsyncEvent had returned normally.

```
Signature

public

void handleAsyncEvent()
```

initialMemoryPinnable

Test to see if the default memory area is a pinned scoped memory area.

Available since RTSJ 2.0

```
Signature

public
boolean initialMemoryPinnable()

Returns
```

true is the default memory area is a pinned scoped memory area.

run

When used as part of the internal mechanism activated by firing an async event, this method's detailed semantics are defined by the scheduler associated with this handler.

The general outline is:

```
enter initial memory area
while (fireCount > 0)
{
    [initiate release]
    fireCount--;
    try { handleAsyncEvent(); }
    catch (Throwable th) { th.printStackTrace(); }
    [effect completion]
}
```

leave initial memory area

All throwables from (or propagated through) handleAsyncEvent⁹¹ are caught, a stack trace is printed and execution continues as if handleAsyncEvent had returned normally.

```
When it is directly invoked, this method invokes handleAsyncEvent 2 repeatedly while the fireCount is greater than zero; e.g., while (getAndDecrementPendingFireCount() > 0) {
    enter initial memory area handleAsyncEvent();
    leave initial memory area }
```

however direct invocation of run is not recommended as it may interact with the normal release of this handler.

Applications cannot override this method and thus should use the logic parameter at construction, or override handleAsyncEvent() in subclasses with the logic of the handler.

```
Signature
public final
void run()
```

8.4.3.6 AsyncLongEvent

A new type of event that carries a long as a payload. See Section AsyncEvent

Available since RTSJ 2.0

Inheritance

```
java.lang.Object
javax.realtime.AbstractAsyncEvent
javax.realtime.AsyncLongEvent
```

⁹¹Section 8.4.3.5.2 ⁹²Section 8.4.3.5.2

8.4.3.6.1 Constructors

AsyncLongEvent

Create a new AsyncEvent object.

```
Signature

public

AsyncLongEvent()
```

8.4.3.6.2 Methods

fire(long)

When enabled, release the asynchronous events associated with this instance of AsyncLongEvent with the long passed by fire(long)⁹³. When no handlers are attached or this object is disabled the method does nothing, i.e., it skips the release.

- When the instance of AsyncLongEvent is associated with more than one instance of AsyncLongEventHandler⁹⁴ with release parameters object of type AperiodicParameters⁹⁵ and the execution of fire(long)⁹⁶ introduces the requirement to throw at least one type of exception, then all instances of AsyncLongEventHandler⁹⁷ not affected by the exception are handled normally.
- When this instance of AsyncLongEvent is associated with more than one instance of AsyncLongEventHandler⁹⁸ with release parameters object of type SporadicParameters⁹⁹ and the execution of fire(long)¹⁰⁰ introduces the simultaneous requirement to throw more than one type of exception or error,

```
93 Section 8.4.3.6.2
94 Section 8.4.3.7
95 Section 6.4.2.2
96 Section 8.4.3.6.2
97 Section 8.4.3.7
98 Section 8.4.3.7
99 Section 6.4.2.14
100 Section 8.4.3.6.2
```

then MITViolation Exception 101 has precedence over Arrival TimeQueueOverflowException $^{102}.$

Signature

```
public
void fire(long value)
```

 $throws \ {\tt MITV} iolation {\tt Exception}, \ {\tt ArrivalTimeQueueOverflowException}$

Parameters

value is the payload passed to the event.

Throws

MITViolationException Thrown under the base priority scheduler's semantics, when there is a handler associated with this event that has its MIT violated by the call to fire (and it has set the minimum inter-arrival time violation behavior to MITViolationExcept). Only the handlers which do not have their MITs violated are released in this situation.

Arrival Time Queue Overflow Exception when the queue of arrival time information overflows. Only the handlers which do not cause this exception to be thrown are released in this situation.

8.4.3.7 AsyncLongEventHandler

A version of AbstractAsyncEventHandler¹⁰³ that carries a long value as paylaod. Available since RTSJ 2.0

Inheritance

```
javax.realtime.AbstractAsyncEventHandler
javax.realtime.AsyncLongEventHandler
```

8.4.3.7.1 Constructors

 $^{^{101}}$ Section 14.2.2.6

¹⁰²Section 14.2.2.1

 $^{^{103}\}mathrm{Section}~8.4.3.2$

AsyncLongEventHandler(SchedulingParameters, ReleaseParameters, MemoryParameters, ProcessingGroup, ConfigurationParameters, LongConsumer)

Create an asynchronous event handler that receives a Long payload with each fire.

Signature

public

 $A sync Long Event Handler (Scheduling Parameters \ scheduling, \ Release Parameters \ release, \ and \ release Parameters \ release, \ release Parameters \ release Parameters \ release, \ release Parameters \ rele$

Parameters

scheduling parameters for the new handler. release parameters for the new handler. memory parameters for the new handler. group parameters for the new handler. sizing parameters for the new handler. logic is the logic to run for each fire.

A syncLong Event Handler (Scheduling Parameters, Release Parameters, Long Consumer)

Calling this constructor is equivalent to calling AsyncLongEventHandler(SchedulingParameters, ReleaseParameters, MemoryParameters, ProcessingGroup, ConfigurationParameters, LongConsumer) 104 with arguments (scheduling, release, null, null, null, logic).

Signature

public

AsyncLongEventHandler(SchedulingParameters scheduling, ReleaseParameters release,

¹⁰⁴Section 8.4.3.7.1

AsyncLongEventHandler(SchedulingParameters, ReleaseParameters)

Calling this constructor is equivalent to calling AsyncLongEventHandler(SchedulingParameters ReleaseParameters, MemoryParameters, ProcessingGroup, ConfigurationParameters, LongConsumer) with arguments (scheduling, release, null, null, null, null)

Signature

public

AsyncLongEventHandler(SchedulingParameters scheduling, ReleaseParameters rele

AsyncLongEventHandler(LongConsumer)

Calling this constructor is equivalent to calling AsyncLongEventHandler(SchedulingParameters ReleaseParameters, MemoryParameters, ProcessingGroup, ConfigurationParameters, LongConsumer) with arguments (null, null, null, null, null, null, null, logic).

Signature

public

AsyncLongEventHandler(LongConsumer logic)

AsyncLongEventHandler

Create an instance of AsyncLongEventHandler with default values for all parameters.

See Section AsyncLongEventHandler(SchedulingParameters, ReleaseParameters, MemoryParameters, ProcessingGroup, ConfigurationParameters, LongConsumer)

Signature

¹⁰⁵Section 8.4.3.7.1 ¹⁰⁶Section 8.4.3.7.1

```
public
   AsyncLongEventHandler()
```

8.4.3.7.2 Methods

handleAsyncEvent(long)

This method holds the logic which is to be executed when any AsyncEvent¹⁰⁷ with which this handler is associated is fired. This method will be invoked repeatedly while fireCount is greater than zero.

This ALEH is a source of reference for its initial memory area while this ALEH is released.

All throwables from (or propagated through) handleAsyncEvent are caught, a stack trace is printed and execution continues as if handleAsyncEvent had returned normally.

```
Signature

public

void handleAsyncEvent(long payload)

Parameters

payload is the long value associated with a fire.
```

peekPending

```
Signature
    public
    long peekPending()
    throws IllegalStateException
Throws
    IllegalStateException when the fire count is zero.
Returns
```

The long value at the head of the queue of longs to be passed to handleAsyncEvent(long)¹⁰⁸.

¹⁰⁷Section 8.4.3.4 ¹⁰⁸Section 8.4.3.7.2

run

When used as part of the internal mechanism activated by firing an async event, this method's detailed semantics are defined by the scheduler associated with this handler.

The general outline is as follows:

```
enter initial memory area
while (fireCount > 0)
{
    [initiate release]
    fireCount--;
    try
    {
       handleAsyncEvent(value);
    }
    catch (Throwable th)
    {
       th.printStackTrace();
    }
    [effect completion]
}
leave initial memory area
```

All throwables from (or propagated through) handleAsyncEvent¹⁰⁹ are caught, a stack trace is printed and execution continues as if handleAsyncEvent had returned normally.

```
When it is directly invoked, this method invokes handleAsyncEvent<sup>110</sup> repeatedly while the fireCount is greater than zero; e.g., while (getAndDecrementPendingFireCount() > 0) enter initial memory area handleAsyncEvent(value); leave initial memory area
```

however direct invocation of run is not recommended as it may interact with the normal release of this handler.

Applications cannot override this method and thus should use the logic parameter at construction, or override handleAsyncEvent() in subclasses with the logic of the handler.

¹⁰⁹Section 8.4.3.7.2 ¹¹⁰Section 8.4.3.7.2

```
Signature

public final

void run()
```

8.4.3.8 AsyncObjectEvent

A new type of event that carries an object as a payload. See Section AsyncEvent

Available since RTSJ 2.0

Inheritance

```
javax.realtime.AbstractAsyncEvent
javax.realtime.AsyncObjectEvent
```

8.4.3.8.1 Constructors

AsyncObjectEvent

Create a new AsyncEvent object.

Signature

```
public
  AsyncObjectEvent()
```

8.4.3.8.2 Methods

fire(PAYLOAD)

When enabled, fire this instance of AsyncObjectEvent. The asynchronous event handlers associated with this event will be released with the object passed by {link

2.0 (Draft 20)

fire(PAYLOAD)¹¹¹. When no handlers are attached or this object is disabled the method does nothing, i.e., it skips the release.

- When the instance of AsyncObjectEvent is associated with more than one instance of AsyncObjectEventHandler¹¹² with release parameters object of type AperiodicParameters¹¹³ and the execution of fire(PAYLOAD)¹¹⁴ introduces the requirement to throw at least one type of exception, then all instances of AsyncObjectEventHandler¹¹⁵ not affected by the exception are handled normally.
- When this instance of AsyncObjectEvent is associated with more than one instance of AsyncObjectEventHandler¹¹⁶ with release parameters object of type SporadicParameters¹¹⁷ and the execution of fire(PAYLOAD)¹¹⁸ introduces the simultaneous requirement to throw more than one type of exception or error, then MITViolationException¹¹⁹ has precedence over ArrivalTime—QueueOverflowException¹²⁰.

Signature

```
public
void fire(PAYLOAD value)
```

throws MITViolationException, ArrivalTimeQueueOverflowException

Parameters

value is the payload passed to the event.

Throws

MITViolationException Thrown under the base priority scheduler's semantics when there is a handler associated with this event that has its MIT violated by the call to fire (and it has set the minimum inter-arrival time violation behavior to MITViolationExcept). Only the handlers which do not have their MITs violated are released in this situation.

Arrival Time Queue Overflow Exception when the queue of arrival time information overflows. Only the handlers which do not cause this exception to be thrown are released in this situation.

```
111 Section 8.4.3.8.2

112 Section 8.4.3.9

113 Section 6.4.2.2

114 Section 8.4.3.8.2

115 Section 8.4.3.9

116 Section 8.4.3.9

117 Section 6.4.2.14

118 Section 8.4.3.8.2

119 Section 14.2.2.6

120 Section 14.2.2.1
```

8.4.3.9 AsyncObjectEventHandler

A version of AbstractAsyncEventHandler¹²¹ that carries an Object value as payland.

Available since RTSJ 2.0

Inheritance

java.lang.Object javax.realtime.AbstractAsyncEventHandler javax.realtime.AsyncObjectEventHandler

8.4.3.9.1 Constructors

AsyncObjectEventHandler(SchedulingParameters, ReleaseParameters, MemoryParameters, ProcessingGroup, ConfigurationParameters, java.util.function.Consumer<PAYLOAD>)

Create an asynchronous event handler that receives a Long payload with each fire.

Signature

public

 $A sync Object Event Handler (Scheduling Parameters \ scheduling, \ Release Parameters \ rel$

Parameters

scheduling parameters for the new handler.
release parameters for the new handler.
memory parameters for the new handler.
group parameters for the new handler.
sizing parameters for the new handler.
logic is the logic to run for each fire.

 $^{^{121}}$ Section 8.4.3.2

AsyncObjectEventHandler(SchedulingParameters, ReleaseParameters, java.util.function.Consumer<PAYLOAD>)

Calling this constructor is equivalent to calling AsyncObjectEventHandler(SchedulingParameter ReleaseParameters, MemoryParameters, ProcessingGroupParameters, ConfigurationParameters, Consumer) with arguments (scheduling, release, null, null, logic).

Signature

public

AsyncObjectEventHandler(SchedulingParameters scheduling, ReleaseParameters re

$\label{lem:asyncObjectEventHandler} A syncObjectEventHandler (Scheduling Parameters, Release Parameters)$

Calling this constructor is equivalent to calling AsyncObjectEventHandler(SchedulingParamete ReleaseParameters, MemoryParameters, ProcessingGroupParameters, ConfigurationParameters, Consumer) with arguments (scheduling, release, null, null, null, null)

Signature

public

AsyncObjectEventHandler(SchedulingParameters scheduling, ReleaseParameters re

AsyncObjectEventHandler(java.util.function.Consumer<PAYLOAD>)

Calling this constructor is equivalent to calling AsyncObjectEventHandler(SchedulingParameter ReleaseParameters, MemoryParameters, ProcessingGroupParameters, ConfigurationParameters, Consumer) with arguments (null, null, null, null, null, null, null, null, logic).

¹²²Section ??

 $^{^{123}}$ Section ??

 $^{^{124}}$ Section ??

```
Signature
```

```
public
```

AsyncObjectEventHandler(java.util.function.Consumer<PAYLOAD> logic)

Parameters

logic is the function to call on the object received.

AsyncObjectEventHandler

Create an instance of AsyncObjectEventHandler with default values for all parameters.

See Section AsyncObjectEventHandler(SchedulingParameters, ReleaseParameters, MemoryParameters, ProcessingGroupParameters, ConfigurationParameters, Consumer)

Signature

```
public
```

AsyncObjectEventHandler()

8.4.3.9.2 Methods

peekPending

```
Signature
```

```
public
```

PAYLOAD peekPending() throws IllegalStateException

Throws

IllegalStateException when the fire count is zero.

2.0 (Draft 20)

Returns

The object reference at the head of the queue of object references to be passed to handleAsyncEvent(PAYLOAD)¹²⁵}.

run

When used as part of the internal mechanism activated by firing an async event, this method's detailed semantics are defined by the scheduler associated with this handler.

The general outline is:

```
enter initial memory area
while (fireCount > 0)
{
    [initiate release]
    fireCount--;
    try { handleAsyncEvent(value); }
    catch (Throwable th) { th.printStackTrace(); }
    [effect completion]
}
leave initial memory area
```

All throwables from (or propagated through) handleAsyncEvent(PAYLOAD)¹²⁶} are caught, a stack trace is printed and execution continues as if handleAsyncEvent had returned normally.

```
When it is directly invoked, this method invokes handleAsyncEvent(PAYLOAD)<sup>127</sup>} repeatedly while the fireCount is greater than zero; e.g., while (getAndDecrementPendingFireCount() > 0)
{
    enter initial memory area handleAsyncEvent(value); leave initial memory area
}
```

however direct invocation of run is not recommended as it may interact with the normal release of this handler.

Applications cannot override this method and thus should use the logic parameter at construction, or override handleAsyncEvent in subclasses with the logic of the handler.

¹²⁵ Section ?? 126 Section ?? 127 Section ??

```
Signature
public final
void run()
```

8.4.3.10 BoundAsyncEventHandler

A bound asynchronous event handler is an instance of AsyncEventHandler¹²⁸ that is permanently bound to a dedicated realtime thread. Bound asynchronous event handlers are for use in situations where the added timeliness is worth the overhead of dedicating an individual realtime thread to the handler. Individual server realtime threads can only be dedicated to a single bound event handler.

Inheritance

```
java.lang.Object
    javax.realtime.AbstractAsyncEventHandler
    javax.realtime.AsyncEventHandler
    javax.realtime.BoundAsyncEventHandler

Interfaces
BoundAbstractAsyncEventHandler
```

8.4.3.10.1 Constructors

BoundAsyncEventHandler(SchedulingParameters, ReleaseParameters, MemoryParameters, ProcessingGroup, ConfigurationParameters, Runnable)

Signature

public

BoundAsyncEventHandler(SchedulingParameters scheduling, ReleaseParameters release,

 $^{^{128}\}mathrm{Section}~8.4.3.5$

BoundAsyncEventHandler(SchedulingParameters, ReleaseParameters, MemoryParameters, ProcessingGroupParameters, ConfigurationParameters, Runnable)

Signature

public

BoundAsyncEventHandler(SchedulingParameters scheduling, ReleaseParameters rel

BoundAsyncEventHandler(SchedulingParameters, ReleaseParameters, Runnable)

Signature

public

 ${\tt BoundAsyncEventHandler} ({\tt SchedulingParameters\ scheduling},\ {\tt ReleaseParameters\ releaseParameters$

BoundAsyncEventHandler(SchedulingParameters, ReleaseParameters)

Signature

public

BoundAsyncEventHandler(SchedulingParameters scheduling, ReleaseParameters rel

BoundAsyncEventHandler(Runnable)

Signature

2.0 (Draft 20)

```
public
  BoundAsyncEventHandler(Runnable logic)
```

BoundAsyncEventHandler

Create an instance of BoundAsyncEventHandler using default values. This constructor is equivalent to BoundAsyncEventHandler(null, null, null, null, null, null) false, null)

```
Signature

public

BoundAsyncEventHandler()
```

8.4.3.11 BoundAsyncLongEventHandler

A bound asynchronous event handler is an instance of AsyncEventHandler¹²⁹ that is permanently bound to a dedicated realtime thread. Bound asynchronous event handlers are for use in situations where the added timeliness is worth the overhead of dedicating an individual realtime thread to the handler. Individual server realtime threads can only be dedicated to a single bound event handler.

Available since RTSJ 2.0

Inheritance

```
java.lang.Object
    javax.realtime.AbstractAsyncEventHandler
    javax.realtime.AsyncLongEventHandler
    javax.realtime.BoundAsyncLongEventHandler

Interfaces
BoundAbstractAsyncEventHandler
```

8.4.3.11.1 Constructors

¹²⁹Section 8.4.3.5

BoundAsyncLongEventHandler(SchedulingParameters, Release-Parameters, MemoryParameters, ProcessingGroup, ConfigurationParameters, LongConsumer)

Signature

public

BoundAsyncLongEventHandler(SchedulingParameters scheduling, ReleaseParameters

BoundAsyncLongEventHandler(SchedulingParameters, Release-Parameters, LongConsumer)

Signature

public

 ${\tt BoundAsyncLongEventHandler} (Scheduling Parameters\ scheduling,\ Release Parameters\ scheduling) and the property of the$

BoundAsyncLongEventHandler(SchedulingParameters, Release-Parameters)

Signature

public

 ${\tt BoundAsyncLongEventHandler} (Scheduling Parameters\ scheduling,\ Release Parameters\ scheduling)$

Bound A sync Long Event Handler (Long Consumer)

Signature

2.0 (Draft 20)

```
public
  BoundAsyncLongEventHandler(LongConsumer logic)
```

${\bf Bound A sync Long Event Handler}$

Create an instance of BoundAsyncEventHandler using default values. This constructor is equivalent to BoundAsyncEventHandler(null, null, null, null, null, false, null)

Signature

public

BoundAsyncLongEventHandler()

8.4.3.12 BoundAsyncObjectEventHandler

A bound asynchronous event handler is an instance of AsyncEventHandler¹³⁰ that is permanently bound to a dedicated realtime thread. Bound asynchronous event handlers are for use in situations where the added timeliness is worth the overhead of dedicating an individual realtime thread to the handler. Individual server realtime threads can only be dedicated to a single bound event handler.

Available since RTSJ 2.0

Inheritance

java.lang.Object
 javax.realtime.AbstractAsyncEventHandler
 javax.realtime.AsyncObjectEventHandler
 javax.realtime.BoundAsyncObjectEventHandler

Interfaces
BoundAbstractAsyncEventHandler

8.4.3.12.1 Constructors

 $^{^{130}}$ Section 8.4.3.5

BoundAsyncObjectEventHandler(SchedulingParameters, ReleaseParameters, MemoryParameters, ProcessingGroup, ConfigurationParameters, java.util.function.Consumer<Payload>)

```
public
BoundAsyncObjectEventHandler(SchedulingParameters scheduling, ReleaseParameter)

Parameters
scheduling
release
```

BoundAsyncObjectEventHandler(SchedulingParameters, ReleaseParameters, java.util.function.Consumer<Payload>)

```
Signature
```

public

 $\begin{array}{c} memory\\ group\\ sizing\\ logic \end{array}$

 ${\tt BoundAsyncObjectEventHandler(SchedulingParameters\ scheduling,\ ReleaseParameters\ schedu$

BoundAsyncObjectEventHandler(SchedulingParameters, ReleaseParameters)

Signature

public

BoundAsyncObjectEventHandler(SchedulingParameters scheduling, ReleaseParamete

2.0 (Draft 20)

284 8.5 Rationale

BoundAsyncObjectEventHandler(java.util.function.Consumer<Payload>)

```
Signature

public

BoundAsyncObjectEventHandler(java.util.function.Consumer<Payload> logic)
```

BoundAsyncObjectEventHandler

Create an instance of BoundAsyncEventHandler using default values. This constructor is equivalent to BoundAsyncEventHandler(null, null, null, null, null)

```
Signature
    public
    BoundAsyncObjectEventHandler()
```

8.5 Rationale

The design of the asynchronous event handling facilities was intended to provide the necessary functionality while allowing efficient implementations and catering for a variety of realtime applications. In particular, in some realtime systems there may be a large number of potential events and event handlers (numbering in the thousands or perhaps even the tens of thousands), although at any given time only a small number will be used. Thus it would not be appropriate to dedicate a realtime thread to each event handler. The RTSJ addresses this issue by allowing the programmer to specify an event handler either as not bound to a specific realtime thread (the class AsyncEventHandler) or alternatively as bound to a dedicated realtime thread (the class BoundAsyncEventHandler). The RTSJ does not define at what point a non-bound event handler is bound to a realtime thread for its execution. Events are dataless: the fire method does not pass any data to the handler. This was intentional in the interest of simplicity and efficiency. An application that needs to associate data with an AsyncEvent can do so explicitly by setting up a buffer; it will then need to deal with buffer overflow issues as required by the application.

8 Asynchrony 285

The ability to trigger an ATC in a schedulable is necessary in many kinds of realtime applications but must be designed carefully in order to minimize the risks of problems such as data structure corruption and deadlock. There is, invariably, a tension between the desire to cause an ATC to be immediate, and the desire to ensure that certain sections of code are executed to completion.

One basic decision was to allow ATC in a method only if the method explicitly permits this. The default of no ATC is reasonable, since legacy code might be written expecting no ATC, and asynchronously aborting the execution of such a method could lead to unpredictable results. Since the natural way to model ATC is with an exception (AsynchronouslyInterruptedException), the way that a method indicates its susceptibility to ATC is by including AsynchronouslyInterrupted-Exception in its throws clause. Causing this exception to be thrown in a realtime thread t as an effect of calling t.interrupt() was a natural extension of the semantics of interrupt as currently defined by java.lang.Thread.

One ATC-deferred section is synchronized code. This is a context that needs to be executed completely in order to ensure a program operates correctly. If synchronized code were aborted, a shared object could be left in an inconsistent state. Note that by making synchronized code ATC-deferred, this specification avoids the problems that caused Thread.stop() to be deprecated and that have made the use of Thread.destroy(), (now also deprecated in Java 1.5) prone to deadlock. If synchronized code calls an AI-method and an associated AIE is generated, then if no appropriate handler is present in the synchronized code, the AIE will propagate through the code.

Constructors and finally clauses are subject to interruption if the program indicates so. However, if a constructor is aborted, an object might be only partially initialized. If the execution of a finally clause in an AI-method is aborted, needed cleanup code might not be performed. Indeed, a finally clause in an aborted AI-method will not be executed at all if the abort occurs before its execution begins. It is the programmer's responsibility to ensure that executing these constructs either does not induce unwanted ATC latency (if ATCs are not allowed) or does not produce undesirable results (if ATCs are allowed).

A potential problem with using the exception mechanism to model ATC is that a method with a "catch-all" handler (for example a catch clause identifying Exception or even Throwable as the exception class) can inadvertently intercept an exception intended for a caller. This problem is avoided by having special semantics for catching an AIE. Even though a catch clause may catch an AIE, the exception will be propagated unless the handler invokes the happened method from AIE. Thus, if a schedulable is asynchronously interrupted while in a try block that has a handler such as

catch (Throwable e) return;

286 8.5 Rationale

the AIE will remain pending and will be thrown next time control enters or returns to an AI method.

This specification does not provide a special mechanism for terminating a real-time thread; ATC can be used to achieve this effect. This means that, by default, a realtime thread cannot be asynchronously terminated; to support asynchronous termination it needs to enter methods that are AI enabled at frequent intervals. Allowing termination as the default would have been questionable, bringing the same insecurities that are found in Thread.stop() and Thread.destroy().

Chapter 9

Time

9.1 Overview

Realtime systems must be able to handle both very short time durations and very long ones. They also needs to distinguish between relative time—a duration of time—and absolute time. Simply using a primitive integral value, such as int or long, does not provide the necessary range. Floating point primitive values, such as float and double, do not provide the necessary precision. Neither provides any type safety. This specification addresses this by requiring three time classes: High-ResolutionTime, AbsoluteTime, and RelativeTime, where HighResolutionTime is the parent class of the other two.

Instances of HighResolutionTime are not created, as the class exists to provide an implementation of the other two classes. An instance of AbsoluteTime encapsulates an absolute time. An instance of RelativeTime encapsulates a point in time that is relative to some other absolute time value.

All methods returning a time object come in both allocating and nonallocating forms. The classes

- enable describing a point in time with up to nanosecond accuracy and precision (actual accuracy and precision is dependent on the precision of the underlying system),
- enable the distinction between absolute points in time, and times relative to some starting point, and
- provide simple arithmetic operations for using them.

All time handling is based on these classes.

9.2 Definitions

The following terms and abbreviations will be used.

288 9.3 Semantics

A time object is an instance of AbsoluteTime or RelativeTime.

A *time object* is always associated with a clock. By default it is associated with the realtime clock.

The *Epoch* is the standard base time, conventionally January 1 00:00:00 GMT 1970. It is the point from which the realtime clock measures absolute time.

The *time value representation* is a compound format composed of 64 bits of millisecond timing, and 32 bits of nanoseconds within a millisecond. The millisecond constituent uses the 64 bits of a Java long while the nanosecond constituent uses the 32 bits of a Java int.

The *normalized (canonical) form* for time objects uniquely specifies the values for the millisecond and nanosecond components of a point in time, including the case of 0 milliseconds or 0 nanoseconds, and a negative time value, according to the following three rules:

- When both millisecond and nanosecond components are nonzero they have the same sign. The algebraic time value of the time object is the algebraic sum of the two components.
- The millisecond component represents the algebraic number of milliseconds in the time object, with a range of $[-2^{63}, 2^{63} 1]$
- The nanosecond component represents the algebraic number of nanoseconds within a millisecond in the time object, that is $[-10^6 + 1, 10^6 1]$.

Instances of HighResolutionTime classes always hold a normalized form of a time value. Values that cannot be normalized are not valid; for example, (MAX_LONG milliseconds, MAX_INT nanoseconds) cannot be normalized and is an illegal value.

 			_
			representations.

time in ns	millis	nanos
2000000	2	0
1999999	1	999999
1000001	1	1
1	0	1
0	0	0
-1	0	-1
-999999	0	-999999
-1000000	-1	0
-1000001	-1	-1

9.3 Semantics

This list establishes the semantics that are applicable across the classes of this section. Semantics that apply to particular classes, constructors, methods, and fields will be found in the class description and the constructor, method, and field

9 Time 289

detail sections.

• All time objects must maintain nanosecond precision and report their values in terms of millisecond and nanosecond constituents.

- Time objects must be constructed from other time objects, from millisecond/nanosecond values, from a java.util.Date or obtained as a result of invocations of methods on instances of the Clock class.
- Time objects maintain and report time values in normalized form, but the normalized form is not required for input parameter values. This allows computations individually with time constituent parts using the full *signed* range and restrictions of the underlying type.
 - Normalization is accomplished upon method invocation by methods that accept a time object represented with individual component parts, and executed as if the following hold.
 - * The nanosecond parameter value, which may be negative, is algebraically added to the scaled millisecond parameter value. The sign of the result provides the sign for any nonzero resulting component.
 - * The absolute of the result is then partitioned, giving the number of integral milliseconds for the millisecond component, while the remaining fractional part provides the number of nanoseconds for the nanosecond component.
 - * The resulting components are then represented, and reported when necessary, with the above computed sign.
 - Normalization is also performed on the result of operations by methods that perform time object addition and subtraction. Operations are executed using the appropriate arithmetic precision. If the final result of an operation can be represented in normalized form, then the operation must not throw arithmetic exceptions while producing intermediate results.
 - The results of time objects operations and the normalization of results of operations performed with millis and nanos, individually as Java long and Java int types respectively, are not always equivalent. This is due to the possibility of overflow for nanos values outside of the normalized nanosecond range, that is $[-10^6 + 1, 10^6 1]$, when performing operations as int types, while the same values could be handled with no overflow in time object operations.
 - When invoking setter methods that take as a parameter only one of the two time value components, the other component has implicitly the value of 0.
- Although logically a negative time may represent time before the Epoch or a negative time interval involved in time operations, an Exception may be thrown if a negative absolute time or a negative time interval is given as a

290 9.3 Semantics

parameter to methods. In general, the time values accepted by a method may be a subset of the full time values range, and depend on the method.

- A time object is always associated with a clock. By default it is associated with the realtime clock. Clocks are involved both in the setting as well as the usage of time objects, for example in comparisons.
- Methods are provided to facilitate the handling of time objects generically via the HighResolutionTime class. These methods allow the conversion, according to a clock, between AbsoluteTime objects and RelativeTime objects. These methods also allow the change of clock association of a time object. Note that the conversions depend on the time at which they are performed. The semantics of these operations are listed in the following table:

clock association and conversion	returned/updated object
this has clock_a and ms,ns	
this_is_absolute.absolute(clock_a)	clock_a
	ms,ns
this_is_absolute.absolute(clock_b)	clock_b
	ms,ns
this_is_absolute.absolute(null)	realtime_clock
	ms,ns
this_is_absolute.relative(clock_a)	clock_a
	<pre>clock_a.getTime().subtract(ms,ns)</pre>
this_is_absolute.relative(clock_b)	clock_b
	<pre>clock_b.getTime().subtract(ms,ns)</pre>
this_is_absolute.relative(null)	realtime_clock
	realtime_clock.getTime().subtract(ms,ns)
this_is_relative.relative(clock_a)	clock_a
	ms,ns
this_is_relative.relative(clock_b)	clock_b
	ms,ns
this_is_relative.relative(null)	realtime_clock
	ms,ns
this_is_relative.absolute(clock_a)	clock_a
	clock_a.getTime().add(ms,ns)
this_is_relative.absolute(clock_b)	clock_b
	clock_b.getTime().add(ms,ns)
this_is_relative.absolute(null)	realtime_clock
	realtime_clock.getTime().add(ms,ns)

• Time objects must implement the Comparable interface if it is available. The compareTo() method must be implemented even if the interface is not available.

9.4 Package javax.realtime

9.4.1 Classes

9.4.1.1 AbsoluteTime

An object that represents a specific point in time given by milliseconds plus nanoseconds past some point in time fixed by the clock. For the default realtime clock the fixed point is the Epoch (January 1, 1970, 00:00:00 GMT). The correctness of the Epoch as a time base depends on the realtime clock synchronization with an external world time reference. This representation was designed to be compatible with the standard Java representation of an absolute time in the java.util.Date class.

A time object in normalized form represents negative time when both components are nonzero and negative, or one is nonzero and negative and the other is zero. For add and subtract negative values behave as they do in arithmetic.

Caution: This class is explicitly unsafe for multithreading when being changed. Code that mutates instances of this class should synchronize at a higher level.

Inheritance

```
javax.realtime.HighResolutionTime
javax.realtime.AbsoluteTime
```

9.4.1.1.1 Constructors

AbsoluteTime(AbsoluteTime, Chronograph)

Make a new AbsoluteTime object from the given AbsoluteTime object.

The clock association is made with the chronograph parameter. When chronograph is null the association is made with the default realtime clock.

Available since RTSJ 2.0

Signature

public

AbsoluteTime(AbsoluteTime time, Chronograph chronograph)

throws IllegalArgumentException

Parameters

time The AbsoluteTime object which is the source for the copy. chronograph The chronograph providing the association for the newly constructed object.

Throws

IllegalArgumentException when the time parameter is null.

AbsoluteTime(Chronograph)

Equivalent to new AbsoluteTime(0,0,chronograph).

The chronograph association is made with the chronograph parameter. When chronograph is null the association is made with the default realtime clock.

Available since RTSJ 2.0

Signature

```
public
  AbsoluteTime(Chronograph chronograph)
```

Parameters

chronograph The chronograph providing the association for the newly constructed object.

AbsoluteTime

```
Equivalent to new AbsoluteTime(0,0).
```

The clock association is implicitly made with the default realtime clock.

Signature

```
public
  AbsoluteTime()
```

AbsoluteTime(AbsoluteTime)

Make a new AbsoluteTime object from the given AbsoluteTime object.

The new object will have the same clock association as the time parameter.

```
public
AbsoluteTime(AbsoluteTime time)

throws IllegalArgumentException

Parameters
time The AbsoluteTime object which is the source for the copy.

Throws
```

IllegalArgumentException when the time parameter is null.

AbsoluteTime(BaseCalendar.Date)

Equivalent to new AbsoluteTime(date.getTime(),0). The clock association is implicitly made with the default realtime clock.

```
Signature

public
AbsoluteTime(BaseCalendar.Date date)
```

throws IllegalArgumentException

Parameters

 $\it date$ The java.util.Date representation of the time past the Epoch. $\it Throws$

IllegalArgumentException when the date parameter is null.

AbsoluteTime(BaseCalendar.Date, Chronograph)

Equivalent to new AbsoluteTime(date.getTime(),0,chronograph).

Warning: While the date is used to set the milliseconds component of the new AbsoluteTime object (with nanoseconds component set to 0), the new object represents the date only when the chronograph parameter has an epoch equal to Epoch.

The clock association is made with the chronograph parameter. When chronograph is null the association is made with the default realtime clock.

Available since RTSJ 2.0

Signature

public

AbsoluteTime(BaseCalendar.Date date, Chronograph chronograph)

throws IllegalArgumentException

Parameters

date The java.util.Date representation of the time past the Epoch. chronograph The chronograph providing the association for the newly constructed object.

Throws

IllegalArgumentException when the date parameter is null.

AbsoluteTime(long, int)

Construct an AbsoluteTime object with time millisecond and nanosecond components past the realtime clock's Epoch (00:00:00 GMT on January 1, 1970) based on the parameter millis plus the parameter nanos. The construction is subject to millis and nanos parameters normalization. When, after normalization, the time object is negative, the time represented by this is time before the Epoch of its Chronograph¹. The clock association is implicitly made with the default realtime clock.

Signature

public

AbsoluteTime(long millis, int nanos)

¹Section 10.4.1.2

throws IllegalArgumentException

Parameters

millis is the desired value for the millisecond component of this. The actual value is the result of parameter normalization.

nanos is the desired value for the nanosecond component of this. The actual value is the result of parameter normalization.

Throws

IllegalArgumentException when there is an overflow in the millisecond component when normalizing.

AbsoluteTime(long, int, Chronograph)

Construct an AbsoluteTime object with time millisecond and nanosecond components past the epoch for chronograph.

The value of the AbsoluteTime instance is based on the parameter millis plus the parameter nanos. The construction is subject to millis and nanos parameters normalization. When, after normalization, the time object is negative, the time represented by this is time before this chronograph's epoch. The chronograph association is made with the chronograph parameter. When chronograph is null the association is made with the default realtime clock.

Note: The start of a chronograph's epoch is an attribute of the chronograph. It is defined as the Epoch (00:00:00 GMT on Jan 1, 1970) for the default realtime clock, but other classes of chronograph may define other epochs.

Available since RTSJ 2.0

Signature

public

AbsoluteTime(long millis, int nanos, Chronograph chronograph)

throws IllegalArgumentException

Parameters

millis The desired value for the millisecond component of this. The actual value is the result of parameter normalization.

nanos The desired value for the nanosecond component of this. The actual value is the result of parameter normalization.

chronograph The chronograph providing the association for the newly constructed object.

Throws

IllegalArgumentException when there is an overflow in the millisecond component when normalizing.

9.4.1.1.2 Methods

absolute(Chronograph)

Return a copy of this modified when necessary to have the specified chronograph association. A new object is allocated for the result. This method is the implementation of the abstract method of the HighResolutionTime base class. No conversion into AbsoluteTime is needed in this case. The chronograph association of the result is with the chronograph passed as a parameter. When chronograph is null the association is made with the default realtime clock.

Signature

public

javax.realtime.AbsoluteTime absolute(Chronograph chronograph)

Parameters

chronograph The chronograph parameter is used only as the new chronograph association with the result, since no conversion is needed.

Returns

The copy of this in a newly allocated AbsoluteTime object, associated with the chronograph parameter.

absolute(Chronograph, AbsoluteTime)

Signature

```
public
javax.realtime.AbsoluteTime absolute(Chronograph chronograph,
AbsoluteTime dest)
```

relative(Clock)

Convert the time of this to a relative time, using the given instance of Clock² to determine the current time. The calculation is the current time indicated by the given instance of Clock³ subtracted from the time given by this. When clock is null the default realtime clock is assumed. A destination object is allocated to return the result. The clock association of the result is with the clock passed as a parameter.

Deprecated since RTSJ version since version 2.0

```
Signature
```

```
public
javax.realtime.RelativeTime relative(Clock clock)
throws ArithmeticException
```

Parameters 2 4 1

clock The instance of $Clock^4$ used to convert the time of this into relative time, and the new clock association for the result.

Throws

ArithmeticException when the result does not fit in the normalized format.

Returns

The RelativeTime conversion in a newly allocated object, associated with the clock parameter.

relative(Chronograph)

Convert the time of this to a relative time, using the given instance of Chronograph⁵ to determine the current time. The calculation is the current time indicated by the given instance of Chronograph⁶ subtracted from the time given by this. When chronograph is null the default realtime clock is assumed. A destination object is allocated to return the result. The clock association of the result is with the chronograph passed as a parameter.

Available since RTSJ 2.0

Signature

```
<sup>2</sup>Section 10.4.2.1

<sup>3</sup>Section 10.4.2.1

<sup>4</sup>Section 10.4.2.1

<sup>5</sup>Section 10.4.1.2

<sup>6</sup>Section 10.4.1.2
```

```
public
   javax.realtime.RelativeTime relative(Chronograph chronograph)
Parameters
```

chronograph The instance of Chronograph⁷ used to convert the time of this into relative time, and the new clock association for the result.

Throws

ArithmeticException when the result does not fit in the normalized format.

Returns

The RelativeTime conversion in a newly allocated object, associated with the chronograph parameter.

relative(Chronograph, RelativeTime)

Convert the time of this to a relative time, using the given instance of Chronograph⁸ to determine the current time. The calculation is the current time indicated by the given instance of Chronograph⁹ subtracted from the time given by this. When chronograph is null the default realtime clock is assumed. When dest is not null, the result is placed there and returned. Otherwise, a new object is allocated for the result. The clock association of the result is with the chronograph passed as a parameter.

Signature

```
public
javax.realtime.RelativeTime relative(Chronograph chronograph,
RelativeTime dest)
```

Parameters

chronograph The instance of Chronograph¹⁰ used to convert the time of this into relative time, and the new clock association for the result.

dest When dest is not null, the result is placed there and returned. Otherwise, a new object is allocated for the result.

Throws

Arithmetic Exception when the result does not fit in the normalized format.

Returns

The RelativeTime conversion in dest when dest is not null, otherwise the result is returned in a newly allocated object. It is associated with the chronograph parameter.

⁷Section 10.4.1.2

⁸Section 10.4.1.2

⁹Section 10.4.1.2

 $^{^{10}}$ Section 10.4.1.2

add(long, int)

Create a new object representing the result of adding millis and nanos to the values from this and normalizing the result. The result will have the same clock association as this.

```
Signature
    public
    javax.realtime.AbsoluteTime add(long millis, int nanos)
    throws ArithmeticException
Parameters
     millis The number of milliseconds to be added to this.
     nanos. The number of nanoseconds to be added to this.
Throws
```

ArithmeticException when the result does not fit in the normalized format.

Returns

A new AbsoluteTime object whose time is the normalization of this plus millis and nanos.

add(long, int, AbsoluteTime)

Return an object containing the value resulting from adding millis and nanos to the values from this and normalizing the result. When dest is not null, the result is placed there and returned. Otherwise, a new object is allocated for the result. The result will have the same clock association as this, and the clock association with dest is ignored.

```
Signature
     javax.realtime.AbsoluteTime add(long millis, int nanos,
     AbsoluteTime dest)
     throws ArithmeticException
Parameters
     millis The number of milliseconds to be added to this.
     nanos The number of nanoseconds to be added to this.
     dest When dest is not null, the result is placed there and returned. Other-
     wise, a new object is allocated for the result.
Throws
```

the result of the normalization of this plus millis and nanos in dest when dest is not null, otherwise the result is returned in a newly allocated object.

add(RelativeTime)

Create a new instance of AbsoluteTime representing the result of adding time to the value of this and normalizing the result. The clock associated with this and the clock associated with the time parameter must be the same, and such association is used for the result.

Signature

```
public
javax.realtime.AbsoluteTime add(RelativeTime time)
throws ArithmeticException, IllegalArgumentException
```

Parameters 1 4 1

time The time to add to this.

Throws

IllegalArgumentException when the clock associated with this and the clock associated with the time parameter are different, or when the time parameter is null.

Arithmetic Exception when the result does not fit in the normalized format.

Returns

A new AbsoluteTime object whose time is the normalization of this plus the parameter time.

add(RelativeTime, AbsoluteTime)

Return an object containing the value resulting from adding time to the value of this and normalizing the result. When dest is not null, the result is placed there and returned. Otherwise, a new object is allocated for the result. The clock associated with this and the clock associated with the time parameter must be the same, and such association is used for the result. The clock associated with the dest parameter is ignored.

Signature public

javax.realtime.AbsoluteTime add(RelativeTime time, AbsoluteTime
dest)

throws ArithmeticException, IllegalArgumentException

Parameters

time The time to add to this.

dest When dest is not null, the result is placed there and returned. Otherwise, a new object is allocated for the result.

Throws

IllegalArgumentException when the clock associated with this and the clock associated with the time parameter are different, or when the time parameter is null.

ArithmeticException when the result does not fit in the normalized format.

Returns

the result of the normalization of this plus the RelativeTime parameter time in dest when dest is not null, otherwise the result is returned in a newly allocated object.

getDate

Convert the time given by this to a Date format. Note that Date represents time as milliseconds so the nanoseconds of this will be lost.

Signature

```
public
java.util.Date getDate()
throws UnsupportedOperationException
```

Throws

UnsupportedOperationException when the clock associated with this does not have the concept of date.

Returns

A newly allocated Date object with a value of the time past the Epoch represented by this.

set(Date)

Change the time represented by this to that given by the parameter. Note that Date represents time as milliseconds so the nanoseconds of this will be set to 0. The clock association is implicitly made with the default realtime clock.

Signature

```
public
void set(Date date)
throws IllegalArgumentException
```

Parameters 5 6 7 1

date A reference to a Date which will become the time represented by this after the completion of this method.

Throws

IllegalArgumentException when the parameter date is null.

subtract(AbsoluteTime)

Create a new instance of RelativeTime representing the result of subtracting time from the value of this and normalizing the result. The clock associated with this and the clock associated with the time parameter must be the same, and such association is used for the result.

Signature

```
public
javax.realtime.RelativeTime subtract(AbsoluteTime time)
throws IllegalArgumentException, ArithmeticException
```

Parameters

time The time to subtract from this.

Throws

IllegalArgumentException when the clock associated with this and the clock associated with the time parameter are different, or when the time parameter is null.

ArithmeticException when the result does not fit in the normalized format.

Returns

A new RelativeTime object whose time is the normalization of this minus the AbsoluteTime parameter time.

subtract(AbsoluteTime, RelativeTime)

Return an object containing the value resulting from subtracting time from the value of this and normalizing the result. When dest is not null, the result is placed there and returned. Otherwise, a new object is allocated for the result. The

clock associated with this and the clock associated with the time parameter must be the same, and such association is used for the result. The clock associated with the dest parameter is ignored.

Signature

```
public
javax.realtime.RelativeTime subtract(AbsoluteTime time,
RelativeTime dest)
throws IllegalArgumentException, ArithmeticException
```

Parameters

time The time to subtract from this.

dest When dest is not null, the result is placed there and returned. Otherwise, a new object is allocated for the result.

Throws

IllegalArgumentException when the clock associated with this and the clock associated with the time parameter are different, or when the time parameter is null.

ArithmeticException when the result does not fit in the normalized format.

Returns

the result of the normalization of this minus the AbsoluteTime parameter time in dest when dest is not null, otherwise the result is returned in a newly allocated object.

subtract(RelativeTime)

Create a new instance of AbsoluteTime representing the result of subtracting time from the value of this and normalizing the result. The clock associated with this and the clock associated with the time parameter must be the same, and such association is used for the result.

```
Signature
```

```
public
javax.realtime.AbsoluteTime subtract(RelativeTime time)
throws IllegalArgumentException, ArithmeticException
```

Parameters

time The time to subtract from this.

Throws

IllegalArgumentException when the clock associated with this and the clock associated with the time parameter are different, or when the time parameter is null.

Arithmetic Exception when the result does not fit in the normalized format.

Returns

A new AbsoluteTime object whose time is the normalization of this minus the parameter time.

subtract(RelativeTime, AbsoluteTime)

Return an object containing the value resulting from subtracting time from the value of this and normalizing the result. When dest is not null, the result is placed there and returned. Otherwise, a new object is allocated for the result. The clock associated with this and the clock associated with the time parameter must be the same, and such association is used for the result. The clock associated with the dest parameter is ignored.

Signature

public

javax.realtime.AbsoluteTime subtract(RelativeTime time,

AbsoluteTime dest)

throws IllegalArgumentException, ArithmeticException

Parameters

time The time to subtract from this.

dest When dest is not null, the result is placed there and returned. Otherwise, a new object is allocated for the result.

Throws

IllegalArgumentException when the clock associated with this and the clock associated with the time parameter are different, or when the time parameter is null.

ArithmeticException when the result does not fit in the normalized format.

Returns

the result of the normalization of this minus the RelativeTime parameter time in dest when dest is not null, otherwise the result is returned in a newly allocated object.

toString

Create a printable string of the time given by this.

2.0 (Draft 20)

The string shall be a decimal representation of the milliseconds and nanosecond values; formatted as follows "(2251 ms, 750000 ns)"

```
Signature

public
java.lang.String toString()

Returns

String object converted from the time given by this.
```

9.4.1.2 HighResolutionTime

Class HighResolutionTime is the base class for AbsoluteTime and RelativeTime. It can be used to express time with nanosecond resolution. This class is never used directly; it is abstract and has no public constructor. Instead, one of its subclasses AbsoluteTime¹¹ or RelativeTime¹² should be used. When an API is defined that has a HighResolutionTime as a parameter, it can take either an absolute or a relative time and will do something appropriate.

Caution: This class is explicitly unsafe for multithreading when being changed. Code that mutates instances of this class should synchronize at a higher level.

Inheritance

```
java.lang.Object
javax.realtime.HighResolutionTime
Interfaces
Comparable
Cloneable
```

9.4.1.2.1 Methods

waitForObject(Object, javax.realtime.HighResolutionTime<?>)

Behaves like target.wait() but with the enhancement that it waits with a precision of HighResolutionTime and returns true when the associated notify was

```
<sup>11</sup>Section 9.4.1.1

<sup>12</sup>Section 9.4.1.3
```

received, false when timeout occured. As for target.wait(), there is the possibility of spurious wakeup behavior.

The wait time may be relative or absolute, and it is controlled by the clock associated with it. When the wait time is relative, then the calling thread is blocked waiting on target for the amount of time given by time, and measured by the associated clock. When the wait time is absolute, then the calling thread is blocked waiting on target until the indicated time value is reached by the associated clock.

Available since RTSJ 2.0 updated to add a return value.

Signature

```
public static
boolean waitForObject(Object target,
javax.realtime.HighResolutionTime<?> time)
throws InterruptedException, IllegalMonitorStateException,
IllegalArgumentException, UnsupportedOperationException
```


T is the type of HighResolutionTime

target The object on which to wait. The current thread must have a lock on the object.

time The time for which to wait. When it is RelativeTime(0,0) then wait indefinitely. When it is null then wait indefinitely.

Throws

InterruptedException when this schedulable is interrupted by RealtimeThread.interrupt¹³ or AsynchronouslyInterruptedException.fire¹⁴ while it is waiting.

IllegalArgumentException when time represents a relative time less than zero.

IllegalMonitorStateException when target is not locked by the caller.

UnsupportedOperationException when the wait operation is not supported using the clock associated with time.

Returns

True when the notify was received before the timeout. False otherwise.

equals(T)

Returns true when the argument time has the same type and values as this. Equality includes clock association.

 $^{^{13}}$ Section 5.3.2.2.2

¹⁴Section 8.4.2.1.2

```
Signature

public
boolean equals(T time)

Parameters
time Value compared to this.
```

Returns

true when the parameter time is of the same type and has the same values as this.

getClock

Returns a reference to the clock associated with this.

Available since RTSJ 1.0.1

```
Signature
    public final
    javax.realtime.Clock getClock()
    throws UnsupportedOperationException
```

Throws

UnsupportedOperationException when the time is based on a Chronograph¹⁵ that is not a $Clock^{16}$.

Returns

A reference to the clock associated with this.

getChronograph

Get a reference to the Chronograph 17 associated with this.

Available since RTSJ 2.0

```
Signature
```

public final

Section 10.4.1.2
 Section 10.4.2.1
 Section 10.4.1.2

```
javax.realtime.Chronograph getChronograph() Returns A reference to the Chronograph associated with this.
```

getMilliseconds

Get the milliseconds component of this.

```
Signature

public final
long getMilliseconds()
Returns
```

The milliseconds component of the time represented by this.

getNanoseconds

Get the nanoseconds component of this.

```
Signature

public final

int getNanoseconds()

Returns
```

The nanoseconds component of the time represented by this.

set(T)

Change the value represented by this to that of the given time. The clock associated with this is set to be the clock associated with the time parameter.

Available since RTSJ 1.0.1 The description of the method in 1.0 was erroneous.

```
Signature

public
void set(T time)

18 Section 10.4.1.2
```

Parameters 1

time The new value for this.

Throws

IllegalArgumentException when the parameter time is null.

ClassCastException when the type of this and the type of the parameter time are not the same.

set(long)

Sets the millisecond component of this to the given argument, and the nanosecond component of this to 0. This method is equivalent to set(millis, 0).

```
Signature
```

```
public
void set(long millis)
```

Parameters

millis This value shall be the value of the millisecond component of this at the completion of the call.

set(long, int)

Sets the millisecond and nanosecond components of this. The setting is subject to parameter normalization. When after normalization the time is negative then the time represented by this is set to a negative value, but note that negative times are not supported everywhere. For instance, a negative relative time is an invalid value for a periodic thread's period.

Signature

```
public
void set(long millis, int nanos)
throws IllegalArgumentException
```

Parameters 1 4 1

millis The desired value for the millisecond component of this at the completion of the call. The actual value is the result of parameter normalization. nanos The desired value for the nanosecond component of this at the completion of the call. The actual value is the result of parameter normalization.

Throws

IllegalArgumentException when there is an overflow in the millisecond component while normalizing.

hashCode

Returns a hash code for this object in accordance with the general contract of **name**. Time objects that are equals (T)¹⁹ equal have the same hash code.

```
Signature

public
int hashCode()

Returns

The hashcode value for this instance.
```

clone

Return a clone of this. This method should behave effectively as when it constructed a new object with the visible values of this. The new object is created in the current allocation context.

Available since RTSJ 1.0.1

```
Signature public java.lang.Object clone()
```

compareTo(T)

Compares this HighResolutionTime with the specified HighResolutionTime time.

```
Signature

public
int compareTo(T time)

Parameters

19 Section 9.4.1.2.1
```

time Compares with the time of this.

Throws

ClassCastException when the time parameter is not of the same class as this. IllegalArgumentException when the time parameter is not associated with the same clock as this, or when the time parameter is null.

Returns

a negative integer, zero, or a positive integer as this object is less than, equal to, or greater than time.

equals(Object)

Returns true when the argument object has the same type and values as this. Equality includes clock association.

```
Signature
```

```
public
boolean equals(Object object)
```

Parameters

object Value compared to this.

Returns

true when the parameter object is of the same type and has the same values as this.

absolute(Chronograph)

Convert the time of this to an absolute time, using the given instance of Chronograph²⁰ to determine the current time when necessary. When chronograph is null the realtime clock is assumed.

A destination object is allocated to return the result. The clock association of the result is the clock passed as a parameter. See the subclass comments for more specific information.

```
Signature
```

```
public abstract
  javax.realtime.AbsoluteTime absolute(Chronograph chronograph)
Parameters
```

 $^{^{20}\}mathrm{Section}\ 10.4.1.2$

chronograph is the instance of Chronograph²¹ used to convert the time of this into absolute time, and the new chronograph association for the result.

Returns

The AbsoluteTime conversion in a newly allocated object, associated with the clock parameter.

absolute(Chronograph, AbsoluteTime)

Convert the time of this to an absolute time, using the given instance of Chronograph²² to determine the current time when necessary. When chronograph is null the realtime chronograph is assumed. When dest is not null, the result is placed there and returned. Otherwise, a new object is allocated for the result. The chronograph association of the result is the chronograph passednas a parameter. See the subclass comments for more specific information.

Signature

```
public abstract
javax.realtime.AbsoluteTime absolute(Chronograph chronograph,
AbsoluteTime dest)
```

Parameters 1

chronograph The instance of Chronograph²³ used to convert the time of this into absolute time, and the new chronograph association for the result. dest When dest is not null, the result is placed there and returned. Otherwise, a new object is allocated for the result.

Returns

The AbsoluteTime conversion in dest when dest is not null, otherwise the result is returned in a newly allocated object. It is associated with the chronograph parameter.

relative(Chronograph)

Convert the time of this to a relative time, using the given instance of Chronograph²⁴ to determine the current time when necessary. When chronograph is null the realtime chronograph is assumed. A destination object is allocated to return

²¹Section 10.4.1.2

²²Section 10.4.1.2

 $^{^{23}}$ Section 10.4.1.2

 $^{^{24}}$ Section 10.4.1.2

the result. The chronograph association of the result is the **chronograph** passed as a parameter. See the subclass comments for more specific information.

Signature

```
public abstract
   javax.realtime.RelativeTime relative(Chronograph chronograph)
Parameters
```

chronograph The instance of Chronograph²⁵ used to convert the time of this into relative time, and the new chronograph association for the result.

Returns

The RelativeTime conversion in a newly allocated object, associated with the chronograph parameter.

relative(Chronograph, RelativeTime)

Convert the time of this to a relative time, using the given instance of Chronograph²⁶ to determine the current time when necessary. When chronograph is null the realtime chronograph is assumed. When dest is not null, the result is placed there and returned. Otherwise, a new object is allocated for the result. The chronograph association of the result is the chronograph passed as a parameter. See the subclass comments for more specific information.

Signature

```
public abstract
javax.realtime.RelativeTime relative(Chronograph chronograph,
RelativeTime dest)
```

Parameters

chronograph The instance of Chronograph²⁷ used to convert the time of this into relative time, and the new chronograph association for the result.

dest When dest is not null, the result is placed there and returned. Otherwise, a new object is allocated for the result.

Returns

The RelativeTime²⁸ conversion in dest when dest is not null, otherwise the result is returned in a newly allocated object.

```
<sup>25</sup>Section 10.4.1.2
```

²⁶Section 10.4.1.2

²⁷Section 10.4.1.2

 $^{^{28}}$ Section 9.4.1.3

9.4.1.3 RelativeTime

An object that represents a time interval milliseconds/ 10^3 + nanoseconds/ 10^9 seconds long. It generally is used to represent a time relative to now.

The time interval is kept in normalized form. The range goes from $[(-2^{63})$ milliseconds + (-10^6+1) nanoseconds] to $[(2^{63}-1)$ milliseconds + (10^6-1) nanoseconds].

A negative interval relative to now represents time in the past. For add and subtract negative values behave as they do in arithmetic.

Caution: This class is explicitly unsafe for multithreading when being changed. Code that mutates instances of this class should synchronize at a higher level.

Inheritance

```
javax.realtime.HighResolutionTime
javax.realtime.RelativeTime
```

9.4.1.3.1 Constructors

RelativeTime

```
Equivalent to new RelativeTime(0,0). The clock association is implicitly made with the realtime clock.
```

```
Signature

public

RelativeTime()
```

RelativeTime(Chronograph)

Equivalent to new RelativeTime(0,0,chronograph).

The chronograph association is made with the chronograph parameter. When chronograph is null the association is made with the default realtime clock.

Available since RTSJ 2.0

Signature

```
public
```

RelativeTime(Chronograph chronograph)

Parameters

chronograph The chronograph providing the association for the newly constructed object.

RelativeTime(long, int)

Construct a RelativeTime object representing an interval based on the parameter millis plus the parameter nanos. The construction is subject to millis and nanos parameters normalization. When there is an overflow in the millisecond component when normalizing then an IllegalArgumentException will be thrown. The clock association is implicitly made with the realtime clock.

Signature

```
public
```

RelativeTime(long millis, int nanos)

throws IllegalArgumentException

Parameters

millis The desired value for the millisecond component of this. The actual value is the result of parameter normalization.

nanos The desired value for the nanosecond component of this. The actual value is the result of parameter normalization.

Throws

IllegalArgumentException when there is an overflow in the millisecond component when normalizing.

RelativeTime(long, int, Chronograph)

Construct a RelativeTime object representing an interval based on the parameter millis plus the parameter nanos. The construction is subject to millis and

nanos parameters normalization. When there is an overflow in the millisecond component when normalizing then an IllegalArgumentException will be thrown.

The chronograph association is made with the chronograph parameter. When chronograph is null the association is made with the default realtime clock.

Available since RTSJ 2.0

Signature

public

RelativeTime(long millis, int nanos, Chronograph chronograph)

throws IllegalArgumentException

Parameters 1 4 1

millis The desired value for the millisecond component of this. The actual value is the result of parameter normalization.

nanos The desired value for the nanosecond component of this. The actual value is the result of parameter normalization.

chronograph The chronograph providing the association for the newly constructed object.

Throws

IllegalArgumentException when there is an overflow in the millisecond component when normalizing.

RelativeTime(RelativeTime)

Make a new RelativeTime object from the given RelativeTime object. The new object will have the same clock association as the time parameter.

Signature

```
public
```

RelativeTime(RelativeTime time)

Parameters

time The RelativeTime object which is the source for the copy.

2.0 (Draft 20)

RelativeTime(RelativeTime, Chronograph)

Make a new RelativeTime object from the given RelativeTime object.

The clock association is made with the chronograph parameter. When chronograph is null the association is made with the realtime clock.

Available since RTSJ 2.0

```
Signature
```

public

RelativeTime(RelativeTime time, Chronograph chronograph)

throws IllegalArgumentException

Parameters

time The RelativeTime object which is the source for the copy. chronograph The chronograph providing the association for the newly constructed object.

Throws

IllegalArgumentException when the time parameter is null.

9.4.1.3.2 Methods

add(long, int)

Create a new object representing the result of adding millis and nanos to the values from this and normalizing the result. The result will have the same clock association as this. An ArithmeticException is when the result does not fit in the normalized format.

```
Signature
```

```
public
javax.realtime.RelativeTime add(long millis, int nanos)
throws ArithmeticException
```

millis The number of milliseconds to be added to this.

2.0 (Draft 20)

nanos The number of nanoseconds to be added to this.

Throws

ArithmeticException when the result does not fit in the normalized format.

Returns

A new RelativeTime object whose time is the normalization of this plus millis and nanos.

add(long, int, RelativeTime)

Return an object containing the value resulting from adding millis and nanos to the values from this and normalizing the result. When dest is not null, the result is placed there and returned. Otherwise, a new object is allocated for the result. The result will have the same clock association as this, and the clock association with dest is ignored.

Signature

```
public
```

javax.realtime.RelativeTime add(long millis, int nanos,

RelativeTime dest)

throws ArithmeticException

Parameters

millis The number of milliseconds to be added to this.

nanos The number of nanoseconds to be added to this.

dest When dest is not null, the result is placed there and returned. Otherwise, a new object is allocated for the result.

Throws

Arithmetic Exception when the result does not fit in the normalized format.

Returns

the result of the normalization of this plus millis and nanos in dest when dest is not null, otherwise the result is returned in a newly allocated object.

add(RelativeTime)

Create a new instance of RelativeTime representing the result of adding time to the value of this and normalizing the result.

The clock associated with this and the clock associated with the time parameter are expected to be the same, and such association is used for the result.

Signature

```
public
javax.realtime.RelativeTime add(RelativeTime time)
throws IllegalArgumentException, ArithmeticException
```

Parameters

time The time to add to this.

Throws

IllegalArgumentException when the clock associated with this and the clock associated with the time parameter are different, or when the time parameter is null.

ArithmeticException when the result does not fit in the normalized format.

Returns

A new RelativeTime object whose time is the normalization of this plus the parameter time.

add(RelativeTime, RelativeTime)

Return an object containing the value resulting from adding time to the value of this and normalizing the result. When dest is not null, the result is placed there and returned. Otherwise, a new object is allocated for the result.

The clock associated with this and the clock associated with the time parameter are expected to be the same, and such association is used for the result.

The clock associated with the dest parameter is ignored.

Signature

```
public
javax.realtime.RelativeTime add(RelativeTime time, RelativeTime
dest)
```

throws IllegalArgumentException, ArithmeticException

Parameters

time The time to add to this.

dest When dest is not null, the result is placed there and returned. Otherwise, a new object is allocated for the result.

Throws

IllegalArgumentException when the clock associated with this and the clock associated with the time parameter are different, or when the time parameter is null.

Arithmetic Exception when the result does not fit in the normalized format. Returns

the result of the normalization of this plus the RelativeTime parameter time in dest when dest is not null, otherwise the result is returned in a newly allocated object.

subtract(RelativeTime)

Create a new instance of RelativeTime representing the result of subtracting time from the value of this and normalizing the result.

The clock associated with this and the clock associated with the time parameter are expected to be the same, and such association is used for the result.

Signature

```
public
javax.realtime.RelativeTime subtract(RelativeTime time)
throws IllegalArgumentException, ArithmeticException
```

Parameters 1 4 1

time The time to subtract from this.

Throws

IllegalArgumentException when the clock associated with this and the clock associated with the time parameter are different, or when the time parameter is null.

Arithmetic Exception when the result does not fit in the normalized format.

Returns

A new RelativeTime object whose time is the normalization of this minus the parameter time parameter time.

subtract(RelativeTime, RelativeTime)

Return an object containing the value resulting from subtracting the value of time from the value of this and normalizing the result. When dest is not null, the result is placed there and returned. Otherwise, a new object is allocated for the result.

The clock associated with this and the clock associated with the time parameter are expected to be the same, and such association is used for the result.

The clock associated with the dest parameter is ignored.

Signature public

```
\verb|javax.realtime.RelativeTime subtract(RelativeTime time, RelativeTime dest)|
```

throws IllegalArgumentException, ArithmeticException

time The time to subtract from this.

dest When dest is not null, the result is placed there and returned. Otherwise, a new object is allocated for the result.

Throws

IllegalArgumentException when the when the clock associated with this and the clock associated with the time parameter are different, or when the time parameter is null.

ArithmeticException when the result does not fit in the normalized format.

Returns

the result of the normalization of this minus the RelativeTime parameter time in dest when dest is not null, otherwise the result is returned in a newly allocated object.

scale(int)

Change the length of this relative time by multiplying it by factor.

Available since RTSJ 2.0

```
Signature
```

```
public
javax.realtime.RelativeTime scale(int factor)
```

Parameters

factor by which to increase the time interval.

Returns

a new object with value of this scaled by factor.

scale(RelativeTime, int)

Set time to the value of this time by multiplied by factor.

Available since RTSJ 2.0

Signature

```
public javax.realtime.RelativeTime scale(RelativeTime time, int factor)

Parameters

time in which to store the results.

factor by which to increase the time interval.

Returns

time with the value of this scaled by factor
```

compareToZero

Compare this to relative time zero returning the result of the comparison. Equivalent to constantZero.compareTo(this)

Available since RTSJ 2.0

```
Signature

public

int compareToZero()
```

Returns

negative when this is less than zero, 0, when it is equal to zero and a positive when this is greater than zero.

toString

Create a printable string of the time given by this.

The string shall be a decimal representation of the milliseconds and nanosecond values; formatted as follows "(2251 ms, 750000 ns)"

```
Signature

public
 java.lang.String toString()

Returns

String object converted from the time given by this.
```

compareTo(RelativeTime)

```
Signature
    public
    int compareTo(RelativeTime time)
absolute(Chronograph)
Available since RTSJ 2.0
See Section HighResolutionTime.absolute(Chronograph)
Signature
    public
    javax.realtime.AbsoluteTime absolute(Chronograph chronograph)
absolute(Chronograph, AbsoluteTime)
Available since RTSJ 2.0
See Section HighResolutionTime.absolute(Chronograph, AbsoluteTime)
Signature
    javax.realtime.AbsoluteTime absolute(Chronograph chronograph,
    AbsoluteTime dest)
relative(Chronograph)
Available since RTSJ 2.0
See Section HighResolutionTime.relative(Chronograph)
Signature
    public
    javax.realtime.RelativeTime relative(Chronograph chronograph)
                             2.0 (Draft 20)
```

324 9.5 Rationale

relative(Chronograph, RelativeTime)

Available since RTSJ 2.0

See Section HighResolutionTime.relative(Chronograph, RelativeTime)

9.5 Rationale

Time is the essence of realtime systems, and a method of expressing absolute time with sub-millisecond precision is an absolute minimum requirement. Expressing time in terms of nanoseconds has precedent and allows the implementation to provide time-based services, such as timers, using whatever precision it is capable of while the application requirements are expressed to an arbitrary level of precision.

The standard Java java.util.Date class uses milliseconds as its basic unit in order to provide sufficient range for a wide variety of applications. realtime programming generally requires finer resolution, and nanosecond resolution is fine enough for most purposes, but even a 64 bit realtime clock based in nanoseconds would have insufficient range in some situations, so a compound format composed of 64 bits of millisecond timing, and 32 bits of nanoseconds within a millisecond, was chosen.

The expression of millisecond and nanosecond constituents is consistent with other Java interfaces.

The expression of relative times allows for time-based metaphors such as deadline-based periodic scheduling where the cost of the task is expressed as a relative time and deadlines are usually represented as times relative to the beginning of the period.

Chapter 10

Clocks and Timers

10.1 Overview

In order to reason about time, the RTSJ needs not only to be able to express times and calculate with them; but it also needs to be able to determine the current time and allow actions to be performed when a given time is reached. For this purpose, the specification defines one interface and four classes: Chronograph, Clock, Timer, PeriodicTimer, and OneShotTimer.

A chronograph is used to measure time, whereas a clock is used to both measure time and react to its passage: a clock can get the current time and it can trigger timing events. At least one instance of the abstract Clock class, which implements Chronograph, is provided by the implementation, the system *realtime clock*, and this instance is made available as a singleton. The creation and use of other clocks and chronographs are discussed later (see Section 10.3.2).

The Timer classes provide the means of executing code at a particular point in time or repeatedly at a given interval. Timer is an abstract class and consequently only its subclasses can be instantiated. The Timer class provides the interface and underlying implementation for both one-shot and periodic timers. Instances of OneShotTimer and PeriodicTimer can be created and rescheduled specifying the initial firing time either as an AbsoluteTime or as a RelativeTime, to be considered from the application of the start command. The PhasingPolicy class defines the relationship between a PeriodicTimer's start time and its first release time when the start time is in the past.

By attaching an AbstractAsyncEventHandler to a Timer, the program can cause the release of the handler at a given time or after a given interval. An instance of OneShotTimer describes an event that is to be triggered at most once (unless restarted after expiration). It may be used as the source for time-outs and watchdog timing. An instance of PeriodicTimer fires on a periodic schedule. The period for

326 10.2 Definitions

a PeriodicTimer is always specified as a RelativeTime.

10.2 Definitions

Understanding the support for clocks and timer requires some basic terms.

A *Timing Mechanism* is something capable of representing and following the progress of time, by means of time values.

A *Chronograph* is a passive timing mechanism, which can only provide the current time.

A *Clock* is an active timing mechanism, which can both provide the current time as well as cause some action when a particular time is reached. All clocks are, by definition, chronographs, but not visa versa.

A *Monotonic Timing Mechanism* is a timing mechanism whose time values always progress in one direction, and

A *Monotonically Increasing* timing mechanism is one whose time values never decrease. Monotonicity is a boolean property, while time synchronization, uniformity, and accuracy are characteristics that depend on agreed tolerances.

Time Synchronization is a relation between two timing mechanisms. Two chronographs are synchronized when the difference between their time values is less than some specified offset. Synchronization in general degrades with time, and may be lost, given a specified offset.

Accuracy is the agreement between a chronograph and the true value that it measures (e.g., absolute wall clock time).

Resolution is the minimal time value interval that can be represented by the clock model.

Precision is the smallest tick size that a particular chronograph will observe.

Uniformity, in this context, refers to the measurement of the progress of time at a consistent rate, with a tolerance on the variability. Uniformity is affected by two other factors, *jitter* and *stability*.

Jitter is caused by short-term and non-cumulative small time variation due to noise sources, such as thermal noise. More practically, jitter refers to the distribution of the differences between when events are actually fired or noticed by the software and when they should have really occurred according to time in the real-world.

Stability in this context refers to temporal stability. Lack of stability accounts for large and often cumulative variations, due to e.g. supply voltage and temperature.

Drift is this rate of this cumulative variation between two timing mechanisms.

Epoch An epoch is the date and time relative to which a computer's clock and timestamp values are determined. The epoch traditionally corresponds to 0 hours, 0 minutes, and 0 seconds (00:00:00) Coordinated Universal Time (UTC) on a specific date.

10 Clocks and Timers 327

The Epoch is January 1, 1970, 00:00:00 GMT.

Counting Time is the time accumulated by a Timer, while active, when created or rescheduled using a RelativeTime to specify the initial firing/skipping time. Counting Time is zeroed at the beginning of an activation, or when rescheduled, while active, before the initial firing/skipping of an activation.

10.3 Semantics

The semantics of chronographs, clocks and timers are not simply functional. Temporal attributes dominate their behavior; therefore, the interaction between classes is critical to the overall understanding of the API. The class descriptions as well as their constructor, method, and field documentation given later provide detailed semantics to support the overall behavior.

10.3.1 Clock Model

Clocks and chronographs are backed by a physical means of measuring time. In practice, each one is driven by an oscillator that has susceptible variation due to its environment. There is always some difference between the desired frequency and the actual frequency of the oscillator, which is a major reason of synchronization loss. The RTSJ Clock model must take this variability into account and therefore establishes several invariants and expectations that can be relied upon by RTSJ applications and in turn must be provided by RTSJ implementations.

- The *resolution* of the RTSJ Clock model is 1 nanosecond. This is the smallest unit of time that can be represented by a chronograph or timer via HighResolutionTime and its subclasses.
- The *accuracy* of RTSJ definable chronographs and clocks is outside the scope of this specification. Accuracy is heavily dependent on hardware capabilities and platform characteristics. RTSJ providers and system integrators should characterize accuracy where possible.
- The *precision* of RTSJ definable clock and chronograph (and, by proxy, the precision of the timers associated with cocks) are defined in terms of nanoseconds per observable tick, and provided to the application programmer via the various precision getters on Clock and Chronograph.
- The realtime clock will be monotonically increasing, and other clocks and chronographs should be monotonically increasing as well.
- Time values returned by a chronograph should not be assumed to be comparable to the time values from another chronograph unless the user has platform-specific knowledge that the chronographs are compatible, except under specific circumstances described below.

328 10.3 Semantics

• The system or any other realtime clock is not necessarily synchronized with the external world, and the correctness of the epoch as a time base depends on such synchronization. It is as uniform and accurate as allowed by the underlying hardware.

If two Chronograph objects are both referenced to real time and return a value from getEpochOffset(), then time values from those Chronographs can be compared by applying their respective corrections. As documented in the getEpochOffset() method, its return value represents the offset of the associated Chronograph from the realtime clock Epoch. However, the results of any such comparison must be treated with caution as the accuracy of the two Chronograph objects may be different.

10.3.2 Clocks and Timables

A Clock is the basic mechanism of measuring time and triggering events based on the passage of time. A Timer can request a signal from the clock when a given time is reached. That signal should come as closed to the actual time requested as possible. A schedulable also uses a clock to implement the realtime sleep methods. Each clock instance shall be capable of reporting the achievable resolution of timers based on that clock. Each implementation shall have a default clock that is used whenever no other clock is specified. An application can also defined additional clocks.

A Timer use a clock to measures time, and informs a TimeDispatcher when the time has elapsed (relative time) or has been reached (absolute time). The TimeDispatcher causes the release of any AsyncEventHandler associated with the Timer. In the context of a Timer, triggering is the action that is performed by a TimeDispatcher that informs the Timer that it is time to fire or skip, where skip causes the normal action of fire not to be carried out.

A Timer is *active* when it has been started and not stopped since last started and it has a time in the future at which it is expected to fire or skip, else it is *not active*.

In the context of a Timer, enabling cause the Timer to fire when it is triggered, while disabling causes the Timer to skip when it is triggered. Enabling and disabling act as a mask over firing.

The behavior of a OneShotTimer is that of a Timer that does not automatically reschedule its triggering after an initial triggering, regardless of whether it fires or skips (when *disabled* and *active* when triggered). It is specified using an initial firing time.

The behavior of a PeriodicTimer is that of a Timer that automatically reschedules after each triggering, regardless of whether the triggering results in a fire or a

10 Clocks and Timers 329

skip due to being disabled when triggered. It is specified using an initial firing time and an interval or period used for the self-rescheduling.

A Clock can also be used to regulate pauses in execution of any Schedulable through a realtime sleep method, hence timers and schedulables are classified as timables under the Timable interface.

Both OneShotTimer and PeriodTimer are given an initial firing time. A PeriodicTimer receives two clock references, within two HighResolutionTimer objects, which must be to the same clock. Thus the specification of the initial firing time and the interval or period must refer to the same clock.

A Timer is an ActiveEvent. This means that is has an associated dispatcher called TimeDispatcher. As with other active events, the application can either use the default dispatcher or create a new one with its own priority and affinity. A schedulable can also have a TimeDispatcher to manage sleeping.

Every timable, Timer or Schedulable, has one clock associated with it, on which the measurement of time will be based. Each clock maintains a list of times, called alarms, that are provided to it from timables. The clock is armed with the next alarm. When that time arrives, the clock signals the TimeDispatcher associated with the alarm to signal its timable that the time has arrived.

In the case of a timer, the dispatcher triggers the timer thereby indicating it should fire or skip. In the case of a schedulable, the dispatcher triggers the schedulable to wake up from its sleep. Figure 10.1 illustrates how a timer interacts with a application-defined clock and Figure 10.2 depicts the same for using realtime sleep in a schedulable.

In each case, an external schedulable, depicted on the right, initializes the objects involved. A TimeDispatcher and a Clock are created. These are used when creating the Timable as illustrated with step one and two respectively in both diagrams. A developer can always use a pre-existing clock or dispatcher instead of creating new ones.

Each timable acts as if it had an internal object, depicted as an instance of Alarm, to manage the relationship between a timable and its dispatcher and clock. Alarm is shown simply to illustrate this relationship. It is created, step three in both diagrams, when the timable is created and it represents the next alarm that the timable should receive: a fire for a time or a wake up call for a realtime sleep on a schedulable.

At step four, the two sequences diverge. The application start a timer with the start method, but a thread must call a realtime sleep method. In both cases, step four sets the timing in motion.

Steps (5) through (8) set up the time interval. For initiating the trigger for the first time, step (5) registers the timable with its dispatcher. Later starts or sleeps skip this step. Then the time is set in the alarm and the alarm is added to the clock.

330 10.3 Semantics




Figure 10.1: Sequence Diagram for Using a Timer

When the new alarm is the next alarm to be triggered, the clock arranges to signal that time as in step (8). When the alarm is added anywhere else in the clock queue, step (8) is delayed until the removal of an alarm causes the added alarm to reach the top of the queue.

When the alarm time is reached, step (9), the clock triggers the alarm by calling trigger on the alarm event, step (10). This in turn triggers the dispatcher, step (11). This is an asynchronous call that causes the dispatcher's thread to take over control from the clocks interrupt handler.

In step (12), the dispatcher thread removes the alarm from the clock queue, possibly causing a new alarm to become active. In the periodic thread case, the alarm is rescheduled by incrementing the time in the alarm by the interval and adding it back into the queue. In all other cases, no new alarm is set.

In step (13) any subsequent alarms that were scheduled are also kicked off. The Clock queue is a two dimensional queue that is organized by the time of the alarm and, within any given time, the priority order, highest to lowest, of the dispatchers associated with the alarms. The trigger in step (10) always goes to the alarm with the highest priority dispatcher.

Finally in step (14), the dispatcher fires the alarm which results its timable being

10 Clocks and Timers 331




Figure 10.2: Sequence Diagram for Realtime Sleep

fired or woken-up. In the case of a timer, this causes all its handlers to be released or, in the case of a schedulable, a sleep being woken up; this is marked as (15) in the diagrams.

Clocks and TimeDispatchers may be shared among many as timables as the needs of the application dictate. Different dispatchers can be used with a given clock and a dispatcher can service different clocks. The dispatcher should be chosen based on its priority and affinity, whereas a clock should be chosen based on the temporal reference, where the temporal reference may or may not be associated with clock time. For instance, one could use a clock to represent the rotation of a shaft.

10.3.3 Timers

A timer must be associated with a clock. That clock acts as if it provides an interrupt to each of its timers at the next instance of time at which the timer should do something. In other words, a clock fires its timer at a requested time. Timers can be modeled as counters, or as comparators.

332 10.3 Semantics

10.3.3.1 Counter Model

In the timer model, a timer can be viewed as if every clock interrupt increments a count up to the firing count, initially given by either an instance of RelativeTime or computed as the difference between an instance of AbsoluteTime and a semantically specified "now" (using the same clock).

- start is understood as defining "now" and start counting, stop is understood as stop counting. start after stop may be understood as start counting again from where stopped, or start from scratch after resetting the count.
- In both cases, a delay is introduced.
- An RTSJ Timer, when using the counter model, resets the count when it is restarted after being stopped.
- When a Timer is created or rescheduled using a RelativeTime to specify the initial alarm time, the RTSJ keeps the specified initial trigger time as a RelativeTime and behaves according to the counter model.

10.3.3.2 Comparator Model

In the comparator model, a Timer can be viewed as if every clock interrupt forces a comparison between an absolute time and a firing time, initially given either as an instance of AbsoluteTime or computed as the sum of an instance of RelativeTime and a semantically specified "now" (using the same clock).

- In this model, start is understood as start comparing, and possibly the first start is understood as defining "now". stop is understood as stop comparing. start after stop may be understood as start comparing again.
- In this case, no delay is introduced.
- When a Timer is created or rescheduled using an AbsoluteTime to specify the initial triggering time, the RTSJ keeps the specified initial firing time as an AbsoluteTime and uses the comparator model.

10.3.3.3 Triggering

A clock signals to the associated timable that its alarm time has been reached by triggering the dispatcher associated with the timable. This trigger causes the dispatcher to fire the associated timer. When the timer is active, it releases it handlers and is said to be fired. When the timer is inactive, nothing happens and it is said to be skipped. A stopped timer is never triggered. For this it must be running.

10.3.3.4 Behavior of Timers

There are two kinds of timers defined: OneShotTimer and PeriodicTimer. As their names imply, the first is used to mark a single time interval and the second is to mark a regularly repeating time interval.

The OneShotTimer class shall ensure that each instance is fired at most once at the time specified unless restarted after expiration.

The PeriodicTimer class shall enable the period of a timer to be expressed in terms of a RelativeTime. The initial firing of a PeriodicTimer occurs in response to the invocation of its start method, in accordance with the start time passed to its constructor. The PhasingPolicy class defines the relationship between the timer's start time and its first firing when the start time is in the past. This initial firing or skipping, may be rescheduled by a call to the reschedule method, in accordance with the time passed to that method.

Given an instance of PeriodicTimer, let S be the effective time, as an absolute time, at which the initial firing or skipping, of a PeriodicTimer is scheduled to occur:

- when the start, or reschedule, time was given as an absolute time, A, and that time is in the future when the timer is made active, then S equals A, otherwise
- when the absolute time has passed when the timer is made active, then S depends on the phasing mode of that instance of PeriodicTimer.

The firings of a PeriodicTimer are scheduled to occur according to S + nT, for n = 0, 1, 2, ... where S is as just specified, and T is the interval of the periodic timer.

For all timers, when the start or reschedule time is given as a relative time, R, S equals the time at which the *counting time*, started when the timer was made *active*, equals R. The transition to *not-active* by this timer causes the *counting time* to reset, effectively preventing this kind of timer from firing immediately, unless given a time value of 0.

When in a *not-active* state a Timer retains the parameters given at construction time or the parameters it had at de-activation time. Those are the parameters that will be used upon invocation of start while in that state, unless the parameters are explicitly changed before that, using reschedule and setInterval as appropriate.

When a Timer object is allocated in a scoped memory area, then it will increment the reference count associated with that area. Such a reference count will only be decremented when the Timer object is destroyed. (See semantics in the *Memory* chapter for details.) A Timer object will not fire before its due time.

The states of a Timer are essentially the same as for an ActiveEvent as depicted in Figure 8.3. The main difference is that the time used for the next fire may be either an absolute time or a relative time. Figure 10.3 reflects this difference in a UML state diagram.

334 10.3 Semantics




Figure 10.3: States of a Timer

10.3.3.5 Phasing

Phasing comes into play only when a periodic timer (with period T) starts after its initial time. This can happen when an absolute start time (A) is specified and the start method is called after that time. It is used to determine the effective start time S:

- S is the next multiple of A + nT, when phasing is ADJUST_FORWARD,
- S is the most recent multiple of A + nT, when phasing is ADJUST_BACKWARD,
- \bullet S is "now," when phasing is ADJUST_TO_START, and
- ullet S is undefined and an exception it thrown when phasing is STRICT_PHASING. The default phasing is ADJUST_TO_START.

10.4 Package javax.realtime

10.4.1 Interfaces

10.4.1.1 AsyncTimable

A common type for \mathtt{Timer}^1 and $\mathtt{RealtimeThread}^2$ to indicate that they can be associated with a \mathtt{Clock}^3 and be suspended waiting for time events based on that clock.

Available since RTSJ 2.0

Interfaces
Timable

10.4.1.1.1 Methods

fire

Inform the dispatcher associated with this Timable that a time event has occurred.

Available since RTSJ 2.0

```
Signature
public
void fire()
```

10.4.1.2 Chronograph

The interface for all devices that support the measurement of time with great accuracy.

¹Section 10.4.2.5

 $^{^2}$ Section 5.3.2.2

³Section 10.4.2.1

Available since RTSJ 2.0

10.4.1.2.1 Methods

getEpochOffset

Returns the relative time of the offset of the epoch of this clock from the Epoch of the realtime clock. The value returned may change over time due to clock drift.

```
Signature
```

```
public
javax.realtime.RelativeTime getEpochOffset()
```

Throws

UnsupportedOperationException when the clock does not have the concept of date.

Returns

A newly allocated RelativeTime⁴ object in the current execution context with the offset past the Epoch for this clock. The returned object is associated with this clock.

getQueryPrecision

Gets the precision of the time read, the nominal interval between ticks. It is the same as calling getQueryPrecision(RelativeTime)⁵ with null as an argument.

```
Signature
```

```
public
javax.realtime.RelativeTime getQueryPrecision()
```

Returns

a value representing the read precision.

⁴Section 9.4.1.3

⁵Section 10.4.1.2.1

getQueryPrecision(RelativeTime)

Gets the precision of the time read, the nominal interval between ticks.

```
Signature
```

```
\label{eq:public_public} \texttt{public} \\ \texttt{javax.realtime.RelativeTime} \ \ \texttt{getQueryPrecision(RelativeTime dest)} \\ Parameters
```

dest return the relative time value in dest. When dest is null, allocate a new RelativeTime⁶ instance to hold the returned value.

Returns

dest set to values representing the read precision.

getTime

Returns

Gets the current time in a newly allocated object.

Note: This method will return an absolute time value that represents the clock's notion of an absolute time. For clocks that do not measure calendar time this absolute time may not represent a wall clock time.

```
Signature
    public
    javax.realtime.AbsoluteTime getTime()
```

A newly allocated instance of AbsoluteTime⁷ in the current allocation context, representing the current time. The returned object is associated with this clock.

getTime(AbsoluteTime)

Gets the current time in an existing object. The time represented by the given AbsoluteTime⁸ is changed at some time between the invocation of the method and the return of the method. *Note:* This method will return an absolute time value that

⁶Section 9.4.1.3

⁷Section 9.4.1.1

⁸Section 9.4.1.1

represents the clock's notion of an absolute time. For clocks that do not measure calendar time this absolute time may not represent a wall clock time.

Signature

public

javax.realtime.AbsoluteTime getTime(AbsoluteTime dest)

dest The instance of AbsoluteTime⁹ object which will be updated in place. The clock association of the dest parameter is ignored. When dest is not null the returned object is associated with this clock. When dest is null, then nothing happens.

Returns

The instance of AbsoluteTime¹⁰ passed as parameter, representing the current time, associated with this clock, or null when dest was null.

10.4.1.3 Timable

A type for all classes that can use a Clock¹¹ for timing, either for sleeping or for being released at a given time.

Interfaces

Releasable

10.4.1.3.1 Methods

getDispatcher

Get the dispatcher associated with this Timable.

Available since RTSJ 2.0

Signature

⁹Section 9.4.1.1

 10 Section 9.4.1.1

 11 Section 10.4.2.1

```
public
javax.realtime.TimeDispatcher getDispatcher()
```

10.4.2 Classes

10.4.2.1 Clock

A clock marks the passing of time. It has a concept of now that can be queried through Clock.getTime(), and it can have events queued on it which will be fired when their appointed time is reached.

Note that while all Clock implementations use representations of time derived from HighResolutionTime, which expresses its time in milliseconds and nanoseconds, a particular Clock may track time that is not delimited in seconds or not related to wall clock time in any particular fashion (e.g., revolutions or event detections). In this case, the Clock's timebase should be mapped to milliseconds and nanoseconds in a manner that is computationally appropriate.

Inheritance

```
java.lang.Object
javax.realtime.Clock
Interfaces
Chronograph
```

10.4.2.1.1 Constructors

Clock

Constructor for the abstract class.

```
Signature

public

Clock()
```

10.4.2.1.2 Methods

getRealtimeClock

There is always at least one clock object available: the system realtime clock. This is the default Clock.

```
Signature

public static
 javax.realtime.Clock getRealtimeClock()

Returns

The singleton instance of the default Clock
```

getEpochOffset

Returns the relative time of the offset of the epoch of this clock from the Epoch of the realtime clock.

Available since RTSJ 1.0.1

```
Signature
    public final
    javax.realtime.RelativeTime getEpochOffset()
    throws UnsupportedOperationException
```

Throws

Unsupported Operation Exception when the clock does not have the concept of date.

Returns

A newly allocated RelativeTime¹² object with the offset past the Epoch for this clock. The returned object is associated with this clock.

getDrivePrecision

¹²Section 9.4.1.3

Gets the precision of the clock for driving events, the nominal interval between ticks that can trigger an event. It is the same as calling getDrivePrecision(RelativeTime)¹³ with null as its argument.

Available since RTSJ 2.0

```
Signature

public abstract
    javax.realtime.RelativeTime getDrivePrecision()

Returns

a value representing the drive precision.
```

getDrivePrecision(RelativeTime)

Gets the precision of the clock for driving events, the nominal interval between ticks that can trigger an event. The result may be larger than that of getQuery-Precision(RelativeTime)¹⁴.

Available since RTSJ 2.0

```
public abstract
    javax.realtime.RelativeTime getDrivePrecision(RelativeTime dest)

Parameters
    dest return the relative time value in dest. When dest is null, it allocates a new RelativeTime<sup>15</sup> instance to hold the returned value.

Returns
```

dest set to values representing the drive precision.

${\bf get Query Precision}$

Gets the precision of the time read, the nominal interval between ticks. It is the same as calling getQueryPrecision(RelativeTime)¹⁶ with null as an argument.

```
<sup>13</sup>Section 10.4.2.1.2

<sup>14</sup>Section 10.4.2.1.2

<sup>15</sup>Section 9.4.1.3

<sup>16</sup>Section 10.4.2.1.2
```

Available since RTSJ 2.0

```
Signature

public abstract
    javax.realtime.RelativeTime getQueryPrecision()

Returns

the value representing the read precision.
```

getQueryPrecision(RelativeTime)

Gets the precision of the time read, the nominal interval between ticks. The result may be smaller than that of getDrivePrecision(RelativeTime)¹⁷, when the clock is tied to some system tick for releasing events.

Available since RTSJ 2.0

```
Signature
```

```
\label{eq:public_abstract} \mbox{public abstract} \\ \mbox{javax.realtime.RelativeTime getQueryPrecision(RelativeTime dest)} \\ Parameters
```

dest return the relative time value in dest. When dest is null, allocate a new RelativeTime¹⁸ instance to hold the returned value.

Returns

dest set to values representing the read precision.

getTime

Gets the current time in a newly allocated object.

Note: This method will return an absolute time value that represents the clock's notion of an absolute time. For clocks that do not measure calendar time this absolute time may not represent a wall clock time.

Signature

 $^{^{17}}$ Section 10.4.2.1.2

 $^{^{18}}$ Section 9.4.1.3

```
public final
javax.realtime.AbsoluteTime getTime()
```

Returns

A newly allocated instance of AbsoluteTime¹⁹ representing the current time. The returned object is associated with this clock.

getTime(AbsoluteTime)

Gets the current time in an existing object. The time represented by the given AbsoluteTime²⁰ is changed at some time between the invocation of the method and the return of the method. *Note:* This method will return an absolute time value that represents the clock's notion of an absolute time. For clocks that do not measure calendar time this absolute time may not represent a wall clock time.

Available since RTSJ 1.0.1 The return value is updated from void to AbsoluteTime.

Signature

```
public abstract
javax.realtime.AbsoluteTime getTime(AbsoluteTime dest)
```

Parameters

dest The instance of AbsoluteTime²¹ object which will be updated in place. The clock association of the dest parameter is set to this. When dest is not null the returned object is associated with this clock. When dest is null, a new object is allocated.

Returns

The instance of AbsoluteTime²² passed as parameter, representing the current time, associated with this clock, or null when dest was null.

setResolution(RelativeTime)

Set the resolution of this. For some hardware clocks setting resolution is impossible and when this method is called on those clocks, then an UnsupportedOperationException is thrown.

 $^{^{19}}$ Section 9.4.1.1

²⁰Section 9.4.1.1

 $^{^{21}}$ Section 9.4.1.1

²²Section 9.4.1.1

Signature

```
public abstract
void setResolution(RelativeTime resolution)
```

Parameters

resolution The new resolution of this, when the requested value is supported by this clock. When resolution is smaller than the minimum resolution supported by this clock then it throws IllegalArgumentException. When the requested resolution is not available and it is larger than the minimum resolution, then the clock will be set to the closest resolution that the clock supports, via truncation. The value of the resolution parameter is not altered. The clock association of the resolution parameter is ignored.

Throws

IllegalArgumentException when resolution is null, or when the requested resolution is smaller than the minimum resolution supported by this clock. UnsupportedOperationException when the clock does not support setting its resolution.

triggerAlarm

Code in the abstract base Clock is called by a subclass to signal that the time of the next alarm has been reached. It will trigger a TimeDispatcher²³, which in turn will cause a fire on an associated AsyncTimable²⁴

For timers that do not drive events, this should simply do nothing.

This method should be implemented with a runtime complexity not exceeding O(1). Implementations exceeding this bound shall explicitly document the complexity their implementation. Available since RTSJ 2.0

Signature

protected final
void triggerAlarm()

setAlarm(long, int)

 $^{^{23}}$ Section 10.4.2.4

 $^{^{24}}$ Section 10.4.1.1

Implemented by subclasses to set the time for the next alarm. When there is an alarm outstanding when called, the subclass must override the old time. This should never be called from application or library code. It is intended to be called only from the <code>javax.realtime</code> package.

Available since RTSJ 2.0

```
Signature

protected abstract
void setAlarm(long milliseconds, int nanoseconds)

Parameters
milliseconds of the next alarm.
nanoseconds of the next alarm.
```

clearAlarm

Implemented by subclasses to cancel the current outstanding alarm.

Available since RTSJ 2.0

```
Signature protected abstract void clearAlarm()
```

10.4.2.2 OneShotTimer

A timed AsyncEvent²⁵ that is driven by a Clock²⁶. It will fire once, when the clock time reaches the time-out time, unless restarted after expiration. When the timer is disabled at the expiration of the indicated time, the firing is lost (skipped). After expiration, the OneShotTimer becomes not-active and disabled. When the clock time has already passed the time-out time, it will fire immediately after it is started or after it is rescheduled while active.

Semantics details are described in the Timer²⁷ pseudocode and compact graphic representation of state transitions.

```
<sup>25</sup>Section 8.4.3.4

<sup>26</sup>Section 10.4.2.1

<sup>27</sup>Section 10.4.2.5
```

Caution: This class is explicitly unsafe for multithreading when being changed. Code that mutates instances of this class should synchronize at a higher level.

Inheritance

```
java.lang.Object
    javax.realtime.AbstractAsyncEvent
    javax.realtime.AsyncEvent
    javax.realtime.Timer
    javax.realtime.OneShotTimer
```

10.4.2.2.1 Constructors

OneShotTimer(javax.realtime.HighResolutionTime<?>, Async-EventHandler, TimeDispatcher)

Create an instance of OneShotTimer²⁸, based on the Clock²⁹ associated with the time parameter, that will execute its fire method according to the given time.

Available since RTSJ 2.0

Signature

```
public
```

OneShotTimer(javax.realtime.HighResolutionTime<?> time, AsyncEventHandler handler,

throws IllegalArgumentException, UnsupportedOperationException, IllegalAssignmentError

Parameters

time The time used to determine when to fire the event. A time value of null is equivalent to a RelativeTime of 0, and in this case the Timer fires immediately upon a call to start().

handler The AsyncEventHandler³⁰ that will be released when fire is invoked. When null, no handler is associated with this Timer and nothing will happen when this event fires unless a handler is subsequently associated with the timer using the addHandler() or setHandler() method.

²⁸Section 10.4.2.2

 $^{^{29}}$ Section 10.4.2.1

 $^{^{30}}$ Section 8.4.3.5

dispatcher The TimeDispatcher³¹ to use for triggering this event.

Throws

IllegalArgumentException when time is a RelativeTime instance less than zero.

UnsupportedOperationException when the Chronograph³² associated with time is not a Clock³³.

IllegalAssignmentError when this OneShotTimer cannot hold a reference to handler.

OneShotTimer(javax.realtime.HighResolutionTime<?>, Async-EventHandler)

The equivalent of calling OneShotTimer(HighResolutionTime<?>, AsyncEvent-Handler, TimeDispatcher)³⁴ with arguments time, handler, null.

Signature

public

OneShotTimer(javax.realtime.HighResolutionTime<?> time, AsyncEventHandler han

time is the time to release its handlers.

handler is the handler to release.

10.4.2.3 PeriodicTimer

An AsyncEvent³⁵ whose fire method is executed periodically according to the given parameters. The clock associated with the Timer start time must be identical to the the clock associated with the Timer interval

The first firing is at the beginning of the first interval.

When an interval greater than 0 is given, the timer will fire periodically. When an interval of 0 is given, the PeriodicTimer will only fire once, unless restarted after

 $^{^{31}}$ Section 10.4.2.4

 $^{^{32}}$ Section 10.4.1.2

 $^{^{33}}$ Section 10.4.2.1

³⁴Section ??

 $^{^{35}}$ Section 8.4.3.4

expiration, behaving like a OneShotTimer. In all cases, when the timer is disabled when the firing time is reached, that particular firing is lost (skipped). When enabled at a later time, it will fire at its next scheduled time.

When the clock time has already passed the beginning of the first period, the PeriodicTimer will first fire according to the PhasingPolicy³⁶.

Semantics details are described in the Timer³⁷ pseudo-code and compact graphic representation of state transitions.

Caution: This class is explicitly unsafe for multithreading when being changed. Code that mutates instances of this class should synchronize at a higher level.

Inheritance

```
java.lang.Object
javax.realtime.AbstractAsyncEvent
javax.realtime.AsyncEvent
javax.realtime.Timer
javax.realtime.PeriodicTimer
```

10.4.2.3.1 Constructors

PeriodicTimer(javax.realtime.HighResolutionTime<?>, RelativeTime, AsyncEventHandler)

Create a timer that executes its fire method periodically. Equivalent to PeriodicTimer(start, interval, handler, null).

Signature

```
public
```

PeriodicTimer(javax.realtime.HighResolutionTime<?> start, RelativeTime interval, A

throws IllegalArgumentException, IllegalAssignmentError

PeriodicTimer(javax.realtime.HighResolutionTime<?>, RelativeTime, AsyncEventHandler, TimeDispatcher)

 $^{^{36}}$ Section 5.3.1.1

 $^{^{37}}$ Section 10.4.2.5

Create a timer that executes its fire method periodically.

Available since RTSJ 2.0

Signature

public

PeriodicTimer(javax.realtime.HighResolutionTime<?> start, RelativeTime interv

throws IllegalArgumentException, IllegalAssignmentError, UnsupportedOperationException

Parameters 1

start The time that specifies when the first interval begins, based on the clock associated with it. The first firing of the timer is modified according the PhasingPolicy when the timer is started. A start value of null is equivalent to a RelativeTime of 0.

interval The period of the timer. Its usage is based on the clock specified by the clock parameter. When interval is zero or null, the period is ignored and the firing behavior of the PeriodicTimer is that of a OneShotTimer³⁸.

handler The AsyncEventHandler³⁹ that will be released when fire is invoked. When null, no handler is associated with this Timer and nothing will happen when this event fires unless a handler is subsequently associated with the timer using the addHandler() or setHandler() method.

dispatcher is the dispatcher to use for triggering this event.

Throws

IllegalArgumentException when start or interval is a RelativeTime instance with a value less than zero; or the clocks associated with start and interval are not the identical.

IllegalAssignmentError when this PeriodicTimer cannot hold references to handler, clock and interval.

UnsupportedOperationException when the Chronograph⁴⁰ associated with time is not a Clock⁴¹.

10.4.2.3.2 Methods

 $^{^{38}}$ Section 10.4.2.2

³⁹Section 8.4.3.5

⁴⁰Section 10.4.1.2

 $^{^{41}}$ Section 10.4.2.1

addHandler(AsyncEventHandler)

Add a handler to the set of handlers associated with this event. It overrides the method in AbstractAsyncEvent⁴² to allow the use of handlers with PeriodicParameters⁴³, but these parameters must match the period of this timer, otherwise IllegalArgumentException is thrown.

Available since RTSJ 2.0

Signature

public
void addHandler(AsyncEventHandler handler)
throws IllegalArgumentException, IllegalAssignmentError

Parameters 1

handler a new handler to add to the list of handlers already associated with this. When handler is already associated with the event, the call has no effect.

Throws

IllegalArgumentException when handler is null or the handler has PeriodicParameters⁴⁴ with a period that does not match the period of this.
IllegalAssignmentError when this AsyncEvent cannot hold a reference to handler.

setHandler(AsyncEventHandler)

Associate a new handler with this event and remove all existing handlers. It overrides the method in AbstractAsyncEvent⁴⁵ to allow the use of handlers with PeriodicParameters⁴⁶, but these parameters must match the period of this timer, otherwise IllegalArgumentException is thrown.

Available since RTSJ 2.0

Signature

⁴²Section 8.4.3.1

 $^{^{43}}$ Section 6.4.2.5

⁴⁴Section 6.4.2.5

 $^{^{45}}$ Section 8.4.3.1

 $^{^{46}\}mathrm{Section}\ 6.4.2.5$

```
public
void setHandler(AsyncEventHandler handler)
throws IllegalArgumentException, IllegalAssignmentError
```

Parameters

handler The instance of AbstractAsyncEventHandler⁴⁷ to be associated with this. When handler is null, no handler will be associated with this, i.e., behave effectively as when setHandler(null) invokes removeHandler(AbstractAsyncEventHandler each associated handler.

Throws

IllegalArgumentException when handler has PeriodicParameters⁴⁸ with a period that does not match the period of this.

IllegalAssignmentError when this AsyncEvent cannot hold a reference to handler.

start(PhasingPolicy)

Start the timer with the specified PhasingPolicy⁴⁹.

Available since RTSJ 2.0

Signature

```
public
void start(PhasingPolicy phasingPolicy)
throws LateStartException, IllegalArgumentException
```


phasingPolicy determines what happens when the start is too late.

Throws

LateStartException when this method is called after its absolute start time and the phasingPolicy is PhasingPolicy.STRICT_PHASING⁵⁰.

IllegalArgumentException when the start time of this timer is not an absolute time, or phasingPolicy is null.

start(boolean, PhasingPolicy)

Start the timer with the specified PhasingPolicy⁵¹ and the specified disabled

⁴⁷Section 8.4.3.2 ⁴⁸Section 6.4.2.5

⁴⁹Section 5.3.1.1

 $^{^{50}}$ Section 5.3.1.1.1

 $^{^{51}}$ Section 5.3.1.1

state.

Available since RTSJ 2.0

```
Signature public
```

void start(boolean disabled, PhasingPolicy phasingPolicy)

 $throws\ Late Start Exception,\ Illegal Argument Exception$

Parameters

disabled determine the mode of start: true for enabled and false for disabled for consistency with Timer.start(boolean)⁵².

phasingPolicy determines what happens when the start is too late.

Throws

LateStartException when this method is called after its absolute start time and the phasingPolicy is PhasingPolicy.STRICT_PHASING⁵³.

IllegalArgumentException when the start time of this timer is not an absolute time, or phasingPolicy is null.

getClock

Each instance can only be associated with a single clock, which this method can obtain.

Available since RTSJ 1.0.1

```
Signature
```

```
public
javax.realtime.Clock getClock()
throws IllegalStateException
```

Throws

IllegalStateException when this has been destroyed.

Returns

the instance of ${
m Clock}^{54}$ that is associated with this.

⁵²Section 10.4.2.5.4

⁵³Section 5.3.1.1.1

 $^{^{54}}$ Section 10.4.2.1

createReleaseParameters

Create a release parameters object with new objects containing copies of the values corresponding to this timer. When the PeriodicTimer interval is greater than 0, create a PeriodicParameters⁵⁵ object with a start time and period that correspond to the next firing (or skipping) time, and interval, of this timer. When the interval is 0, create an AperiodicParameters⁵⁶ object, since in this case the timer behaves like a OneShotTimer⁵⁷.

When this timer is active, then the start time is the next firing (or skipping) time returned as an AbsoluteTime⁵⁸. Otherwise, the start time is the initial firing (or skipping) time, as set by the last call to Timer.reschedule⁵⁹, or when there was no such call, by the constructor of this timer.

```
Signature

public

javax.realtime.ReleaseParameters createReleaseParameters()

Throws

IllegalStateException when this Timer has been destroyed.
```

A new release parameters object with new objects containing copies of the values corresponding to this timer. When the interval is greater than zero, return a new instance of PeriodicParameters⁶⁰. When the interval is zero return a new instance of AperiodicParameters⁶¹.

getFireTime

Returns

Get the time at which this PeriodicTimer is next expected to fire or to skip. When the PeriodicTimer is *disabled*, the returned time is that of the skipping of the firing. When the PeriodicTimer is *not-active* it throws IllegalStateException.

```
Signature public ^{55}Section 6.4.2.5 ^{56}Section 6.4.2.2 ^{57}Section 10.4.2.2
```

⁵⁸Section 9.4.1.1 ⁵⁹Section 10.4.2.5.4

⁶⁰Section 6.4.2.5 ⁶¹Section 6.4.2.2

javax.realtime.AbsoluteTime getFireTime()
throws ArithmeticException, IllegalStateException

Throws

ArithmeticException when the result does not fit in the normalized format. IllegalStateException when this Timer has been destroyed, or when it is not-active.

Returns

The absolute time at which this is next expected to fire or to skip, in a newly allocated AbsoluteTime⁶² object. When the timer has been created or re-scheduled (see Timer.reschedule(HighResolutionTime<?>)⁶³) using an instance of RelativeTime for its time parameter then it will return the sum of the current time and the RelativeTime remaining time before the timer is expected to fire/skip. Within a periodic timer activation, the returned time is associated with the start clock before the first fire (or skip) time, and associated with the interval clock otherwise.

getFireTime(AbsoluteTime)

Get the time at which this PeriodicTimer is next expected to fire or to skip. When the PeriodicTimer is *disabled*, the returned time is that of the skipping of the firing. When the PeriodicTimer is *not-active* it throws IllegalStateException. Available since RTSJ 1.0.1

Signature

public

javax.realtime.AbsoluteTime getFireTime(AbsoluteTime dest)

Parameters 5

dest The instance of AbsoluteTime⁶⁴ which will be updated in place and returned. The clock association of the dest parameter is ignored. When dest is null a new object is allocated for the result.

Throws

ArithmeticException when the result does not fit in the normalized format. IllegalStateException when this Timer has been destroyed, or when it is not-active.

Returns

⁶²Section 9.4.1.1

 63 Section ??

⁶⁴Section 9.4.1.1

The instance of AbsoluteTime⁶⁵ passed as parameter, with time values representing the absolute time at which this is expected to fire or to skip. When the dest parameter is null the result is returned in a newly allocated object. When the timer has been created or re-scheduled (see Timer.reschedule (HighResolutionTime using an instance of RelativeTime for its time parameter then it will return the sum of the current time and the RelativeTime remaining time before the timer is expected to fire/skip. Within a periodic timer activation, the returned time is associated with the start clock before the first fire (or skip) time, and associated with the interval clock otherwise.

getInterval

Gets the interval of this Timer.

```
public javax.realtime.RelativeTime getInterval()

Throws

IllegalStateException when this Timer has been destroyed.

Returns
```

The RelativeTime instance assigned as this periodic timer's interval by the constructor or setInterval(RelativeTime)⁶⁷.

setInterval(RelativeTime)

Reset the interval value of this.

```
Signature

public

void setInterval(RelativeTime interval)
```

interval A RelativeTime⁶⁸ object which is the interval used to reset this Timer. A null interval is interpreted as RelativeTime(0,0).

```
<sup>65</sup>Section 9.4.1.1

<sup>66</sup>Section ??

<sup>67</sup>Section 10.4.2.3.2

<sup>68</sup>Section 9.4.1.3
```

The interval does not affect the first firing (or skipping) of a timer's activation. At each firing (or skipping), the next fire (or skip) time of an *active* periodic timer is established based on the interval currently in use. Resetting the interval of an *active* periodic timer only effects future fire (or skip) times after the next.

Throws

IllegalArgumentException when interval is a RelativeTime instance with a value less than zero, or the clock associated with interval is different to the clock associated with this.

IllegalAssignmentError when this PeriodicTimer cannot hold a reference to interval.

IllegalStateException when this Timer has been destroyed.

10.4.2.4 TimeDispatcher

A dispatcher for time events: Timer⁶⁹ and RealtimeThread.sleep⁷⁰. Available since RTSJ 2.0

Inheritance

javax.realtime.ActiveEventDispatcher javax.realtime.TimeDispatcher

10.4.2.4.1 Constructors

TimeDispatcher(SchedulingParameters)

Create a new dispatcher, whose dispatching thread runs with the given scheduling parameters.

Signature

public

 $^{^{69}}$ Section 10.4.2.5

 $^{^{70}}$ Section 5.3.2.2.2

TimeDispatcher(SchedulingParameters schedule)

Parameters

schedule give the parameters for scheduling this dispatcher

10.4.2.4.2 Methods

register(Timable)

Register a AsyncTimable⁷¹ with this dispatcher.

```
Signature

public

void register(Timable target)

throws RegistrationException, IllegalStateException,

IllegalArgumentException

Parameters

target to register

Throws

RegistrationException when target is already registered.

IllegalStateException when this object has been destroyed.

IllegalArgumentException when target is not stopped.
```

unregister(Timable)

Deregister a AsyncTimable⁷² from this dispatcher.

```
Signature

public

void unregister(Timable target)

throws DeregistrationException, IllegalStateException,

IllegalArgumentException

Parameters

71 Section 10.4.1.1

72 Section 10.4.1.1
```

target to deregister

Throws

DeregistrationException when target is not already registered.

IllegalStateException when this object has been destroyed.

destroy

Release all resources thereby making the dispatcher unusable.

IllegalArgumentException when target is not stopped.

```
Signature

public

void destroy()

throws IllegalStateException
```

Throws

IllegalStateException when called on a dispatcher that has one or more registered AsyncTimable⁷³ objects.

10.4.2.5 Timer

A timer is a timed event that measures time according to a given Clock⁷⁴. This class defines basic functionality available to all timers. Applications will generally use either PeriodicTimer⁷⁵ to create an event that is fired repeatedly at regular intervals, or OneShotTimer⁷⁶ for an event that just fires once at a specific time. A timer is always associated with at least one Clock⁷⁷, which provides the basic facilities of something that ticks along following some time line (realtime, CPU-time, user-time, simulation-time, etc.). All timers are created disabled and do nothing until start() is called.

10.4.2.5.1 Pseudo-Code Representation of State Transitions for Timer An implementation shall behave effectively as if it implemented the following pseudocode. Only absolute and relative time behaviors are shown as rational time has been deprecated.

```
<sup>73</sup>Section 10.4.1.1
<sup>74</sup>Section 10.4.2.1
<sup>75</sup>Section 10.4.2.3
<sup>76</sup>Section 10.4.2.2
<sup>77</sup>Section 10.4.2.1
```

NOTE: The pseudo-code does not take into account any issue of synchronization, it just shows the functionality, and the intended behavior is obtained with groups of and'ed statements interpreted as atomic. This is relevant, for example, in cases where the *firing* of an AsyncEventHandler⁷⁸ is part of the statements preceding a state transition. While the *firing* causes the release of the handler before the state transition, the execution of the handler does not take place until after the state transition has completed.

The pseudo-code is a model, it should be interpreted as running continuously, with instructions that take no time.

```
absolute construction state is {not-active, disabled, absolute}
with nextTargetTime = absoluteTime
last_rescheduled_with_AbsoluteTime = TRUE
[(if PeriodicTimer) period = interval]
relative construction state is {not-active, disabled, relative}
with nextDurationTime = relativeTime
last_rescheduled_with_AbsoluteTime = FALSE
[(if PeriodicTimer) period = interval]
{not-active, disabled, absolute}
  (if PeriodicTimer)
   set released_or_skipped_in_current_activation = FALSE
  enable -> no state change, do nothing
  disable -> no state change, do nothing
  stop -> no state change, return FALSE
  start ->
    [if last_rescheduled_with_AbsoluteTime
       [set targetTime = nextTargetTime
        [if targetTime < currentTime
         then set targetTime = currentTime
        then go to state {active, enabled, absolute}]
     else
       [set countingTime = 0]
        and set durationTime = nextDurationTime
        then go to state {active, enabled, relative}]]
  isRunning -> return FALSE
  reschedule ->
```

 $^{^{78}}$ Section 8.4.3.5

```
if using an instance of AbsoluteTime
       [reset the nextTargetTime to absoluteTime arg
        and set last_rescheduled_with_AbsoluteTime = TRUE
        and no state change
     else
       [reset the nextDurationTime to relativeTime arg
        and set last_rescheduled_with_AbsoluteTime = FALSE
        and go to state {not-active, disabled, relative}]]
  getFireTime -> throws IllegalStateException
  destroy -> go to state {destroyed}
  startDisabled ->
    [if last_rescheduled_with_AbsoluteTime
     then
       [set targetTime = nextTargetTime
        [if targetTime < currentTime
         then set targetTime = currentTime]
        then go to state {active, disabled, absolute}]
     else
       [set countingTime = 0]
        and set durationTime = nextDurationTime
        then go to state {active, disabled, relative}]]
{not-active, disabled, relative}
  [(if PeriodicTimer)
  set released_or_skipped_in_current_activation = FALSE
  enable -> no state change, do nothing
  disable -> no state change, do nothing
  stop -> no state change, return FALSE
  start ->
    [if last_rescheduled_with_AbsoluteTime
     then
       [set targetTime = nextTargetTime
        [if targetTime < currentTime
         then set targetTime = currentTime
        then go to state {active, enabled, absolute}]
     else
       [set countingTime = 0]
        and set durationTime = nextDurationTime
        then go to state {active, enabled, relative}]]
```

```
isRunning -> return FALSE
  reschedule ->
    if using an instance of AbsoluteTime
     then
       [reset the nextTargetTime to absoluteTime arg
        and set last_rescheduled_with_AbsoluteTime = TRUE
        and go to state {not-active, disabled, absolute}]
     else
       [reset the nextDurationTime to relativeTime arg
        and set last_rescheduled_with_AbsoluteTime = FALSE
        and no state change]]
  getFireTime -> throws IllegalStateException
  destroy -> go to state {destroyed}
  startDisabled ->
    if last_rescheduled_with_AbsoluteTime
       [set targetTime = nextTargetTime
        [if targetTime < currentTime
         then set targetTime = currentTime
        then go to state {active, disabled, absolute}]
     else
       [set countingTime = 0]
        and set durationTime = nextDurationTime
        then go to state {active, disabled, relative}]]
{active, enabled, absolute}
  [if currentTime >= targetTime
   then
     [if PeriodicTimer
      then
        [if period > 0
         then
            fire
             and set released_or_skipped_in_current_activation = TRUE
             and self reschedule
                 via targetTime = (targetTime + period)
             and re-enter current state
         else
            fire
             and go to state {not-active, disabled, absolute}]]
```

```
else
        [it is a OneShotTimer so
         and go to state {not-active, disabled, absolute}]]]
  enable -> no state change, do nothing
  disable -> go to state {active, disabled, absolute}
 stop -> [go to state {not-active, disabled, absolute}
            and return TRUE
  start -> throws IllegalStateException
  isRunning -> return TRUE
  reschedule ->
    if NOT released_or_skipped_in_current_activation
       if using an instance of AbsoluteTime
        then
          reset the targetTime to absoluteTime arg
           and re-enter current state
        else
           [reset the durationTime to relativeTime arg
           and set counting Time = 0
           and go to state {active, enabled, relative}]]
     else
       if using an instance of AbsoluteTime
           [reset the nextTargetTime to absoluteTime arg
           and set last_rescheduled_with_AbsoluteTime = TRUE
           and no state change
        else
           [reset the nextDurationTime to relativeTime arg
           and set last_rescheduled_with_AbsoluteTime = FALSE
           and no state change]]]
  getFireTime -> return targetTime
  destroy -> go to state {destroyed}
 startDisabled -> throws IllegalStateException
{active, enabled, relative}
  [if countingTime >= durationTime
   then
     [if PeriodicTimer
      then
```

```
[if period > 0
       then
          fire
           and set released_or_skipped_in_current_activation = TRUE
           and self reschedule
               via durationTime = (durationTime + period)
           and re-enter current state
       else
          fire
           and go to state {not-active, disabled, relative}]]
    else
      it is a OneShotTimer so
       and go to state {not-active, disabled, relative}]]]
enable -> no state change, do nothing
disable -> go to state {active, disabled, relative}
stop -> [go to state {not-active, disabled, relative}]
          and return TRUE
start -> throws IllegalStateException
isRunning -> return TRUE
reschedule ->
  [if NOT released_or_skipped_in_current_activation]
     if using an instance of AbsoluteTime
      then
         reset the targetTime to absoluteTime arg
          and go to state {active, enabled, absolute}]
      else
         reset the durationTime to relativeTime arg
          and set counting Time = 0
          and re-enter current state]]
   else
     if using an instance of AbsoluteTime
      then
         [reset the nextTargetTime to absoluteTime arg
          and set last_rescheduled_with_AbsoluteTime = TRUE
          and no state change
      else
         [reset the nextDurationTime to relativeTime arg
          and set last_rescheduled_with_AbsoluteTime = FALSE
```

```
and no state change]]]
  getFireTime ->
    return (currentTime + durationTime - countingTime)
  destroy -> go to state {destroyed}
 startDisabled -> throws IllegalStateException
{active, disabled, absolute}
  [if currentTime >= targetTime
   then
     [if PeriodicTimer
      then
        [if period > 0
         then
            skip
            and set released_or_skipped_in_current_activation = TRUE
             and self reschedule
                 via targetTime = (targetTime + period)
             and re-enter current state
         else
            skip
             and go to state {not-active, disabled, absolute}]]
      else
        [it is a OneShotTimer so
         and go to state {not-active, disabled, absolute}]]]
  enable -> go to state {active, enabled, absolute}
  disable -> no state change, do nothing
  stop -> [go to state {not-active, disabled, absolute}]
            and return TRUE
 start -> throws IllegalStateException
 isRunning -> return FALSE
  reschedule ->
    [if NOT released_or_skipped_in_current_activation]
     then
       if using an instance of AbsoluteTime
           [reset the targetTime to absoluteTime arg
            and re-enter current state
        else
           [reset the durationTime to relativeTime arg
```

```
and set counting Time = 0
            and go to state {active, disabled, relative}]]
     else
       if using an instance of AbsoluteTime
        then
           [reset the nextTargetTime to absoluteTime arg
            and set last_rescheduled_with_AbsoluteTime = TRUE
            and no state change
        else
           [reset the nextDurationTime to relativeTime arg
            and set last_rescheduled_with_AbsoluteTime = FALSE
            and no state change]]]
  getFireTime -> return targetTime
  destroy -> go to state {destroyed}
  startDisabled -> throws IllegalStateException
{active, disabled, relative}
  [if countingTime >= durationTime
   then
     [if PeriodicTimer
      then
        [if period > 0
         then
            skip
             and set released_or_skipped_in_current_activation = TRUE
             and self reschedule
                 via durationTime = (durationTime + period)
             and re-enter current state
         else
            skip
             and go to state {not-active, disabled, relative}]]
      else
        [it is a OneShotTimer so
         skip
         and go to state {not-active, disabled, relative}]]]
  enable -> go to state {active, enabled, relative}
  disable -> no state change, do nothing
  stop -> [go to state {not-active, disabled, relative}]
            and return TRUE
 start -> throws IllegalStateException
```

```
isRunning -> return FALSE
  reschedule ->
    if NOT released_or_skipped_in_current_activation
     then
       if using an instance of AbsoluteTime
        then
           reset the targetTime to absoluteTime arg
            and go to state {active, disabled, absolute}]
        else
           [reset the durationTime to relativeTime arg
            and set counting Time = 0
            and re-enter current state]]
     else
       if using an instance of AbsoluteTime
        then
           [reset the nextTargetTime to absoluteTime arg
            and set last_rescheduled_with_AbsoluteTime = TRUE
            and no state change
        else
           [reset the nextDurationTime to relativeTime arg
            and set last_rescheduled_with_AbsoluteTime = FALSE
            and no state change
  getFireTime ->
    return (currentTime + durationTime - countingTime)
  destroy -> go to state {destroyed}
  startDisabled -> throws IllegalStateException
{destroyed}
  enable — disable — stop — start — isRunning
  — reschedule — getFireTime — destroy
  — startDisabled -> throws IllegalStateException
The following two methods, without loss of generality and to
avoid clutter, have been omitted from the above Pseudo-code.
Every state but {destroyed} has:
[(if PeriodicTimer) setInterval -> reset period = interval]
[(if PeriodicTimer) getInterval -> return period]
The state {destroyed} has:
```

```
[(if PeriodicTimer) setInterval -> throws IllegalStateException]
[(if PeriodicTimer) getInterval -> throws IllegalStateException]
```

10.4.2.5.2 Compact Graphic Representation of State Transitions for Timer The following compact graphic representation, while not as detailed, complements the State Transitions for Timer pseudo-code:

(see image at doc-files/timers_state_machine.gif)

Inheritance

```
java.lang.Object
    javax.realtime.AbstractAsyncEvent
    javax.realtime.AsyncEvent
    javax.realtime.Timer

Interfaces
    AsyncTimable
    ActiveEvent
```

10.4.2.5.3 Constructors

Timer(javax.realtime.HighResolutionTime<?>, AsyncEvent-Handler, TimeDispatcher)

Create a timer that fires according to the given \mathtt{time} , based on the \mathtt{Clock}^{79} clock and is handled by the specified $\mathtt{AsyncEventHandler}^{80}$ handler.

Available since version 2.0

Signature

protected

Timer(javax.realtime.HighResolutionTime<?> time, AsyncEventHandler handler, T

⁷⁹Section 10.4.2.1 ⁸⁰Section 8.4.3.5

throws IllegalArgumentException, UnsupportedOperationException, IllegalAssignmentError

Parameters

time The time used to determine when to fire the event. A time value of null is equivalent to a RelativeTime of 0, and in this case the Timer fires immediately upon a call to start().

handler The default handler to use for this event. When null, no handler is associated with the timer and nothing will happen when this event fires unless a handler is subsequently associated with the timer using the addHandler() or setHandler() method.

dispatcher The dispatcher used to interface between this timer and its associated clock. When null, the system default dispatcher is used.

Throws

IllegalArgumentException when time is a negative RelativeTime value. UnsupportedOperationException when time has a Chronograph⁸¹ is not a clock. IllegalAssignmentError when this Timer cannot hold references to handler and clock.

10.4.2.5.4 Methods

getClock

Return the instance of Clock⁸² on which this timer is based.

```
Signature
```

```
public
javax.realtime.Clock getClock()
throws IllegalStateException
```

Throws

IllegalStateException when this Timer has been destroyed.

Returns

The instance of Clock⁸³ associated with this Timer.

⁸¹Section 10.4.1.2

 $^{^{82}}$ Section 10.4.2.1

 $^{^{83}}$ Section 10.4.2.1

getStartTime

Get the start time of this Timer. Note that the start time uses copy semantics, so changes made to the value returned by this method do not effect the start time of this Timer.

```
public
    javax.realtime.HighResolutionTime<?> getStartTime()

Returns
    a reference to the time (or start) parameter used when constructing this Timer.
    Since RTSJ 2.0
```

getEffectiveStartTime

Return a newly-created time representing the time the timer actually started, or when the timer has been rescheduled, the effective start time after the reschedule.

Available since RTSJ 2.0

```
public javax.realtime.AbsoluteTime getEffectiveStartTime() throws IllegalStateException, ArithmeticException

Throws

IllegalStateException when the timer is not active or has been destroyed.

ArithmeticException when the result does not fit in the normalized format.

Returns
the time this actually started.
```

getEffectiveStartTime(AbsoluteTime)

Update dest to represent the time the timer actually started, or when the timer has been rescheduled, the effective start time after the reschedule. When dest is null, behave as if getEffectiveStartTime()⁸⁴ had been called.

Available since RTSJ 2.0

⁸⁴Section 10.4.2.5.4

Signature

public

javax.realtime.AbsoluteTime getEffectiveStartTime(AbsoluteTime
dest)

throws IllegalStateException, ArithmeticException

Parameters

dest a place to store the time this actually started.

Throws

IllegalStateException when the timer is not active or has been destroyed.

ArithmeticException when the result does not fit in the normalized format.

Returns

The time the timer actually started, or when it has been rescheduled, the effective start time after the reschedule.

getLastReleaseTime

Get the last release time of this timer.

Available since RTSJ 2.0

Signature

```
public final
javax.realtime.AbsoluteTime getLastReleaseTime()
```

Throws

IllegalStateException when this timer has not been released since it was last started.

Returns

a reference to a newly-created AbsoluteTime⁸⁵ object representing this timer's last release time. When the timer has not been released since it was last started, throw an exception.

getLastReleaseTime(AbsoluteTime)

Signature

⁸⁵Section 9.4.1.1

```
public
javax.realtime.AbsoluteTime getLastReleaseTime(AbsoluteTime
dest)
```

Returns

When dest is null, return a reference to a newly-created AbsoluteTime⁸⁶ object representing this timer's last release time. When dest is non-null, set dest to this timer's last release time. When the timer has not been released, return null. Since RTSJ 2.0

getFireTime

Get the time at which this Timer is expected to fire. When the Timer is disabled, the returned time is that of the skipping of the firing. When the Timer is not-active it throws IllegalStateException.

Signature

```
public
javax.realtime.AbsoluteTime getFireTime()
throws IllegalStateException, ArithmeticException
```

Throws

ArithmeticException when the result does not fit in the normalized format. IllegalStateException when this Timer has been destroyed, or when it is not-active.

Returns

The absolute time at which this is expected to fire (release handlers or skip), in a newly allocated AbsoluteTime⁸⁷ object. When the timer has been created or re-scheduled (see Timer.reschedule()⁸⁸) using an instance of RelativeTime for its time parameter then it will return the sum of the current time and the RelativeTime remaining time before the timer is expected to fire/skip. The clock association of the returned time is the clock on which this timer is based.

getFireTime(AbsoluteTime)

⁸⁶Section 9.4.1.1 ⁸⁷Section 9.4.1.1

⁸⁸Section 10.4.2.5.4

Get the time at which this Timer is expected to fire. When the Timer is disabled, the returned time is that of the skipping of the firing. When the Timer is not-active it throws IllegalStateException.

Available since RTSJ 1.0.1

Signature

```
public
javax.realtime.AbsoluteTime getFireTime(AbsoluteTime dest)
throws IllegalStateException, ArithmeticException
```

Parameters

dest The instance of AbsoluteTime⁸⁹ which will be updated in place and returned. The clock association of the dest parameter is ignored. When dest is null a new object is allocated for the result.

Throws

ArithmeticException when the result does not fit in the normalized format. IllegalStateException when this Timer has been destroyed, or when it is not-active.

Returns

The instance of AbsoluteTime⁹⁰ passed as parameter, with time values representing the absolute time at which this is expected to fire (release its handlers or skip). When the dest parameter is null the result is returned in a newly allocated object. When the timer has been created or re-schedule (see Timer.reschedule()⁹¹) using an instance of RelativeTime for its time parameter then it will return the sum of the current time and the RelativeTime remaining time before the timer is expected to fire. The clock association of the returned time is the clock on which this timer is based.

getDispatcher

```
Signature
```

```
public
javax.realtime.TimeDispatcher getDispatcher()
```

⁸⁹Section 9.4.1.1

 $^{^{90}}$ Section 9.4.1.1

⁹¹Section 10.4.2.5.4

isActive

Determine the activation state of this happening, i.e., it has been started.

```
Signature

public
boolean isActive()

Returns

true when active, false otherwise.
```

isRunning

Determines if this is *active* and is *enabled* such that when the given time occurs it will fire the event. Given the Timer current state it answer the question "Is firing expected?".

```
public
    public
    boolean isRunning()
    throws IllegalStateException
Throws
    IllegalStateException when this Timer has been destroyed.
Returns
```

true when the timer is active and enabled; owherwise false, when the timer has either not been started, it has been started but it is disabled, or it has been started and is now stopped.

handledBy(AsyncEventHandler)

Available since RTSJ 1.0.1

```
Signature

public

boolean handledBy(AsyncEventHandler handler)

throws IllegalStateException

Parameters
```

handler to add to the Timer

Throws

IllegalStateException when this Timer has been destroyed.

Returns

true when handler is associated with this, otherwise false.

createReleaseParameters

Create a ReleaseParameters⁹² object appropriate to the timing characteristics of this event. The default is the most pessimistic: AperiodicParameters⁹³. This is typically called by code that is setting up a handler for this event that will fill in the parts of the release parameters for which it has values, e.g. cost.

```
Signature

public
javax.realtime.ReleaseParameters createReleaseParameters()
throws IllegalStateException

Throws
IllegalStateException when this Timer has been destroyed.

Returns
A newly created ReleaseParameters 94 object.
```

addHandler(AsyncEventHandler)

Add a handler to release upon fire.

Available since RTSJ 1.0.1

```
public
void addHandler(AsyncEventHandler handler)
throws IllegalStateException, IllegalAssignmentError

Parameters
handler to add to the Timer

Throws

92Section 6.4.2.9
93Section 6.4.2.2
94Section 6.4.2.9
```

IllegalStateException when this Timer has been destroyed. IllegalAssignmentError @inheritDoc

setHandler(AsyncEventHandler)

Set a handler and remove all others.

Available since RTSJ 1.0.1

```
Signature

public

void setHandler(AsyncEventHandler handler)

throws IllegalStateException, IllegalAssignmentError

Parameters

handler to add to the Timer

Throws

IllegalStateException when this Timer has been destroyed.

IllegalAssignmentError @inheritDoc
```

removeHandler(AsyncEventHandler)

Remove the given handler.

Available since RTSJ 1.0.1

```
public
void removeHandler(AsyncEventHandler handler)
throws IllegalStateException

Parameters
handler to add to the Timer

Throws
IllegalStateException when this Timer has been destroyed.
```

enable

Re-enable this timer after it has been *disabled*. (See Timer.disable()⁹⁵.) When the Timer is already *enabled*, this method does nothing. When the Timer is *notactive*, this method does nothing.

```
Signature

public

void enable()

throws IllegalStateException

Throws

IllegalStateException when this Timer has been destroyed.
```

disable

Disable this timer, preventing it from firing. It may subsequently be re-enabled. When the timer is disabled when its fire time occurs then it will not release its handlers. However, a disabled timer created using an instance of RelativeTime for its time parameter continues to count while it is disabled, and no changes take place in a disabled timer created using an instance of AbsoluteTime, in both cases the potential firing is simply masked, or skipped. When the timer is subsequently re-enabled before its fire time and it is enabled when its fire time occurs, then it will fire. It is important to note that this method does not delay the time before a possible firing. For example, when the timer is set to fire at time 42 and the disable() is called at time 30 and enable() is called at time 40 the firing will occur at time 42 (not time 52). These semantics imply also that firings are not queued. Using the above example, when enable was called at time 43 no firing will occur, since at time 42 this was disabled. When the Timer is already disabled, whether it is active or inactive, this method does nothing.

```
Signature

public

void disable()

throws IllegalStateException

Throws

IllegalStateException when this Timer has been destroyed.
```

start

⁹⁵Section 10.4.2.5.4

Start this timer. A timer starts measuring time from when it is started; this method makes the timer *active* and *enabled*.

```
Signature
    public
    void start()
    throws IllegalStateException
```

Throws

IllegalStateException when this Timer has been *destroyed*, or when this timer is already *active*.

start(boolean)

Start this timer. A timer starts measuring time from when it is started. When disabled is true start the timer making it *active* in a *disabled* state. When disabled is false this method behaves like the start() method.

Available since RTSJ 1.0.1

```
Signature

public

void start(boolean disabled)

throws IllegalStateException
```

Parameters

disabled When true, the timer will be active but disabled after it is started. When false this method behaves like the start() method.

Throws

IllegalStateException when this Timer has been *destroyed*, or when this timer is *active*.

stop

Stops a timer when it is active and changes its state to inactive and disabled.

```
Signature
public
boolean stop()
```

throws IllegalStateException

Throws

IllegalStateException when this Timer has been destroyed.

Returns

true when this was enabled and false otherwise.

reschedule(javax.realtime.HighResolutionTime<?>)

Change the scheduled time for this event. This method can take either an AbsoluteTime or a RelativeTime for its argument, and the Timer will behave as if created using that type for its time parameter. The rescheduling will take place between the invocation and the return of the method.

NOTE: While the scheduled time is changed as described above, the rescheduling itself is applied only on the first firing (or on the first skipping when *disabled*) of a timer's activation. When reschedule is invoked after the current activation timer's firing, then the rescheduled time will be effective only upon the next start or startDisabled command (which may need to be preceded by a stop command).

When reschedule is invoked with a RelativeTime time on an *active* timer before its first firing/skipping, then the rescheduled firing/skipping time is relative to the time of invocation.

Signature

```
public
void reschedule(javax.realtime.HighResolutionTime<?> time)
throws IllegalStateException, IllegalArgumentException
```

Parameters

time The time to reschedule for this event firing. When time is null, the previous time is still the time used for the Timer firing. The clock associated with the parameter time is always ignored.

Throws

IllegalArgumentException when time is a negative RelativeTime value. IllegalStateException when this Timer has been destroyed.

fire

Should not be called except for emulation. The fire method is reserved for the use of the timer. It releases all handlers when this is enabled and does nothing, otherwise.

10 Clocks and Timers 379

```
Signature
public
void fire()
```

10.5 Rationale

Clocks differ because of monotonicity, synchronization, jitter, stability, accuracy, precision, and resolution. There are many possible subclasses of clocks: realtime clocks, user time clocks, simulation time clocks, wall clocks.

The idea of using multiple clocks may at first seem unusual, but it enables the accommodation of difference kinds of clocks and as a possible resource allocation strategy. Consider a realtime system where the natural events of the system have different tolerances for jitter. Assume the system functions properly if event A is triggered within plus or minus 100 seconds of the actual time it should occur but event B must be triggered within 100 microseconds of its actual time. Further assume, without loss of generality, that events A and B are periodic. An application could then create two instances of PeriodicTimer based on two clocks. The timer for event B should be based on a Clock which checks its queue at least every 100 microseconds but the timer for event A could be based on a Clock that checked its queue only every 100 seconds. This use of two clocks reduces the queue size of the accurate clock and thus queue management overhead is reduced.

The importance of the use of one-shot timers for time-out behavior and the vagaries in the execution of code prior to starting the timer for short time-outs dictate that the triggering of the timer should be guaranteed. The problem is exacerbated for periodic timers where the importance of the periodic triggering outweighs the precision of the start time. In such cases, it is also convenient to allow, for example, a relative time of zero to be used as the start time.

Clock resolution is a complicated topic, and clock implementations may have differing precissions for different purposes. For example, a clock for interacting with humans need much less precission than for controlling the openning and closing of values on an internal combustion engine. In this case, their relationship to wall clock time may vary as well.

The precision of time returned by a hardware clock device when queried may be greater than the precision at which that device can supply interrupts. (Consider, for example, a high precision off-chip realtime clock device connected via a shared serial bus.) A different device may provide pulse-per-second interrupts of very high precision, but be unable to interrupt on any other interval. The RTSJ Clock class provides two representation of precision: getDrivePrecission() and

380 10.5 Rationale

getQueryPrecission inherited from Chronograph. Clocks should behave as if their tick (setAlarm()) precision is the same as returned by getResolution().

Chapter 11

Alternative Memory Areas

11.1 Overview

Conventional Java uses a single heap for storing all objects. The thread stacks hold only primative objects and references to objects. This is fine for desktop and server systems, where there are no realtime, locality, or isolation requirements. For most realtime systems, a single heap will a deterministic garbage collector is usually also sufficient. For other situations, this specification defines classes directly related to memory and memory management. These classes provide a more generalized means of memory management than available in a conventional Java VM.

In conventional Java, all of the memory needed for the allocation of an object is taken from a garbage-collected heap. The RTSJ generalizes the concept of a heap to that of a memory area. A memory area consists of two components: a Java object that manages the memory area and the backing memory, which is the actual region of memory from which objects are allocated. Every thread and schedulable has a current allocation context. This context is the memory area which is managing the backing memory that will be used when the thread/schedulable requests memory allocation using the Java "new" operator.

There are three types of memory area, distinguished by object lifetime semantics, defined by the RTSJ.

- Heap memory—the Java heap. Unreferenced objects are collected by a garbage collector. Individual schedulables can specify their rate of allocation of objects on the heap.
- Immortal memory—an area defined by the JVM in which allocated objects might never be collected. Access to the memory area must be independent of garbage collection activity. Individual schedulables can specify the maximum amount of memory they need in immortal memory.
- Scoped memory—multiple areas that can be created by the application; ob-

382 *11.1 Overview*

jects are collected in scoped memory when there are no schedulables currently active in that area. These allow objects with well-defined lifetimes to be created and efficiently collected in an easily identified group.

Given that objects can now be created in multiple memory areas, it is necessary to ensure that an object cannot reference another object that might be collected at an earlier time. For example, an object in immortal memory (that is never collected) must not be allowed to reference an object in scoped memory. This is because the scoped memory object will be collected when there is no schedulable active in its associated backing memory, rendering the immortal object's reference to the scoped memory object invalid. For this reason, the RTSJ defines some memory assignment rules that are checked by the JVM on every object assignment. If the program violates the assignment rules, an exception is thrown.

11.1.1 Physical Memory

In embedded systems it is often the case that multiple directly addressable memory types are available to the application. The JVM implementer may require the VM to be portable between systems within the same processor family. The VM, therefore, may have detailed knowledge of the underlying memory architecture. It is primarily concerned with the standard Random-Access Memory (RAM) provided to it by the host operating system. The RTSJ, therefore, provides a framework with which the embedded systems integrator can define memory characteristics and specify ranges of physical addresses that support those memory characteristics. Physical memory regions can be allocated as either immortal or scoped memory areas, as follows.

- Physical immortal memory—multiple immortal memory areas that can be created by the application such that their associated backing memory areas have specified physical and virtual memory characteristics. For example, the application could specify that the physical characteristics of the backing store should be Static RAM (SRAM) and that it should be mapped by the JVM into virtual memory that is never paged out to disk.
- Physical scoped memory—multiple scoped memory areas that can be created by the application such that their associated backing store has specified physical and virtual memory characteristics.

This physical memory model is based on two constraints.

• Java objects can only be allocated in a memory area if the physical backing memory supports the Java Memory Model (JMM) without the JVM having to perform any operation additional to those that it performs when accessing the main RAM for the host machine. No extra compiler or JVM interactions shall be required. Hence memory regions (such as EEPROM) that potentially require special hardware instructions to perform write operations cannot be used as the backing store for physical memory areas. Similarly, non-volatile

memory cannot be used, as object lifetimes in such an area may be longer than the lifetime of the VM. Although memory having such characteristics incompatible with the JMM are prohibited from being used as backing stores for object allocation, they can contain objects of primitive Java types and be accessed via the RTSJ Raw Memory facilities (see Section 12.3.1).

• Any API must delegate detailed knowledge of the memory architecture to the programmer/integrator of the specific embedded system to be implemented. The model assumes that the programmer is aware of the memory map, either through some native operating system interface¹ or from some property file read at program initialization time.

The RTSJ defines a physical memory manager, which maintains a mapping between physical memory characteristics and the associated physical addresses of memory that support those characteristics. The physical memory manager has no knowledge of the meaning of the physical characteristics. It only provides a look-up service and keeps track of which physical memory has been allocated to a physical memory area's backing store by the application. The physical memory manager does, however, have detailed knowledge of the types of virtual memory it can support. It advertises this knowledge to the application. For example, it knows if the VM can lock memory pages into memory to ensure that they are never swapped out to disk. The application can then request that the physical memory manager create an association between physical memory with certain characteristics and a virtual memory type (for example, SRAM that is permanently resident in memory). The physical memory manager creates a filter to represent this association. These filters can then be used in the constructors to physical immortal and scoped memory areas to ensure that the backing memory has the required properties.

11.1.2 Stacked Memory

Systems that must both maintain predictable memory performance over a long period of time and allocate and release memory at runtime must be able to characterize and control both internal and external fragmentation. The RTSJ provides scoped memory for safe, application-driven allocation and release of memory, but the bare scoped memory interface (e.g., LTMemory) leaves sufficient ambiguity in specification that using it to create and release scopes at runtime in a fragmentation-free manner may depend on the VM platform. The StackedMemory class provides a safe interface for creating and releasing scopes with a set of rules under which the VM must guarantee fragmentation-free behavior with predictable memory overhead. These

¹For example, the Advanced Configuration and Power Interface (ACPI) specification is an open standard for device configuration and power management by the operating system. The ACPI defines platform-independent interfaces for hardware discovery, configuration, power management and monitoring. See http://www.acpi.info/

384 *11.1 Overview*

guarantees are provided by constraining the order in which an application may enter StackedMemory areas, as well as the manner in which they may be arranged on the scope stack. These constraints are to be enforced by the implementation.

A StackedMemory area represents both a backing memory providing Scoped-Memory semantics and a backing memory container from which the backing memory is drawn. The backing memory container may be further subdivided into additional backing memories and backing memory containers. Such divisions behave as if new containers are allocated contiguously from the bottom of the container, while new backing memories are allocated contiguously from the top, with containers and backing memories meeting when the container is completely occupied.

StackedMemory backing memory containers are explicitly created and sized, and have well-defined lifetimes similar to objects in a ScopedMemory area. A Stacked-Memory object can be created as either a host, which has its own backing memory container, or a guest, which draws its backing memory directly from its parent's backing memory container. When a StackedMemory object is created in an allocation context other than StackedMemory, it is necessarily a host and we call it a root StackedMemory. In this case, its backing memory container is drawn from a notional global backing memory container. Applications should assume that a root StackedMemory's object is immortal, and implementations need not release it even if it is finalized. When a StackedMemory object is created in another StackedMemory's allocation context, it may be created as either a host or guest, as illustrated in Figure 11.1. When it is created as a host, its backing memory container is drawn from its parent area's container, and its backing memory is created in the newly-divided container. When it is created as a guest, its backing memory is created in its parent's backing memory container.

Object lifetimes for objects allocated in StackedMemory backing memories are the same as those in ScopedMemory allocation areas. When a StackedMemory object itself is finalized, its backing memory is returned to the container from which it was drawn, and in the case of host StackedMemory areas, the associated backing memory container is also returned to the parent's container. As previously mentioned, root StackedMemory backing memory containers are effectively immortal. Additionally, the backing memory of a StackedMemory can be resized under certain conditions. These semantics allow the memory represented by a root StackedMemory backing memory container to be partitioned and re-partitioned as the application requires, without danger of fragmentation and without requiring memory allocation external to the container to track the partitioning.

In order to preserve the fragmentation-free nature of this contract, certain rules are enforced, and certain additional rules must be observed by the application. The rules that are enforced by the StackedMemory infrastructure are:

• A non-root StackedMemory area can only be entered from the same allocation




Figure 11.1: Manipulation of StackedMemory Areas

context in which it was created.

- A StackedMemory area may have at most one direct child in the scope stack that is a guest StackedMemory area.
- A StackedMemory object cannot be created from another StackedMemory allocation context unless it is allocated from that area's backing memory.
- A StackedMemory's backing memory cannot be resized if there are non-finalized guest StackedMemory backing memories placed after it in the same backing memory container.

The additional rules that are not enforced by the infrastructure are not enforced because it may be desirable for an application to temporarily violate them (e.g., when joining child threads in completion order, rather than creation order). They nevertheless must be observed at critical times in order to preserve fragmentation-free allocation. They are that, when a new StackedMemory is created as either a host or guest in a particular container, one of the following conditions must be met:

- The new StackedMemory area is a host, and there are existing non-finalized host StackedMemory descendants in the parent backing memory, but all such descendants were *created after* all non-finalized host descendants. (That is, effectively last-in first-out finalization.)
- The new StackedMemory area is a host, and there are no existing non-finalized host StackedMemory descendants in the parent backing memory.
- The new StackedMemory area is a guest.

Note that the first bullet point effectively can be violated only if the parent has both host and guest children.

Figure 11.1 graphically depicts the behavior of StackedMemory backing memory containers and backing memories for a root StackedMemory as well as one host and one guest child StackedMemory under that root. A code fragment that could create

the stack topology in Figure 11.1 is as follows. Assume that this fragment executes in an allocation context other than a StackedMemory, and that zero overhead is required for memory area creation. (Implementations may require a constant amount of backing memory overhead for each StackedMemory area created in the store.)

```
// Create a StackedMemory with a 10 kB backing memory container and 2 kB backing memory
 2 rootArea = new StackedMemory(2048, 10240); // (a)
 3 rootArea.enter(new Runnable() {
       public void run() {
 4
 5
           // Create a host area with a 6 kB backing memory container and 2 kB backing memory
 6
           hostArea = new StackedMemory(2048, 6144); // (b)
 7
           // Create a guest area with a 2 kB backing memory
 8
           guestArea = new StackedMemory(1536); // (c)
9
       }
10 });
```

Commented points (a), (b), and (c) correspond to their respective subfigures in Figure 11.1. At point (a), a root StackedMemory has been created with its 10 kB backing memory container drawn from the notional global container. It contains a 2 kB backing memory, which is then entered. With that backing memory as the current allocation context, a new host StackedMemory is created at (b), reserving 6 kB of the root StackedMemory's backing memory container for its own use and creating a second 2 kB backing memory within that reservation. A new guest StackedMemory is then created at (c) in the root area (without entering the host child), occupying 1.5 kB of the remaining free 2 kB of the container in the root area. At this point, the root area's backing memory container is almost entirely occupied, with one 2 kB backing memory, one 1.5 kB backing memory, and a 6 kB host area backing memory container reservation, and 512 B of free backing memory container in between. The host StackedMemory created at (b) has 4 kB of its backing memory container remaining unoccupied in its reservation, which could be allocated to additional host or guest StackedMemory areas beneath it in the stack.

11.1.3 **Summary**

In summary, the classes and interfaces defined in this chapter enable

- the definition of regions of memory outside of the conventional Java heap;
- the definition of regions of scoped memory, that is, memory regions with a limited lifetime:
- the definition of regions of memory containing objects whose lifetime matches that of the application;
- the definition of regions of memory mapped to specific physical addresses with specific virtual memory characteristics;

- the specification of maximum memory area consumption and maximum allocation rates for individual schedulables;
- the programmer to query information characterizing the behavior of the garbage collection algorithm, and to some limited ability, alter the behavior of that algorithm.

11.2 Definitions

The following terms are used throughout this chapter.

Allocation Context—the place where a given task allocated new object. In conventional Java, this is the Java heap. This is just one type of MemoryArea, the base class representing all allocation contexts in the RTSJ.

Current allocation context—the memory area which will be used when object allocation is requested.

Backing store or backing memory—the area of memory that is managed by a MemoryArea and is logically separate from the Java heap.

Firable asynchronous event handler—An AbstractAsyncEventHandler is firable whenever there is an agent that can release it. This includes cases when the AbstractAsyncEventHandler is

- a miss handler, or overrun handler of a RealtimeThread instance that has been started but not yet terminated;
- a handler associated with an AsyncEvent that can be fired;
- a miss handler or overrun handler for an instance of AbstractAsync-EventHandler.

It excludes the final stage of scoped memory wrap-up.

Execution context—the memory area upon which execution is dependent. This includes the area a Schedulable or ActiveEvent is allocated. In order to prevent references from becoming invalid, the memory of an execution context may not be reclaimed. A memory area containing one of the following is such a context:

- Thread instances that have been started and have not terminated (including the RealtimeThread instances contained by ActiveEventDispatcher instances),
- AbstractAsyncEvent instances that have a least one associated Abstract-AsyncEventHandler,
- ActiveEvent instances that are active,
- Firable AbstractAsyncEventHandler instance, and
- active threads of control which have the memory area enter on their stack.

Default initial memory area—The initial memory area for a schedulable is default when it is the memory area where the schedulable was created.

388 11.3 Semantics

Portal—A reference inside a ScopedMemory instance settable on that instance which may reference an object in that area. A portal can be used to pass information between instances of Schedulable executing in that areas.

Scope stack—A stack of the memory areas the current Schedulable instance has entered in order of entry. in-use memory areas.

11.3 Semantics

The following list establishes the semantics that are applicable across the classes of this section. Semantics that apply to particular classes, constructors, methods, and fields will be found in the class description and the constructor, method, and field detail sections.

11.3.1 Allocation time

- 1. Some MemoryArea classes are required to have linear (in object size) allocation time. The linear time attribute requires that, ignoring performance variations due to hardware caches or similar optimizations and ignoring execution time of any static initializers, the execution time of new must be bounded by a polynomial, f(n), where n is the size of the object and for all n > 0, $f(n) \le Cn$ for some constant C.
- 2. Execution time of object constructors, and time spent in class loading and static initialization are not governed by bounds on object allocation in this specification, but setting default initial values for fields in the instance (as specified in *The Java Virtual Machine Specification*, Second Edition, section 2.5.1, "Each class variable, instance variable, and array component is initialized with a default value when it is created.") is considered part of object allocation and included in the time bound.

11.3.2 The allocation context

- 3. A memory area is represented by an instance of a subclass of the MemoryArea class. When a memory area, m, is entered by calling m.enter (or another method from the family of enter-like methods defined in MemoryArea or its subclasses), m becomes the allocation context of the current schedulable object. When control returns from the enter method, the allocation context is restored to the value it had immediately before enter was called.
- 4. When a memory area, m, is entered by calling m's executeInArea method, m becomes the current allocation context of the current schedulable. When

- control returns from the executeInArea method, the allocation context is restored to the value it had before executeInArea was called.
- 5. The initial allocation context for a schedulable is the memory area that was designated the *initial memory area* when the schedulable was constructed. This initial allocation context becomes the current allocation context for that schedulable when the schedulable object first becomes eligible for execution. For instances of AbstractAsyncEventHandler, the initial allocation context is the same on each release; for realtime threads, in releases subsequent to the first, the allocation context is the same as it was when the realtime thread became *blocked-for-release-event*.
- 6. All object allocation through the new keyword will use the current allocation context, but note that allocation can be performed in a specific memory area using the newInstance and newArray methods.
- 7. Instances of schedulables behave as if they stored their memory area context in a structure called the *scope stack*. This structure is manipulated by the instantiation of a schedulables, and the following methods from MemoryArea and its subclasses: all the enter and joinAndEnter methods, executeInArea, and both newInstance methods. See the semantics in Maintaining the Scope Stack for details.
- 8. The scope stack is accessible through a set of static methods on Realtime—Thread. These methods allow outer allocation contexts to be accessed by their index number. Memory areas on a scope stack may be referred to as *inner* or *outer* relative to other entries in that scope stack. An "outer scope" is further from the current allocation context on the current scope stack and has a lower index.
- 9. The executeInArea, newInstance and newArray methods, when invoked on an instance of ScopedMemory require that instance to be an outer allocation context on the current schedulable object's current scope stack.
- 10. An instance of ScopedMemory is said to be *in use* if it has a non-zero reference count as defined by semantic 17 below.

11.3.3 The Parent Scope

- 11. Instances of ScopedMemory have special semantics including definition of parent. If a ScopedMemory object is neither in use nor the initial memory area for a schedulable, it has no parent scope.
 - When a ScopedMemory object becomes in use, its parent is the nearest ScopedMemory object outside it on the current scope stack. If there is no outside ScopedMemory object in the current scope stack, the parent is the *primordial scope* which is not actually a memory area, but only a marker that constrains the parentage of ScopedMemory objects.

390 11.3 Semantics

• At construction of a schedulable, if the initial memory area has no parent, the initial memory area is assigned the parent it will have when the schedulable is in execution. This rule determines the initial memory area's parent until the schedulable object is de-allocated or, in the case of a RealtimeThread, it completes execution.

12. Instances of ScopedMemory must satisfy the *single parent rule* which requires that each scoped memory has a unique parent as defined in semantic 11.

11.3.4 Memory areas and schedulables

- 13. Pushing a scoped memory onto a scope stack is always subject to the single parent rule.
- 14. Each schedulable has an initial memory area which is that object's initial allocation context. The default initial memory area is the current allocation context in effect during execution of the schedulable's constructor, but schedulables may supply constructors that override the default.
- 15. A Java thread cannot have a scope stack; consequently it can only be created and execute within heap or immortal memory. The thread starts execution with its allocation context set to the memory area containing the Thread object. An attempt to create a Java thread in a scoped memory area throws IllegalAssignmentError.
- 16. A Java thread may use executeInArea, and the newInstance and newArray methods from the ImmortalMemory and HeapMemory classes. These methods allow it to execute with an immortal current allocation context, but semantic 15 applies even during execution of these methods.

11.3.5 Scoped memory reference counting

- 17. Each instance of the class **ScopedMemory** or its subclasses must maintain a reference count which is greater than zero if and only if either:
 - the scoped memory area is the current allocation context or an outer allocation context for one or more *execution contexts*; or else
 - the scoped memory area contains the *fireable* AsyncEventHandler that was created with the pinInitialmemoryArea flag set to True.
- 18. Each instance of the PinnableMemory class must support a pinned count. This count is incremented for each call of the pin method and decremented for each call of the unpin method. The count is always greater than or equal to zero (that is, calling the unpin method has no effect if the count equals zero).
- 19. When the reference count for an instance of the class ScopedMemory is ready to be decremented from one to zero and the pinned count (if present) is equal to zero, all unfinalized objects within that area are considered ready for fi-

nalization. If after the finalizers for all such unfinalized objects in the scoped memory area run to completion, the reference count for the memory area is still ready to be decremented to zero and the pinned count is still equal to zero, any newly created unfinalized objects are considered ready for finalization and the process is repeated until no new objects are created or the scoped memory's reference count is no longer ready to be decremented from one to zero. When the scope contains no unfinalized objects and its reference count is ready to be decremented from one to zero and the pinned count is equal to zero, any async event in the scope is no longer treated as a source of fireability for async event handlers. If that action causes object creation in the scope the finalization process resumes from the beginning, if the reference count is no longer ready to be decremented to zero the finalization process terminates, otherwise, the reference count is decremented to zero and the memory scope is emptied of all objects. The process of scope finalization starts when the scope's reference count is about to go to zero with a zero pin count and continues until the scope is emptied or the process is terminated because the reference count is no longer about to go to zero. The RTSJ implementation must behave effectively as if during the finalization process the SO executing the finalization of a scope held a synchronized lock that must also be acquired to increase the reference count when entering the scope, to increase the reference count during startup for a thread with the finalizing scope as its non-default initial memory area, and to increase the reference count while making fireable an AEH with the scope as its non-default initial memory area. Although the steps in scope finalization are ordered no order is specified for finalization of objects or for disarming fireability of AEHs. The objects may be processed in any order or concurrently, but at no time may a scope's reference count be reduced to zero while it has one or more child scopes. (This semantic is a special case of the finalization implementation specified in The Java Language Specification, second edition, section 12.6.1.)

- 20. When the pinned count is ready to go to zero and the reference count is zero, all unfinalized objects within that area are considered ready for finalization, and the same semantics as 19 above applies.
- 21. Finalization may start when all unfinalized objects in the scope are ready for finalization. Finalizers are executed with the current allocation context set to the finalizing scope and are executed by the schedulable in control of the scope when its reference count is ready to be decremented from one to zero. If finalizers are executed because a realtime thread terminates or an AsyncEvent-Handler becomes non-fireable, that realtime thread or AsyncEventHandler is considered in control of the scope and must execute the finalizers.
- 22. From the time objects in a scope are deleted until the portal on the scope

392 11.3 Semantics

is successfully set to a non-null value with setPortal, the value returned by getPortal on that scoped memory object must be null.

11.3.6 Immortal memory

- 23. Objects created in any immortal memory area are unexceptionally referenceable from all Java threads, and all schedulables, and the allocation and use of objects in immortal memory is never subject to garbage collection delays.
- 24. An implementation may execute finalizers for immortal objects when it determines that the application has terminated. Finalizers will be executed by a thread or schedulable whose current allocation context is not scoped memory. Regardless of any call to runFinalizersOnExit, except as required to support the base Java platform, the system need not execute finalizers for immortal objects that remain unfinalized when the JVM begins termination.
- 25. Class objects, the associated static memory, and interned Strings behave effectively as if they were allocated in immortal memory with respect to reference rules, assignment rules, and preemption delays by no-heap schedulables. Static initializers are executed effectively as if the current thread performed ImmortalMemory.instance().executeInArea(r) where r is a Runnable that executes the <clinit> method of the class being initialized.

11.3.7 Maintaining referential integrity

26. Assignment rules placed on reference assignments prevent the creation of dangling references, and thus maintain the referential integrity of the Java runtime. The restrictions are listed in the following table:

Stored in	Reference	Reference	Reference to Object	null
Area	to Object	to Object in	in Scoped	
	in Heap	Immortal		
Heap	Permit	Permit	Forbid	Permit
Immortal	Permit	Permit	Forbid	Permit
Scoped	Permit	Permit	Permit from same or	Permit
			less deeply nested scope	
Local	Permit	Permit	Permit	Permit
Variable				

For this table, ImmortalMemory and ImmortalPhysicalMemory are equivalent, and all sub-classes of ScopedMemory are equivalent.

27. An implementation must ensure that the above checks are performed for each assignment statement before the statement is executed, either by runtime checks or by static analysis of the application logic. Checks for operations on local

variables are not required because a potentially invalid reference would be captured by the other checks before it reached a local variable.

11.3.8 Object initialization

- 28. Static initializers run with the immortal memory area as their allocation context.
- 29. The current allocation context in a constructor for an object is the memory area in which the object is allocated. For new, this is the current allocation context when new was called. For members of the m.newinstance family, the current allocation context is memory area m.

11.3.9 Maintaining the Scope Stack

This section describes maintenance of a data structure that is called the *scope stack*. Implementations are not required to use a stack or implement the algorithms given here. It is only required that an implementation behave with respect to the ordering and accessibility of memory scopes effectively as if it implemented these algorithms. The scope stack is implicitly visible through the assignment rules, and the stack is explicitly visible through the static method getOuterMemoryArea(int) on Real-timeThread.

Four operations affect the scope stack: the enter methods defined in MemoryArea and its subclasses, instantiation of a new Schedulable, the executeInArea method in MemoryArea, and the new instance methods in MemoryArea.

- The memory area at the top of a schedulable object's scope stack is the schedulable's current allocation context.
- When a schedulable, t, creates a schedulable object, n_t , in a ScopedMemory object's allocation area, n_t acquires a copy of the scope stack associated with t at the time n_t is constructed including all entries from up to and including the memory area containing n_t . If n_t is created in heap, immortal, or immortal physical memory, n_t is created with a scope stack containing only heap, immortal, or immortal physical memory respectively. If n_t has a non-default initial memory area, ima, then ima is pushed on n_t 's newly-created scope stack.
- When a memory area, ma is entered by calling a ma.enter method, ma is pushed on the scope stack and becomes the *allocation context* of the current schedulable object. When control returns from the enter method, the allocation context is popped from the scope stack
- When a memory area, m, is entered by calling m's executeInArea method or one of the m.newInstance methods, the scope stack before the method call is preserved and replaced with a scope stack constructed as follows:

394 11.3 Semantics

 when ma is a scoped memory area, the new scope stack is a copy of the schedulable's previous scope stack up to and including ma, and

when ma is not a scoped memory area, the new scope stack includes only

When control returns from the executeInArea method, the scope stack is restored to the value it had before ma.executeInArea or ma.newInstance was called.

For the purposes of these algorithms, stacks grow up. One should also note that the representative algorithms ignore important issues like freeing objects in scopes.

- In every case, objects in a scoped memory area are eligible to be freed when the reference count for the area is zero after finalizers for that scope are run.
- Informally, any objects in a scoped memory area *must* be freed and their finalizers run before the reference count for the memory area is incremented from zero to one.

11.3.10 The enter method

For ma.enter(logic):

```
push ma on the scope stack belonging to the current schedulable

-- which may throw ScopedCycleException

execute logic.run method

pop ma from the scope stack
```

11.3.11 The executeInArea or newInstance methods

For ma.executeInArea(logic), ma.newInstance(), or ma.newArray():

```
when ma is an instance of heap immortal or ImmortalPhysicalMemory,
 1
 2
         start a new scope stack containing only ma.
 3
        make the new scope stack the scope stack for the current
 4
            schedulable.
 5
     else if ma is in the scope stack for the current schedulable,
 6
        start a new scope stack containing ma and all
 7
           scopes below ma on the scope stack.
 8
        make the new scope stack the scope stack for the current
 9
           schedulable.
10
     else
11
        throw InaccessibleAreaException, execute logic.run,
12
            or construct the object.
13
        restore the previous scope stack for the current schedulable.
14
         discard the new scope stack.
15
     end
```

11.3.12 Constructor methods for Schedulables

For construction of a schedulable in memory area cma with initial memory area of ima:

```
1
    if cma is heap, immortal or ImmortalPhysicalMemory,
2
       create a new scope stack containing cma.
3
    else
4
       start a new scope stack containing the entire
5
           current scope stack.
6
7
    if ima != cma
8
       push ima on the new scope stack
9
           -- which may throw ScopedCycleException.
```

The above pseudocode illustrates a straightforward implementation of this specification's semantics, but any implementation that behaves effectively like this one with respect to reference count values of zero and one is permissible. An implementation may be eager or lazy in maintenance of its reference count provided that it correctly implements the semantics for reference counts of zero and one.

11.3.13 The Single Parent Rule

Every push of a scoped memory type on a scope stack requires reference to the single parent rule, this enforces the invariant that every scoped memory area has no more than one parent.

The parent of a scoped memory area is identified by the following rules:

- when the memory area is not currently on any scope stack, it has no parent;
- when the memory area is the first scoped memory area on a scope stack, i.e., was entered from ImmortalMemory or Heap, its parent is the *primordial scope*,
- otherwise, the parent is the first scoped memory area outside it on the scope stack, i.e., the scope from which this scope was entered.

Except for the primordial scope, which represents heap, immortal and immortal physical memory, only scoped memory areas are visible to the single parent rule.

The operational effect of the single parent rule is that when a scoped memory area has a parent, the only legal change to that value is to "no parent." Thus an ordering imposed by the first assignments of parents of a series of nested scoped memory areas is the only nesting order allowed until control leaves the scopes; then a new nesting order is possible. Thus, a schedulable attempting to enter a scope can only do so by entering in the established nesting order.

396 11.3 Semantics

11.3.14 Scope Tree Maintenance

The single parent rule is enforced effectively as if there were a tree with the primordial scope (representing heap, immortal, and immortal physical memory) at its root, and other nodes corresponding to every scoped memory area that is currently on any schedulable's scope stack.

Each scoped memory has a reference to its parent memory area, ma.parent. The parent reference may indicate a specific scoped memory area, no parent, or the primordial parent.

If a scoped memory area is the non-default initial memory area of an async event handler, or the non-default initial memory area of a realtime thread that has not terminated, it is referred to as *pinned*.

11.3.14.1 On Scope Stack Push of ma

The following procedure could be used to maintain the scope tree and ensure that push operations on a schedulable's scope stack do not violate the single parent rule.

```
precondition: ma.parent is set to the correct parent (either a scoped
 2
      memory area or the primordial scope) or to noParent.
 3
 4
     t.scopeStack is the scope stack of the current schedulable
 5
 6
     if ma is scoped,
 7
        parent = findFirstScope(t.scopeStack)
 8
     if ma.parent == noParent
9
        ma.parent = parent.
10
     else if ma.parent != parent
11
        throw ScopedCycleException.
12
13
         t.scopeStack.push(ma).
```

findFirstScope is a convenience function that looks down the scope stack for the next entry that is a reference to an instance of ScopedMemoryArea.

```
findFirstScope(scopeStack)

for s = top of scope stack to bottom of scope stack
if s is an instance of scopedMemory
return s return primordial scope

}
```

11.3.14.2 On Scope Stack Pop of ma

```
1 ma = t.scopeStack.pop.
2 if ma is scoped
3     if !(ma.in_use || ma.pinned)
4          ma.parent = noParent
```

11.4 Package javax.realtime

11.4.1 Interfaces

11.4.1.1 ChildScopeVisitor

This interface is used to visit the members of the set of scoped children of a memory area. An object implementing this interface is passed to the MemoryArea.visitScopedChildren² method.

11.4.1.1.1 Methods

visit(ScopedMemory)

Visit the members of the set of child scopes. It provides a means of accessing all live scopes contained in a memory area, even those to which no reference exits, such a PinnableMemory³ that is pinned or another ScopedMemory that contains a Schedulable. The set may be concurrently modified by other tasks, but the view seen by the visitor may not be updated to reflect those changes. The following is guarantees even when the set is disturbed by other tasks:

- the visitor shall visit no member more than once,
- it shall visit only scopes that were a member of the set at some time during the enumeration of the set, and it shall visit all the scopes that are not deleted during the execution of the visitor.

Signature

public
R visit(ScopedMemory scope)

Parameters

scope The scoped memory area being visited.

Returns

Any object chosen by the application. When visit returns a non-null value, no more scopes are visited and the MemoryArea.visitScopedChildren⁴ method

²Section 11.4.2.3.2

 $^{^3}$ Section 11.5.3.5

 $^{^{4}}$ Section 11.4.2.3.2

returns the value returned by visit(ScopedMemory)⁵.

11.4.2 Classes

11.4.2.1 HeapMemory

The HeapMemory class is a singleton object that allows logic with a non-heap allocation context to allocate objects in the Java heap.

Inheritance

```
javax.realtime.MemoryArea
javax.realtime.HeapMemory
```

11.4.2.1.1 Methods

enter

Associate this memory area with the current schedulable for the duration of the execution of the run() method of the instance of Runnable given in the constructor. During this period of execution, this memory area becomes the default allocation context until another default allocation context is selected (using enter, or executeInArea⁶) or the enter method exits.

```
Signature \\ \text{public} \\ \text{void enter()} \\ Throws \\ \textit{IllegalThreadStateException} \text{ when the caller is a Java thread.} \\ \textit{IllegalArgumentException} \text{ @inheritDoc} \\ \textit{MemoryAccessError} \text{ when caller is a no-heap schedulable.} \\
```

```
<sup>5</sup>Section 11.4.1.1.1

<sup>6</sup>Section 11.4.2.1.1
```

enter(Runnable)

Associate this memory area with the current schedulable for the duration of the execution of the run() method of the given Runnable. During this period of execution, this memory area becomes the default allocation context until another default allocation context is selected (using enter, or executeInArea⁷) or the enter method exits.

```
Signature

public

void enter(Runnable logic)

Parameters

logic The Runnable object whose run() method should be invoked.

Throws

MemoryAccessError when caller is a no-heap schedulable.

IllegalThreadStateException @inheritDoc

IllegalArgumentException @inheritDoc
```

instance

Returns a reference to the singleton instance of HeapMemory⁸ representing the Java heap. The singleton instance of this class shall be allocated in the Immortal-Memory⁹ area.

```
Signature

public static
javax.realtime.HeapMemory instance()

Returns

The singleton HeapMemory<sup>10</sup> object.
```

executeInArea(Runnable)

Execute the run method from the logic parameter using heap as the current allocation context. For a schedulable, this saves the current scope stack and replaces

```
<sup>7</sup>Section 11.4.2.1.1

<sup>8</sup>Section 11.4.2.1

<sup>9</sup>Section 11.4.2.2

<sup>10</sup>Section 11.4.2.1
```

it with one consisting only of the HeapMemory instance; restoring the original scope stack upon completion.

```
Signature
```

public

void executeInArea(Runnable logic)

Parameters 1 4 1

logic The runnable object whose run() method should be executed.

Throws

IllegalArgumentException when logic is null.

MemoryAccessError when caller is a no-heap schedulable.

newArray(java.lang.Class<?>, int)

Allocate an array of the given type in this memory area. This method may be concurrently used by multiple threads.

```
Signature
```

public

java.lang.Object newArray(java.lang.Class<?> type, int number)

Parameters

type @inheritDoc

number @inheritDoc

Throws

MemoryAccessError when caller is a no-heap schedulable.

IllegalArgumentException @inheritDoc

OutOfMemoryError @inheritDoc

Returns

@inheritDoc

newInstance(java.lang.Class)

Allocate an object in this memory area. This method may be concurrently used by multiple threads.

Signature

public

```
java.lang.Object newInstance(java.lang.Class type)
throws IllegalAccessException, InstantiationException

Parameters
type @inheritDoc

Throws

MemoryAccessError when caller is a no-heap schedulable.
IllegalAccessException @inheritDoc
IllegalArgumentException @inheritDoc
ExceptionInInitializerError @inheritDoc
OutOfMemoryError @inheritDoc
InstantiationException @inheritDoc
Returns
@inheritDoc
```

newInstance(java.lang.reflect.Constructor, java.lang.Object[])

Allocate an object in this memory area. This method may be concurrently used by multiple threads.

```
Signature
    public
    java.lang.Object newInstance(java.lang.reflect.Constructor c,
    java.lang.Object[] args)
    throws IllegalAccessException, InstantiationException,
    InvocationTargetException
c T@inheritDoc
    args @inheritDoc
Throws
    MemoryAccessError when caller is a no-heap schedulable.
    IllegalAccessException @inheritDoc
    InstantiationException @inheritDoc
     OutOfMemoryError @inheritDoc
    IllegalArgumentException @inheritDoc
    Invocation TargetException @inheritDoc
Returns
    @inheritDoc
```

2.0 (Draft 20)

visitScopedChildren(javax.realtime.ChildScopeVisitor<R>)

Visit each scoped memory area who's parent is the primordial scope and was created in heap memory.

```
public
    R visitScopedChildren(javax.realtime.ChildScopeVisitor<R>
    visitor)
Parameters
```

visitor invoke the ChildScopeVisitor.visit(ScopedMemory)¹¹ method for each member of the set of scoped memory areas that was created in heap memory and has the primordial scope as its parent.

Throws

IllegalArgumentException @inheritDoc

Returns

@inheritDoc

11.4.2.2 ImmortalMemory

ImmortalMemory is a memory resource that is unexceptionally available to all schedulables and Java threads for use and allocation.

An immortal object may not contain references to any form of scoped memory, e.g., LTMemory¹², StackedMemory¹³, PinnableMemory¹⁴, or LTPhysicalMemory¹⁵.

Objects in immortal have the same states with respect to finalization as objects in the standard Java heap, but there is no assurance that immortal objects will be finalized even when the JVM is terminated.

Methods from ImmortalMemory should be overridden only by methods that use super.

Inheritance

```
javax.realtime.MemoryArea
javax.realtime.ImmortalMemory
```

¹¹Section 11.4.1.1.1 ¹²Section 11.5.3.1

¹³Section 11.5.3.6

¹⁴Section 11.5.3.5

 $^{^{15}}$ Section 15.3.3.2

11.4.2.2.1 Methods

instance

Returns a pointer to the singleton ImmortalMemory¹⁶ object.

```
Signature

public static
 javax.realtime.ImmortalMemory instance()

Returns

The singleton ImmortalMemory<sup>17</sup> object.
```

executeInArea(Runnable)

Execute the run method from the logic parameter using this memory area as the current allocation context. For a schedulable, this saves the current scope stack and replaces it with one consisting only of the ImmortalMemory instance; restoring the original scope stack upon completion.

```
Signature

public

void executeInArea(Runnable logic)

Parameters

logic The runnable object whose run() method should be executed.

Throws

IllegalArgumentException when logic is null.
```

visitScopedChildren(javax.realtime.ChildScopeVisitor<R>)

Visit each scoped memory area who's parent is the primordial scope and was created in this memory area.

Signature

```
<sup>16</sup>Section 11.4.2.2
<sup>17</sup>Section 11.4.2.2
```

public
R visitScopedChildren(javax.realtime.ChildScopeVisitor<R>
visitor)

visitor invoke the ChildScopeVisitor.visit(ScopedMemory)¹⁸ method for each member of the set of scoped memory areas that was created in this immortal memory area and has the primordial scope as its parent.

Throws

IllegalArgumentException @inheritDoc

Returns

@inheritDoc

11.4.2.3 MemoryArea

MemoryArea is the abstract base class of all classes dealing with the representations of allocatable memory areas, including the immortal memory area, physical memory and scoped memory areas. This is an abstract class, but no method in this class is abstract. An application should not subclass MemoryArea without complete knowledge of its implementation details.

Inheritance

```
java.lang.Object
javax.realtime.MemoryArea
```

11.4.2.3.1 Constructors

MemoryArea(long)

Create an instance of MemoryArea.

Signature

protected
 MemoryArea(long size)

¹⁸Section 11.4.1.1.1

throws IllegalArgumentException, OutOfMemoryError

Parameters

size The size of MemoryArea to allocate, in bytes.

Throws

IllegalArgumentException when size is less than zero.

OutOfMemoryError when there is insufficient memory for the MemoryArea object or for the backing memory.

MemoryArea(SizeEstimator)

Create an instance of MemoryArea.

Signature

protected

MemoryArea(SizeEstimator size)

throws IllegalArgumentException, OutOfMemoryError

Parameters 1

size A SizeEstimator¹⁹ object which indicates the amount of memory required by this MemoryArea.

Throws

IllegalArgumentException when the size parameter is null, or size.getEstimate() is negative.

OutOfMemoryError when there is insufficient memory for the MemoryArea object or for the backing memory.

MemoryArea(long, Runnable)

Create an instance of MemoryArea.

Signature

protected

MemoryArea(long size, Runnable logic)

¹⁹Section 11.4.2.6

throws IllegalArgumentException, OutOfMemoryError, IllegalAssignmentError

Parameters

size The size of MemoryArea to allocate, in bytes.

logic The run() method of this object will be called whenever enter()²⁰ is called. When logic is null, this constructor is equivalent to Memory-Area(long size).

Throws

IllegalArgumentException when the size parameter is less than zero.

OutOfMemoryError when there is insufficient memory for the MemoryArea object or for the backing memory.

IllegalAssignmentError when storing logic in this would violate the assignment rules.

MemoryArea(SizeEstimator, Runnable)

Create an instance of MemoryArea.

Signature

protected

MemoryArea(SizeEstimator size, Runnable logic)

throws IllegalArgumentException, OutOfMemoryError, IllegalAssignmentError

Parameters

size A SizeEstimator object which indicates the amount of memory required by this MemoryArea.

logic The run() method of this object will be called whenever enter()²¹ is called. When logic is null, this constructor is equivalent to Memory-Area(SizeEstimator size).

Throws

IllegalArgumentException when size is null or size.getEstimate() is negative.

OutOfMemoryError when there is insufficient memory for the MemoryArea object or for the backing memory.

 $^{^{20}}$ Section 11.4.2.3.2

²¹Section 11.4.2.3.2

IllegalAssignmentError when storing logic in this would violate the assignment rules.

11.4.2.3.2 Methods

enter

Associate this memory area with the current schedulable for the duration of the execution of the run() method of the instance of Runnable given in the constructor. During this period of execution, this memory area becomes the default allocation context until another default allocation context is selected (using enter, or executeInArea²²) or the enter method exits.

```
Signature
    public
    void enter()
    throws IllegalArgumentException, OutOfMemoryError,
    IllegalAssignmentError, MemoryAccessError
Throws
```

IllegalThreadStateException when the caller is a Java thread.

IllegalArgumentException when the caller is a schedulable and no non-null value for logic was supplied when the memory area was constructed.

ThrowBoundaryError Thrown when the JVM needs to propagate an exception allocated in this scope to (or through) the memory area of the caller. Storing a reference to that exception would cause an IllegalAssignmentError²³, so the JVM cannot be permitted to deliver the exception. The ThrowBoundary-Error²⁴ is allocated in the current allocation context and contains information about the exception it replaces.

MemoryAccessError when caller is a no-heap schedulable and this memory area's logic value is allocated in heap memory.

enter(Runnable)

²²Section 11.4.2.3.2 ²³Section 14.2.3.3

 $^{^{24}}$ Section 14.2.3.6

Associate this memory area with the current schedulable for the duration of the execution of the run() method of the given Runnable. During this period of execution, this memory area becomes the default allocation context until another default allocation context is selected (using enter, or executeInArea²⁵) or the enter method exits.

```
Signature

public

void enter(Runnable logic)
```

Parameters 5 4 1

logic The Runnable object whose run() method should be invoked.

Throws

IllegalThreadStateException when the caller is a Java thread.

IllegalArgumentException when the caller is a schedulable and logic is null. ThrowBoundaryError Thrown when the JVM needs to propagate an exception allocated in this scope to (or through) the memory area of the caller. Storing a reference to that exception would cause an IllegalAssignmentError²⁶, so the JVM cannot be permitted to deliver the exception. The ThrowBoundary-Error²⁷ is allocated in the current allocation context and contains information about the exception it replaces.

enter(java.util.function.Supplier<T>)

Same as enter (Runnable)²⁸ except that the executed method is called get and an object is returned.

```
Signature
```

```
public
T enter(java.util.function.Supplier<T> logic)
```

Parameters 5

logic the object who's get method will be executed.

Returns

a result from the computation.

```
<sup>25</sup>Section 11.4.2.3.2

<sup>26</sup>Section 14.2.3.3
```

 $^{^{27}}$ Section 14.2.3.6

²⁸Section 11.4.2.3.2

enter(BooleanSupplier)

Same as enter(Runnable)²⁹ except that the executed method is called get and a boolean is returned.

```
Signature

public
boolean enter(BooleanSupplier logic)

Parameters
logic the object who's get method will be executed.

Returns
a result from the computation.
```

enter(IntSupplier)

Same as $enter(Runnable)^{30}$ except that the executed method is called get and an int is returned.

```
public
    int enter(IntSupplier logic)

Parameters
    logic the object who's get method will be executed.

Returns
    a result from the computation.
```

enter(LongSupplier)

Same as $enter(Runnable)^{31}$ except that the executed method is called get and a long is returned.

```
public long enter(LongSupplier logic)

29 Section 11.4.2.3.2
30 Section 11.4.2.3.2
31 Section 11.4.2.3.2
```

Parameters

logic the object who's get method will be executed.

Returns

a result from the computation.

enter(DoubleSupplier)

Same as enter (Runnable)³² except that the executed method is called get and a double is returned.

```
Signature

public
double enter(DoubleSupplier logic)

Parameters
logic the object who's get method will be executed.

Returns
a result from the computation.
```

getMemoryArea(Object)

Gets the MemoryArea in which the given object is located.

```
Signature
```

```
public static
javax.realtime.MemoryArea getMemoryArea(Object object)
```

Throws

IllegalArgumentException when the value of object is null.

Returns

The instance of MemoryArea from which object was allocated.

${\bf memory Consumed}$

For memory areas where memory is freed under program control this returns an exact count, in bytes, of the memory currently used by the system for the allocated objects. For memory areas (such as heap) where the definition of "used" is imprecise, this returns the best value it can generate in constant time.

 $^{^{32}}$ Section 11.4.2.3.2

```
Signature

public
long memoryConsumed()

Returns

The amount of memory consumed in bytes.
```

memoryRemaining

An approximation to the total amount of memory currently available for future allocated objects, measured in bytes.

```
Signature

public
long memoryRemaining()

Returns

The amount of remaining memory in bytes.
```

newArray(java.lang.Class<?>, int)

Allocate an array of the given type in this memory area. This method may be concurrently used by multiple threads.

```
Signature
```

```
public
java.lang.Object newArray(java.lang.Class<?> type, int number)
throws IllegalArgumentException, OutOfMemoryError,
SecurityException
```

Parameters

type The class of the elements of the new array. To create an array of a primitive type use a type such as Integer. TYPE (which would call for an array of the primitive int type.)

number The number of elements in the new array.

Throws

IllegalArgumentException when number is less than zero, type is null, or type is java.lang.Void.TYPE.

OutOfMemoryError when space in the memory area is exhausted.

2.0 (Draft 20)

SecurityException when the caller does not have permission to create a new instance.

Returns

A new array of class type, of number elements.

newInstance(java.lang.Class<T>)

Allocate an object in this memory area. This method may be concurrently used by multiple threads.

Signature

public

T newInstance(java.lang.Class<T> type)

throws IllegalAccessException, IllegalArgumentException,

InstantiationException, OutOfMemoryError,

ExceptionInInitializerError, SecurityException

Parameters

type The class of which to create a new instance.

Throws

IllegalAccessException The class or initializer is inaccessible.

IllegalArgumentException when type is null.

InstantiationException when the specified class object could not be instantiated. Possible causes are: it is an interface, it is abstract, it is an array, or an exception was thrown by the constructor.

OutOfMemoryError when space in the memory area is exhausted.

ExceptionInInitializerError when an unexpected exception has occurred in a static initializer

SecurityException when the caller does not have permission to create a new instance.

Returns

A new instance of class type.

newInstance(java.lang.reflect.Constructor<T>, java.lang.Object[])

Allocate an object in this memory area. This method may be concurrently used by multiple threads.

Signature

public

T newInstance(java.lang.reflect.Constructor<T> c,

java.lang.Object[] args)

throws ExceptionInInitializerError, IllegalAccessException,

IllegalArgumentException, InstantiationException,

InvocationTargetException, OutOfMemoryError, SecurityException

Parameters

c The constructor for the new instance.

args An array of arguments to pass to the constructor.

Throws

ExceptionInInitializerError when an unexpected exception has occurred in a static initializer

IllegalAccessException when the class or initializer is inaccessible under Java access control.

IllegalArgumentException when c is null, or the args array does not contain the number of arguments required by c. A null value of args is treated like an array of length 0.

Instantiation Exception when the specified class object could not be instantiated. Possible causes are: it is an interface, it is abstract, it is an array.

Invocation Target Exception when the underlying constructor throws an exception.

OutOfMemoryError when space in the memory area is exhausted.

Security Exception when the caller does not have permission to create a new instance.

Returns

A new instance of the object constructed by c.

size

Query the size of the memory area. The returned value is the current size. Current size may be larger than initial size for those areas that are allowed to grow.

Signature

public
long size()

Returns

The size of the memory area in bytes.

2.0 (Draft 20)

executeInArea(Runnable)

Execute the run method from the logic parameter using this memory area as the current allocation context. The effect of executeInArea on the scope stack is specified in the subclasses of MemoryArea.

```
Signature

public

void executeInArea(Runnable logic)

throws IllegalArgumentException

Parameters

logic The runnable object whose run() method should be executed.

Throws

IllegalArgumentException when logic is null.
```

executeInArea(java.util.function.Supplier<T>)

Same as executeInArea(Runnable)³³ except that the executed method is called get and an object is returned.

```
public
    T executeInArea(java.util.function.Supplier<T> logic)
Parameters
    logic the object who's get method will be executed.
Returns
    a result from the computation.
```

executeInArea(BooleanSupplier)

Same as executeInArea(Runnable)³⁴ except that the executed method is called get and a boolean is returned.

```
Signature \\ \texttt{public}
\frac{^{33}\text{Section } 11.4.2.3.2}{^{34}\text{Section } 11.4.2.3.2}
```

boolean executeInArea(BooleanSupplier logic)

Parameters

logic the object who's get method will be executed.

Returns

a result from the computation.

executeInArea(IntSupplier)

Same as $executeInArea(Runnable)^{35}$ except that the executed method is called get and an int is returned.

```
Signature
```

public

int executeInArea(IntSupplier logic)

Parameters

logic the object who's get method will be executed.

Returns

a result from the computation.

executeInArea(LongSupplier)

Same as $executeInArea(Runnable)^{36}$ except that the executed method is called get and a long is returned.

Signature

public

long executeInArea(LongSupplier logic)

Parameters 5

logic the object who's get method will be executed.

Returns

a result from the computation.

execute In Area (Double Supplier)

 $^{^{35}}$ Section 11.4.2.3.2

 $^{^{36}}$ Section 11.4.2.3.2

Same as executeInArea(Runnable)³⁷ except that the executed method is called get and a double is returned.

```
Signature

public
double executeInArea(DoubleSupplier logic)

Parameters
logic the object who's get method will be executed.

Returns
a result from the computation.
```

visitScopedChildren(javax.realtime.ChildScopeVisitor<R>)

Perform an action on all children scopes of this memory area, so long as the ChildScopeVisitor.visit(LocalAllocationContext) method returns null. When that method returns an object, the visit is terminated and that object is returned by this method,

The set of children may be concurrently modified by other tasks, but the view seen by the visitor might not be updated to reflect those changes. The guarantees when the set is disturbed by other tasks are

- the visitor shall visit no member more than once,
- it shall visit only scopes that were a member of the set at some time during the enumeration of the set,
- it shall visit all the scopes that are not deleted during the enumeration of the set.
- it shall visit only scopes that were a member of the set at some time during the enumeration of the set, but need not visit all scopes that became a member of the set during the enumeration of the set, and
- it shall visit all the scopes that are not deleted during the execution of the visitor, but may also visit scopes that were deleted.

When execution of the visitor's visit method terminated abruptly by throwing an exception, then execution of visitScopedChildren also terminates abruptly by throwing the same exception.

```
Signature
public

37Section 11.4.2.3.2
```

```
R visitScopedChildren(javax.realtime.ChildScopeVisitor<R>
visitor)
throws IllegalArgumentException
```

Parameters

visitor determines the action to be performed on each of the children scopes.

Throws

IllegalArgumentException when visitor is null.

Returns

null when all elements where visited and some object when the visit is forced to terminate at the end of visiting some element.

mayHoldReferenceTo

Determine whether an object A allocated in the memory area represented by this can hold a reference to an object B allocated in the current memory area.

```
Signature
public
boolean mayHoldReferenceTo()
```

Returns

true when B can be assigned to a field of A, otherwise false.

mayHoldReferenceTo(Object)

Determine whether an object A allocated in the memory area represented by this can hold a reference to the object value.

```
Signature

public

boolean mayHoldReferenceTo(Object value)
```

Parameters

value is the object to test.

Returns

true when value can be assigned to a field of A, otherwise false.

11.4.2.4 MemoryParameters

Memory parameters can be given on the constructor of RealtimeThread³⁸ and Async-EventHandler³⁹. These can be used both for the purposes of admission control by the scheduler and for the purposes of pacing the garbage collector (if any) to satisfy all of the schedulable memory allocation rates.

The limits in a MemoryParameters instance are enforced when a schedulable creates a new object, e.g., uses the new operation. When a schedulable exceeds its allocation or allocation rate limit, the error is handled as if the allocation failed because of insufficient memory. The object allocation throws an OutOfMemoryError.

When a reference to a MemoryParameters object is given as a parameter to a constructor, the MemoryParameters object becomes bound to the object being created. Changes to the values in the MemoryParameters object affect the constructed object. When given to more than one constructor, then changes to the values in the MemoryParameters object affect all of the associated objects. Note that this is a one-to-many relationship and not a many-to-many.

A MemoryParameters object may be shared, but that does not cause the memory budgets reflected by the parameter to be shared among the schedulables that are associated with the parameter object.

Caution: This class is explicitly unsafe for multithreading when being changed. Code that mutates instances of this class should synchronize at a higher level.

Inheritance

java.lang.Object javax.realtime.MemoryParameters Interfaces Cloneable Serializable

11.4.2.4.1 Fields

NO₋MAX

public static final NO_MAX
Specifies no maximum limit.

11.4.2.4.2 Constructors

 $^{^{38}}$ Section 5.3.2.2 39 Section 8.4.3.5

MemoryParameters(long, long)

Create a MemoryParameters object with the given values.

Signature

public

MemoryParameters(long maxMemoryArea, long maxImmortal)

Parameters

maxMemoryArea A limit on the amount of memory the schedulable may allocate in its initial memory area. Units are in bytes. When zero, no allocation allowed in the memory area. To specify no limit, use NO_MAX.

maxImmortal A limit on the amount of memory the schedulable may allocate in the immortal area. Units are in bytes. When zero, no allocation allowed in immortal. To specify no limit, use NO_MAX.

Throws

IllegalArgumentException when any value other than positive. zero, or NO_MAX is passed as the value of maxMemoryArea or maxImmortal.

MemoryParameters(long, long, long)

Create a MemoryParameters object with the given values.

Signature

public

MemoryParameters(long maxMemoryArea, long maxImmortal, long allocationRate)

Parameters

maxMemoryArea A limit on the amount of memory the schedulable may allocate in its initial memory area. Units are in bytes. When zero, no allocation allowed in the memory area. To specify no limit, use NO_MAX.

maxImmortal A limit on the amount of memory the schedulable may allocate in the immortal area. Units are in bytes. When zero, no allocation allowed in immortal. To specify no limit, use NO_MAX.

2.0 (Draft 20)

allocationRate A limit on the rate of allocation in the heap. Units are in bytes per second of wall clock time. When allocationRate is zero, no allocation is allowed in the heap. To specify no limit, use NO_MAX. Measurement starts when the schedulable is first released for execution (not when it is constructed.) Enforcement of the allocation rate is an implementation option. When the implementation does not enforce allocation rate limits, it treats all non-zero allocation rate limits as NO_MAX.

Throws

IllegalArgumentException when any value other than positive. zero, or NO_MAX is passed as the value of maxMemoryArea or maxImmortal, or allocationRate.

11.4.2.4.3 Methods

clone

Return a clone of this. This method should behave effectively as if it constructed a new object with the visible values of this.

- The new object is in the current allocation context.
- clone does not copy any associations from this and it does not implicitly bind the new object to a SO.

Available since RTSJ 1.0.1

```
Signature
public
java.lang.Object clone()
```

getAllocationRate

Gets the limit on the rate of allocation in the heap. Units are in bytes per second.

```
Signature
    public
    long getAllocationRate()
Returns
```

2.0 (Draft 20)

The allocation rate in bytes per second. When zero, no allocation is allowed in the heap. When the returned value is NO_MAX⁴⁰ then the allocation rate on the heap is uncontrolled.

getMaxImmortal

Gets the limit on the amount of memory the schedulable may allocate in the immortal area. Units are in bytes.

```
Signature
    public
    long getMaxImmortal()
```

Returns

The limit on immortal memory allocation. When zero, no allocation is allowed in immortal memory. When the returned value is NO_MAX⁴¹ then there is no limit for allocation in immortal memory.

getMaxMemoryArea

Gets the limit on the amount of memory the schedulable may allocate in its initial memory area. Units are in bytes.

```
Signature

public
long getMaxMemoryArea()

Returns
```

The allocation limit in the schedulable's initial memory area. When zero, no allocation is allowed in the initial memory area. When the returned value is NO_MAX^{42} then there is no limit for allocation in the initial memory area.

setAllocationRate(long)

Sets the limit on the rate of allocation in the heap.

⁴⁰Section 11.4.2.4.1

⁴¹Section 11.4.2.4.1

 $^{^{42}}$ Section 11.4.2.4.1

Signature

public

void setAllocationRate(long allocationRate)

Parameters 5 4 1

allocationRate Units are in bytes per second of wall-clock time. When allocationRate is zero, no allocation is allowed in the heap. To specify no limit, use NO_MAX. Measurement starts when the schedulable starts (not when it is constructed.) Enforcement of the allocation rate is an implementation option. When the implementation does not enforce allocation rate limits, it treats all non-zero allocation rate limits as NO_MAX.

Throws

IllegalArgumentException when any value other than positive, zero, or NO_MAX is passed as the value of allocationRate.

11.4.2.5 ScopedMemory

ScopedMemory is the abstract base class of all classes dealing with representations of memory spaces which have a limited lifetime. In general, objects allocated in scoped memory are freed when (and only when) no schedulable object has access to the objects in the scoped memory.

A ScopedMemory area is a connection to a particular region of memory and reflects the current status of that memory. The object does not necessarily contain direct references to the region of memory. That is implementation dependent.

When a ScopedMemory area is instantiated, the object itself is allocated from the current memory allocation context, but the memory space that object represents (it's backing store) is allocated from memory that is not otherwise directly visible to Java code; e.g., it might be allocated with the C malloc function. This backing store behaves effectively as if it were allocated when the associated scoped memory object is constructed and freed at that scoped memory object's finalization.

The ScopedMemory enter⁴³ method of ScopedMemory is one mechanism used to make a memory area the current allocation context. The other mechanism for activating a memory area is making it the initial memory area for a realtime thread or async event handler. Entry into the scope is accomplished, for example, by calling the method:

public void enter(Runnable logic)

where logic is a instance of Runnable whose run() method represents the entry point of the code that will run in the new scope. Exit from the scope occurs between the time the runnable.run() method completes and the time control returns from

⁴³Section 11.4.2.5.2

the enter method. By default, allocations of objects within runnable.run() are taken from the backing store of the ScopedMemory.

ScopedMemory is an abstract class, but all specified methods include implementations. The responsibilities of MemoryArea, ScopedMemory and the classes that extend ScopedMemory are not specified. Application code should not extend ScopedMemory without detailed knowledge of its implementation.

Inheritance

```
javax.realtime.MemoryArea
javax.realtime.ScopedMemory
```

11.4.2.5.1 Constructors

ScopedMemory(long)

Create a new ScopedMemory area with the given parameters.

```
Signature
```

```
public
  ScopedMemory(long size)
```

Parameters

size of the new ScopedMemory area in bytes.

Throws

IllegalArgumentException when size is less than zero.

OutOfMemoryError when there is insufficient memory for the ScopedMemory object or for the backing memory.

ScopedMemory(long, Runnable)

Create a new ScopedMemory area with the given parameters.

Signature

public

ScopedMemory(long size, Runnable logic)

size The size of the new ScopedMemory area in bytes.

logic The Runnable to execute when this ScopedMemory is entered. When logic is null, this constructor is equivalent to constructing the memory area without a logic value.

Throws

IllegalArgumentException when size is less than zero.

IllegalAssignmentError when storing logic in this would violate the assignment rules.

OutOfMemoryError when there is insufficient memory for the ScopedMemory object or for the backing memory.

ScopedMemory(SizeEstimator)

Create a new ScopedMemory area with the given parameters.

Signature

public

ScopedMemory(SizeEstimator size)

Parameters

size The size of the new ScopedMemory area estimated by an instance of SizeEstimator⁴⁴.

Throws

IllegalArgumentException when size is null, or size.getEstimate() is negative.

OutOfMemoryError when there is insufficient memory for the ScopedMemory object or for the backing memory.

ScopedMemory(SizeEstimator, Runnable)

Create a new ScopedMemory area with the given parameters.

⁴⁴Section 11.4.2.6

Signature

```
public
```

ScopedMemory(SizeEstimator size, Runnable logic)

size The size of the new ScopedMemory area estimated by an instance of SizeEstimator⁴⁵.

logic The logic which will use the memory represented by this as its initial memory area. When logic is null, this constructor is equivalent to constructing the memory area without a logic value.

Throws

IllegalArgumentException when size is null, or size.getEstimate() is negative.

OutOfMemoryError when there is insufficient memory for the ScopedMemory object or for the backing memory.

IllegalAssignmentError when storing logic in this would violate the assignment rules.

11.4.2.5.2 Methods

enter

Associate this memory area with the current schedulable for the duration of the execution of the run() method of the instance of Runnable given in the constructor. During this period of execution, this memory area becomes the default allocation context until another default allocation context is selected (using enter, or executeInArea⁴⁶) or the enter method exits.

```
Signature

public
void enter()

Throws

45Section 11.4.2.6
```

⁴⁶Section 11.4.2.5.2

ScopedCycleException when this invocation would break the single parent rule. ThrowBoundaryError Thrown when the JVM needs to propagate an exception allocated in this scope to (or through) the memory area of the caller. Storing a reference to that exception would cause an IllegalAssignmentError⁴⁷, so the JVM cannot be permitted to deliver the exception. The ThrowBoundary-Error⁴⁸ is allocated in the current allocation context and contains information about the exception it replaces.

IllegalThreadStateException when the caller is a Java thread, or when this method is invoked during finalization of objects in scoped memory and entering this scoped memory area would force deletion of the SO that triggered finalization. This would include the scope containing the SO, and the scope (if any) containing the scope containing the SO.

 ${\it Illegal Argument Exception} \ @inherit Doc$

MemoryAccessError @inheritDoc

enter(Runnable)

Associate this memory area with the current schedulable for the duration of the execution of the run() method of the given Runnable. During this period of execution, this memory area becomes the default allocation context until another default allocation context is selected (using enter, or executeInArea⁴⁹) or the enter method exits.

```
Signature

public

void enter(Runnable logic)

Parameters

logic @inheritDoc

Throws
```

ScopedCycleException when this invocation would break the single parent rule. ThrowBoundaryError Thrown when the JVM needs to propagate an exception allocated in this scope to (or through) the memory area of the caller. Storing a reference to that exception would cause an IllegalAssignmentError⁵⁰, so the JVM cannot be permitted to deliver the exception. The ThrowBoundary-Error⁵¹ is allocated in the current allocation context and contains information

```
<sup>47</sup>Section 14.2.3.3

<sup>48</sup>Section 14.2.3.6

<sup>49</sup>Section 11.4.2.5.2

<sup>50</sup>Section 14.2.3.3
```

 $^{^{51}}$ Section 14.2.3.6

about the exception it replaces.

IllegalThreadStateException when the caller is a Java thread, or when this method is invoked during finalization of objects in scoped memory and entering this scoped memory area would force deletion of the SO that triggered finalization. This would include the scope containing the SO, and the scope (if any) containing the scope containing the SO.

IllegalArgumentException @inheritDoc

enter(java.util.function.Supplier<T>)

Same as $enter(Runnable)^{52}$ except that the executed method is called get and an object is returned.

```
Signature
```

```
public
T enter(java.util.function.Supplier<T> logic)
```

Parameters 5 6 7 1

logic the object who's get method will be executed.

Returns

a result from the computation.

enter(BooleanSupplier)

Same as enter(Runnable)⁵³ except that the executed method is called get and a boolean is returned.

```
Signature
```

```
public
boolean enter(BooleanSupplier logic)
```

Parameters

logic the object who's get method will be executed.

Returns

a result from the computation.

 $^{^{52}}$ Section 11.4.2.5.2

⁵³Section 11.4.2.5.2

enter(IntSupplier)

Same as enter(Runnable)⁵⁴ except that the executed method is called get and an int is returned.

```
Signature

public
int enter(IntSupplier logic)

Parameters
logic the object who's get method will be executed.

Returns
a result from the computation.
```

enter(LongSupplier)

Same as $enter(Runnable)^{55}$ except that the executed method is called get and a long is returned.

```
public
long enter(LongSupplier logic)

Parameters
logic the object who's get method will be executed.

Returns
a result from the computation.
```

enter(DoubleSupplier)

Same as enter (Runnable)⁵⁶ except that the executed method is called get and a double is returned.

```
Signature

public
double enter(DoubleSupplier logic)

54Section 11.4.2.5.2
55Section 11.4.2.5.2
56Section 11.4.2.5.2
```

Parameters

logic the object who's get method will be executed.

Returns

a result from the computation.

executeInArea(Runnable)

Execute the run method from the logic parameter using this memory area as the current allocation context. This method behaves as if it moves the allocation context down the scope stack to the occurrence of this.

Signature

```
public
void executeInArea(Runnable logic)
```

Parameters 1 4 1

logic The runnable object whose run() method should be executed.

Throws

IllegalThreadStateException when the caller is a Java thread.

Inaccessible Area Exception when the memory area is not in the schedulable's scope stack.

IllegalArgumentException when the caller is a schedulable and logic is null.

executeInArea(java.util.function.Supplier<T>)

Same as executeInArea(Runnable)⁵⁷ except that the executed method is called get and an object is returned.

Signature

```
public
T executeInArea(java.util.function.Supplier<T> logic)
```

Parameters

logic the object who's get method will be executed.

Returns

a result from the computation.

⁵⁷Section 11.4.2.5.2

executeInArea(BooleanSupplier)

Same as executeInArea(Runnable)⁵⁸ except that the executed method is called get and a boolean is returned.

```
Signature

public
boolean executeInArea(BooleanSupplier logic)

Parameters
logic the object who's get method will be executed.

Returns
a result from the computation.
```

executeInArea(IntSupplier)

Same as executeInArea(Runnable)⁵⁹ except that the executed method is called get and an int is returned.

```
Signature

public
int executeInArea(IntSupplier logic)

Parameters
logic the object who's get method will be executed.

Returns
a result from the computation.
```

executeInArea(LongSupplier)

Same as executeInArea(Runnable)⁶⁰ except that the executed method is called get and a long is returned.

```
Signature

public
long executeInArea(LongSupplier logic)

58Section 11.4.2.5.2
59Section 11.4.2.5.2
60Section 11.4.2.5.2
```

Parameters

logic the object who's get method will be executed.

Returns

a result from the computation.

executeInArea(DoubleSupplier)

Same as executeInArea(Runnable)⁶¹ except that the executed method is called get and a double is returned.

```
public double executeInArea(DoubleSupplier logic)

Parameters logic the object who's get method will be executed.

Returns

a result from the computation.
```

getPortal

Return a reference to the portal object in this instance of ScopedMemory.

Assignment rules are enforced on the value returned by getPortal as if the return value were first stored in an object allocated in the current allocation context, then moved to its final destination.

```
Signature
     public
     java.lang.Object getPortal()
Throws
```

IllegalAssignmentError when a reference to the portal object cannot be stored in the caller's allocation context; that is, when this is "inner" relative to the current allocation context or not on the caller's scope stack.

IllegalThreadStateException when the caller is a Java thread.

Returns

A reference to the portal object or null when there is no portal object. The portal value is always set to null when the contents of the memory are deleted.

⁶¹Section 11.4.2.5.2

getReferenceCount

Returns the reference count of this ScopedMemory.

Note: A reference count of 0 reliably means that the scope is not referenced, but other reference counts are subject to artifacts of lazy/eager maintenance by the implementation.

```
Signature

public

int getReferenceCount()

Returns

The reference count of this ScopedMemory.
```

join

Wait until the reference count of this ScopedMemory goes down to zero. Return immediately when the memory is unreferenced.

```
Signature
    public
    void join()
    throws InterruptedException
Throws
```

InterruptedException When this schedulable is interrupted by RealtimeThread.interrupt()⁶² or AsynchronouslyInterruptedException.fire()⁶³ while waiting for the reference count to go to zero.

IllegalThreadStateException when the caller is a Java thread.

join(javax.realtime.HighResolutionTime<?>)

Wait at most until the time designated by the time parameter for the reference count of this ScopedMemory to drop to zero. Return immediately when the memory area is unreferenced.

Since the time is expressed as a HighResolutionTime⁶⁴, this method is an accurate timer with nanosecond granularity. The actual resolution of the timer and

```
<sup>62</sup>Section 5.3.2.2.2

<sup>63</sup>Section 8.4.2.1.2

<sup>64</sup>Section 9.4.1.2
```

even the quantity it measures depends on the clock associated with time. The delay time may be relative or absolute. When relative, then the delay is the amount of time given by time, and measured by its associated clock. When absolute, then the delay is until the indicated value is reached by the clock. When the given absolute time is less than or equal to the current value of the clock, the call to join returns immediately.

```
Signature
    public
    void join(javax.realtime.HighResolutionTime<?> time)
    throws InterruptedException
```

Parameters 1 4 1

time When this time is an absolute time, the wait is bounded by that point in time. When the time is a relative time (or a member of the RationalTime subclass of RelativeTime) the wait is bounded by a the specified interval from some time between the time join is called and the time it starts waiting for the reference count to reach zero.

Throws

InterruptedException When this schedulable is interrupted by RealtimeThread.interrupt()⁶⁵ or AsynchronouslyInterruptedException.fire()⁶⁶ while waiting for the reference count to go to zero.

IllegalThreadStateException when the caller is a Java thread.

IllegalArgumentException when the caller is a schedulable and time is null.

UnsupportedOperationException when the wait operation is not supported using the clock associated with time.

joinAndEnter

In the error-free case, joinAndEnter combines join(); enter(); such that no enter() from another schedulable can intervene between the two method invocations. The resulting method will wait for the reference count on this ScopedMemory to reach zero, then enter the ScopedMemory and execute the run method from logic passed in the constructor. When no instance of Runnable was passed to the memory area's constructor, the method throws IllegalArgumentException immediately.

When multiple threads are waiting in joinAndEnter family methods for a memory area, at most *one* of them will be released each time the reference count goes to zero.

⁶⁵Section 5.3.2.2.2

 $^{^{66}\}mathrm{Section}~8.4.2.1.2$

Note that although joinAndEnter guarantees that the reference count is zero when the schedulable is released for entry, it does not guarantee that the reference count will remain one for any length of time. A subsequent enter could raise the reference count to two.

```
Signature

public

void joinAndEnter()

throws InterruptedException

Throws
```

InterruptedException When this schedulable is interrupted by RealtimeThread.interrupt()⁶⁷ or AsynchronouslyInterruptedException.fire()⁶⁸ while waiting for the reference count to go to zero.

IllegalThreadStateException when the caller is a Java thread, or when this method is invoked during finalization of objects in scoped memory and entering this scoped memory area would force deletion of the SO that triggered finalization. This would include the scope containing the SO, and the scope (if any) containing the scope containing the SO.

ThrowBoundaryError Thrown when the JVM needs to propagate an exception allocated in this scope to (or through) the memory area of the caller. Storing a reference to that exception would cause an IllegalAssignmentError⁶⁹, so the JVM cannot be permitted to deliver the exception. The ThrowBoundary-Error⁷⁰ is allocated in the current allocation context and contains information about the exception it replaces.

ScopedCycleException when this invocation would break the single parent rule. IllegalArgumentException when the caller is a schedulable and no non-null logic value was supplied to the memory area's constructor.

MemoryAccessError when caller is a non-heap schedulable and this memory area's logic value is allocated in heap memory.

joinAndEnter(javax.realtime.HighResolutionTime<?>)

In the error-free case, joinAndEnter combines join(); enter(); such that no enter() from another schedulable can intervene between the two method invocations. The resulting method will wait for the reference count on this ScopedMemory

⁶⁷Section 5.3.2.2.2 ⁶⁸Section 8.4.2.1.2

⁶⁹Section 14.2.3.3

 $^{^{70}}$ Section 14.2.3.6

to reach zero, or for the current time to reach the designated time, then enter the ScopedMemory and execute the run method from Runnable object passed to the constructor. When no instance of Runnable was passed to the memory area's constructor, the method throws IllegalArgumentException immediately. *

When multiple threads are waiting in joinAndEnter family methods for a memory area, at most *one* of them will be released each time the reference count goes to zero.

Since the time is expressed as a HighResolutionTime⁷¹, this method has an accurate timer with nanosecond granularity. The actual resolution of the timer and even the quantity it measures depends on the clock associated with time. The delay time may be relative or absolute. When relative, then the calling thread is blocked for at most the amount of time given by time, and measured by its associated clock. When absolute, then the time delay is until the indicated value is reached by the clock. When the given absolute time is less than or equal to the current value of the clock, the call to joinAndEnter behaves effectively like enter⁷².

Note that expiration of time may cause control to enter the memory area before its reference count has gone to zero.

```
Signature
```

```
public
void joinAndEnter(javax.realtime.HighResolutionTime<?> time)
throws InterruptedException
```

Parameters

time The time that bounds the wait.

Throws

ThrowBoundaryError Thrown when the JVM needs to propagate an exception allocated in this scope to (or through) the memory area of the caller. Storing a reference to that exception would cause an IllegalAssignmentError⁷³, so the JVM cannot be permitted to deliver the exception. The ThrowBoundary-Error⁷⁴ is allocated in the current allocation context and contains information about the exception it replaces.

InterruptedException When this schedulable is interrupted by RealtimeThread.interrupt()⁷⁵ or AsynchronouslyInterruptedException.fire()⁷⁶ while waiting for the reference count to go to zero.

```
<sup>71</sup>Section 9.4.1.2

<sup>72</sup>Section 11.4.2.5.2

<sup>73</sup>Section 14.2.3.3

<sup>74</sup>Section 14.2.3.6

<sup>75</sup>Section 5.3.2.2.2

<sup>76</sup>Section 8.4.2.1.2
```

IllegalThreadStateException when the caller is a Java thread, or when this method is invoked during finalization of objects in scoped memory and entering this scoped memory area would force deletion of the SO that triggered finalization. This would include the scope containing the SO, and the scope (if any) containing the scope containing the SO.

ScopedCycleException when the caller is a schedulable and this invocation would break the single parent rule.

IllegalArgumentException when the caller is a schedulable, and time is null or no non-null logic value was supplied to the memory area's constructor.

UnsupportedOperationException when the wait operation is not supported using the clock associated with time.

MemoryAccessError when caller is a no-heap schedulable and this memory area's logic value is allocated in heap memory.

joinAndEnter(Runnable)

In the error-free case, joinAndEnter combines join(); enter(); such that no enter() from another schedulable can intervene between the two method invocations. The resulting method will wait for the reference count on this ScopedMemory to reach zero, then enter the ScopedMemory and execute the run method from logic

When logic is null, throw IllegalArgumentException immediately.

When multiple threads are waiting in joinAndEnter family methods for a memory area, at most *one* of them will be released each time the reference count goes to zero.

Note that although joinAndEnter guarantees that the reference count is zero when the schedulable is released for entry, it does not guarantee that the reference count will remain one for any length of time. A subsequent enter could raise the reference count to two.

```
Signature
```

```
public
void joinAndEnter(Runnable logic)
throws InterruptedException
```

logic The Runnable object which contains the code to execute.

Throws

InterruptedException When this schedulable is interrupted by RealtimeThread.interrupt() 77

 $^{^{77}}$ Section 5.3.2.2.2

or AsynchronouslyInterruptedException.fire() 78 while waiting for the reference count to go to zero.

IllegalThreadStateException when the caller is a Java thread, or when this method is invoked during finalization of objects in scoped memory and entering this scoped memory area would force deletion of the SO that triggered finalization. This would include the scope containing the SO, and the scope (if any) containing the scope containing the SO.

ThrowBoundaryError Thrown when the JVM needs to propagate an exception allocated in this scope to (or through) the memory area of the caller. Storing a reference to that exception would cause an IllegalAssignmentError⁷⁹, so the JVM cannot be permitted to deliver the exception. The ThrowBoundary-Error⁸⁰ is allocated in the current allocation context and contains information about the exception it replaces.

ScopedCycleException when this invocation would break the single parent rule. IllegalArgumentException when the caller is a schedulable and logic is null.

joinAndEnter(java.util.function.Supplier<T>)

Same as joinAndEnter(Runnable)⁸¹ except that the executed method is called get and an object is returned.

```
public
    T joinAndEnter(java.util.function.Supplier<T> logic)
Parameters
    logic the object who's get method will be executed.
Returns
    a result from the computation.
```

joinAndEnter(BooleanSupplier)

Same as joinAndEnter(Runnable)⁸² except that the executed method is called get and a boolean is returned.

```
<sup>78</sup>Section 8.4.2.1.2

<sup>79</sup>Section 14.2.3.3

<sup>80</sup>Section 14.2.3.6

<sup>81</sup>Section 11.4.2.5.2

<sup>82</sup>Section 11.4.2.5.2
```

```
Signature

public
boolean joinAndEnter(BooleanSupplier logic)

Parameters
logic the object who's get method will be executed.

Returns
a result from the computation.
```

joinAndEnter(IntSupplier)

Same as $joinAndEnter(Runnable)^{83}$ except that the executed method is called get and an int is returned.

```
public int joinAndEnter(IntSupplier logic)

Parameters

logic the object who's get method will be executed.

Returns

a result from the computation.
```

joinAndEnter(LongSupplier)

⁸⁴Section 11.4.2.5.2

Same as $joinAndEnter(Runnable)^{84}$ except that the executed method is called get and a long is returned.

```
Signature

public
long joinAndEnter(LongSupplier logic)

Parameters
logic the object who's get method will be executed.

Returns
a result from the computation.

83Section 11.4.2.5.2
```

^{2.0 (}Draft 20)

joinAndEnter(DoubleSupplier)

Same as joinAndEnter(Runnable)⁸⁵ except that the executed method is called get and a double is returned.

```
public double joinAndEnter(DoubleSupplier logic)

Parameters

logic the object who's get method will be executed.

Returns

a result from the computation.
```

joinAndEnter(Runnable, javax.realtime.HighResolutionTime<?>)

In the error-free case, joinAndEnter combines join(); enter(); such that no enter() from another schedulable can intervene between the two method invocations. The resulting method will wait for the reference count on this ScopedMemory to reach zero, or for the current time to reach the designated time, then enter the ScopedMemory and execute the run method from logic.

Since the time is expressed as a HighResolutionTime⁸⁶, this method is an accurate timer with nanosecond granularity. The actual resolution of the timer and even the quantity it measures depends on the clock associated with time. The delay time may be relative or absolute. When relative, then the delay is the amount of time given by time, and measured by its associated clock. When absolute, then the delay is until the indicated value is reached by the clock. When the given absolute time is less than or equal to the current value of the clock, the call to joinAndEnter behaves effectively like enter(Runnable)⁸⁷.

Throws IllegalArgumentException immediately when logic is null.

When multiple threads are waiting in joinAndEnter family methods for a memory area, at most *one* of them will be released each time the reference count goes to zero.

Note that expiration of time may cause control to enter the memory area before its reference count has gone to zero.

⁸⁵Section 11.4.2.5.2

⁸⁶Section 9.4.1.2

⁸⁷Section 11.4.2.5.2

```
public
    public
    void joinAndEnter(Runnable logic,
        javax.realtime.HighResolutionTime<?> time)
        throws InterruptedException

Parameters
    logic The Runnable object which contains the code to execute.
```

time The time that bounds the wait.

Throws

InterruptedException When this schedulable is interrupted by RealtimeThread.interrupt()⁸⁸ or AsynchronouslyInterruptedException.fire()⁸⁹ while waiting for the reference count to go to zero.

IllegalThreadStateException when the caller is a Java thread, or when this method is invoked during finalization of objects in scoped memory and entering this scoped memory area would force deletion of the SO that triggered finalization. This would include the scope containing the SO, and the scope (if any) containing the scope containing the SO.

ThrowBoundaryError Thrown when the JVM needs to propagate an exception allocated in this scope to (or through) the memory area of the caller. Storing a reference to that exception would cause an IllegalAssignmentError⁹⁰, so the JVM cannot be permitted to deliver the exception. The ThrowBoundary-Error⁹¹ is allocated in the current allocation context and contains information about the exception it replaces.

ScopedCycleException when the caller is a schedulable and this invocation would break the single parent rule.

IllegalArgumentException when the caller is a schedulable and time or logic is null.

UnsupportedOperationException when the wait operation is not supported using the clock associated with time.

joinAndEnter(java.util.function.Supplier<P>, javax.realtime.HighResolu

Same as joinAndEnter(Runnable, HighResolutionTime) 92 except that the ex-

```
<sup>88</sup>Section 5.3.2.2.2
<sup>89</sup>Section 8.4.2.1.2
```

⁹⁰Section 14.2.3.3

⁹¹Section 14.2.3.6

⁹²Section 11.4.2.5.2

ecuted method is called get and an object is returned.

```
public
    p joinAndEnter(java.util.function.Supplier<P> logic,
    javax.realtime.HighResolutionTime<?> time)

Parameters
    logic the object who's get method will be executed.

Returns
    a result from the computation.
```

joinAndEnter(BooleanSupplier, javax.realtime.HighResolutionTime<?>)

Same as joinAndEnter(Runnable, HighResolutionTime)⁹³ except that the executed method is called get and a boolean is returned.

```
public boolean joinAndEnter(BooleanSupplier logic, javax.realtime.HighResolutionTime<?> time)

Parameters

logic the object who's get method will be executed.

Returns

a result from the computation.
```

joinAndEnter(IntSupplier, javax.realtime.HighResolutionTime<?>)

Same as joinAndEnter(Runnable, HighResolutionTime)⁹⁴ except that the executed method is called get and an int is returned.

```
Signature
public

93Section 11.4.2.5.2
94Section 11.4.2.5.2
```

```
int joinAndEnter(IntSupplier logic,
    javax.realtime.HighResolutionTime<?> time)
Parameters
    logic the object who's get method will be executed.
Returns
    a result from the computation.
```

joinAndEnter(LongSupplier, javax.realtime.HighResolutionTime<?>)

Same as joinAndEnter(Runnable, HighResolutionTime)⁹⁵ except that the executed method is called get and a long is returned.

```
public
long joinAndEnter(LongSupplier logic,
javax.realtime.HighResolutionTime<?> time)

Parameters
logic the object who's get method will be executed.

Returns
a result from the computation.
```

joinAndEnter(DoubleSupplier, javax.realtime.HighResolutionTime<?>)

Same as joinAndEnter(Runnable, HighResolutionTime)⁹⁶ except that the executed method is called get and a double is returned.

```
public double joinAndEnter(DoubleSupplier logic, javax.realtime.HighResolutionTime<?> time)

Parameters

logic the object who's get method will be executed.

Returns

a result from the computation.

95 Section 11.4.2.5.2

96 Section 11.4.2.5.2
```

getParent

Return a reference to this scopes parent scope (e.g., its parent in the single-parent-rule tree).

Available since RTSJ 2.0

```
Signature
    public
    javax.realtime.MemoryArea getParent()
```

Returns

a reference to the next outer scoped memory region on the caller's scope stack.

- When there is no outer scoped memory and the primordial parent is heap memory, return a reference to this.
- When there is no outer scoped memory and the primordial parent is immortal, or when **this** is unreferenced and unpinned, return **null**

Problem. The single-parent tree is RTT-independent except for the primordial scope. The type of the primordial scope is RTT-dependent. What should we do about that? When called from a RTT that has entered this, the above rules make some sense, but what if the caller has not even entered the scope, should we throw an exception? Or just return null? I think the right solution is to return this whatever the type of the primordial scope. The app can then know that null means the scope is not pinned and not referenced, and this means the parent is either heap or immortal. At that point, the app can learn what it wants to know by just finding what memory area contains the scope object.

visitScopedChildren(javax.realtime.ChildScopeVisitor < R >)

@inheritDoc

```
Signature
```

```
public
R visitScopedChildren(javax.realtime.ChildScopeVisitor<R>
visitor)
```

Throws

IllegalArgumentException when visitor is null.

```
newArray(java.lang.Class<?>, int)
```

2.0 (Draft 20)

Allocate an array of the given type in this memory area. This method may be concurrently used by multiple threads.

```
public java.lang.Object newArray(java.lang.Class<?> type, int number)

Parameters type @inheritDoc number @inheritDoc

Throws

IllegalArgumentException @inheritDoc

OutOfMemoryError @inheritDoc

IllegalThreadStateException when the caller is a Java thread.

InaccessibleAreaException when the memory area is not in the schedulable's scope stack.
```

newInstance(java.lang.Class<T>)

Returns

@inheritDoc

Allocate an object in this memory area. This method may be concurrently used by multiple threads.

```
public
T newInstance(java.lang.Class<T> type)
throws IllegalAccessException, InstantiationException

Parameters
type @inheritDoc

Throws

IllegalAccessException @inheritDoc
IllegalArgumentException @inheritDoc
ExceptionInInitializerError @inheritDoc
OutOfMemoryError @inheritDoc
InstantiationException @inheritDoc
InstantiationException @inheritDoc
IllegalThreadStateException when the caller is a Java thread.
InaccessibleAreaException when the memory area is not in the schedulable's scope stack.
```

Returns

@inheritDoc

newInstance(java.lang.reflect.Constructor<T>, java.lang.Object[])

Allocate an object in this memory area. This method may be concurrently used by multiple threads.

```
Signature
     public
     T newInstance(java.lang.reflect.Constructor<T> c,
     java.lang.Object[] args)
     throws IllegalAccessException, InstantiationException,
     InvocationTargetException
Parameters
     c T@inheritDoc
     args @inheritDoc
Throws
     IllegalAccessException @inheritDoc
     InstantiationException @inheritDoc
     OutOfMemoryError @inheritDoc
     IllegalArgumentException @inheritDoc
     IllegalThreadStateException when the caller is a Java thread.
     Invocation TargetException @inheritDoc
     InaccessibleAreaException when the memory area is not in the schedulable's
     scope stack.
Returns
     @inheritDoc
```

setPortal(Object)

Sets the *portal* object of the memory area represented by this instance of Scoped-Memory to the given object. The object must have been allocated in this Scoped-Memory instance.

```
Signature public
```

void setPortal(Object object)

Parameters

object The object which will become the portal for this. When null the previous portal object remains the portal object for this or when there was no previous portal object then there is still no portal object for this.

Throws

IllegalThreadStateException when the caller is a Java Thread.

IllegalAssignmentError when the caller is a schedulable, and object is not allocated in this scoped memory instance and not null.

InaccessibleAreaException when the caller is a schedulable, this memory area is not in the caller's scope stack and object is not null.

toString

Returns a user-friendly representation of this ScopedMemory of the form "Scoped-Memory#<num>" where <num> is a number that uniquely identifies this scoped memory area.

```
Signature

public

java.lang.String toString()

Returns

The string representation
```

11.4.2.6 SizeEstimator

This class maintains an estimate of the amount of memory required to store a set of objects.

SizeEstimator is a floor on the amount of memory that should be allocated. Many objects allocate other objects when they are constructed. SizeEstimator only estimates the memory requirement of the object itself, it does not include memory required for any objects allocated at construction time. When the instance itself is allocated in several parts (when for instance the object and its monitor are separate), the size estimate shall include the sum of the sizes of all the parts that are allocated from the same memory area as the instance. Alignment considerations, and possibly other order-dependent issues may cause the allocator to leave a small amount of unusable space, consequently the size estimate cannot be seen as more than a close estimate.

See Section MemoryArea.MemoryArea(SizeEstimator)

See Section LTMemory.LTMemory(SizeEstimator)

Inheritance

```
java.lang.Object
javax.realtime.SizeEstimator
```

11.4.2.6.1 Constructors

SizeEstimator

```
Signature

public
    SizeEstimator()
```

11.4.2.6.2 Methods

reserve(java.lang.Class, int)

Take into account additional number instances of Class c when estimating the size of the MemoryArea⁹⁷.

```
Signature \\ \text{public} \\ \text{void reserve(java.lang.Class c, int number)} \\ Parameters \\ c \text{ The class to take into account.} \\ number \text{ The number of instances of c to estimate.} \\ \hline \hline \\ ^{97}\text{Section } 11.4.2.3
```

Throws

IllegalArgumentException when c is null.

reserve(SizeEstimator, int)

Take into account additional number instances of SizeEstimator size when estimating the size of the MemoryArea⁹⁸.

```
Signature
     public
     void reserve(SizeEstimator estimator, int number)
     estimator The given instance of SizeEstimator<sup>99</sup>.
     number The number of times to reserve the size denoted by estimator.
Throws
```

IllegalArgumentException when estimator is null.

reserve(SizeEstimator)

Take into account an additional instance of SizeEstimator size when estimating the size of the MemoryArea¹⁰⁰.

```
Signature
     public
     void reserve(SizeEstimator size)
     size The given instance of SizeEstimator.
Throws
     IllegalArgumentException when size is null.
```

reserveArray(int)

Take into account an additional instance of an array of length reference values when estimating the size of the MemoryArea¹⁰¹.

```
<sup>98</sup>Section 11.4.2.3
 <sup>99</sup>Section 11.4.2.6
<sup>100</sup>Section 11.4.2.3
^{101}Section 11.4.2.3
```

Available since RTSJ 1.0.1

```
public
void reserveArray(int length)

Parameters
length The number of entries in the array.

Throws
```

IllegalArgumentException when length is negative.

reserveArray(int, java.lang.Class)

Take into account an additional instance of an array of length primitive values when estimating the size of the MemoryArea¹⁰².

Class values for the primitive types are available from the corresponding class types; e.g., Byte.TYPE, Integer.TYPE, and Short.TYPE.

Available since RTSJ 1.0.1

```
Signature
    public
    void reserveArray(int length, java.lang.Class type)
```

Parameters

length The number of entries in the array.

type The class representing a primitive type. The reservation will leave room for an array of length of the primitive type corresponding to type.

Throws

IllegalArgumentException when length is negative, or type does not represent a primitive type.

getEstimate

Gets an estimate of the number of bytes needed to store all the objects reserved.

$\frac{Signature}{^{102}Section \ 11.4.2.3}$

public
long getEstimate()

Returns

The estimated size in bytes.

11.5 Package javax.realtime.memory

11.5.1 Interfaces

11.5.1.1 PhysicalMemoryCharacteristic

A tagging interface used to identify physical memory characteristics. Applications can give names to regions of memory that are described by PhysicalMemoryRegion¹⁰³. The names are defined by creating instances of this interface. For example, final static PhysicalMemoryCharacteristic STATIC_RAM = ...;

Available since RTSJ 2.0

11.5.1.2 VirtualMemoryCharacteristic

A tagging interface used to identify virtual memory characteristics. The PhysicalMemoryFactory defines static public objects that implement this interface. Each instant represent a particular virtual memory characteristics supported by the hosting machine.

For example, public final static VirtualMemoryCharacteristic PERMANENTLY_RESIDENT Available since RTSJ 2.0

11.5.1.2.1 Methods

apply(long, long)

Apply the Characteristic to a given memory area.

```
Signature

public

void apply(long base, long size)

Parameters

103 Section 11.5.3.3
```

base is the physical start of the memory size is the length of the memory in bytes.

unapply(long, long)

Unapply the Characteristic to a given memory area.

```
Signature

public

void unapply(long base, long size)

Parameters

base is the physical start of the memory

size is the length of the memory in bytes.
```

11.5.2 Enumerations

11.5.2.1 Physical Memory Selector. Caching Behavior

Marker for standard caching behaviors. Not all need be supported. For example, a VM running in Kernel mode might only support DISABLED.

Inheritance

```
java.lang.Object
java.lang.Enum
javax.realtime.memory.PhysicalMemorySelector.CachingBehavior
```

11.5.2.1.1 Enumeration Constants

DISABLED

```
public static final DISABLED
```

WRITE_THROUGH

```
public static final WRITE_THROUGH
```

WRITE_BACK

public static final WRITE_BACK

11.5.2.1.2 Methods

values

```
Signature
```

```
public static
javax.realtime.memory.PhysicalMemorySelector.CachingBehavior[]
values()
```

valueOf(String)

Signature

```
public static
javax.realtime.memory.PhysicalMemorySelector.CachingBehavior
valueOf(String name)
```

11.5.2.2 Physical Memory Selector. Paging Behavior

Marker for standard paging behaviors. Not all need be supported. For example, a VM running in Kernel mode might only support DIRECT.

Inheritance

```
java.lang.Object
java.lang.Enum
javax.realtime.memory.PhysicalMemorySelector.PagingBehavior
```

11.5.2.2.1 Enumeration Constants

DIRECT

```
public static final DIRECT
```

FIXED

```
public static final FIXED
```

SWAPPABLE

public static final SWAPPABLE

11.5.2.2.2 Methods

values

```
Signature
```

```
public static
javax.realtime.memory.PhysicalMemorySelector.PagingBehavior[]
values()
```

valueOf(String)

Signature

```
public static
javax.realtime.memory.PhysicalMemorySelector.PagingBehavior
valueOf(String name)
```

11.5.3 Classes

11.5.3.1 LTMemory

LTMemory represents a memory area guaranteed by the system to have linear time allocation when memory consumption from the memory area is less than the memory area's *initial* size. Execution time for allocation is allowed to vary when memory consumption is between the initial size and the maximum size for the area. Furthermore, the underlying system is not required to guarantee that memory between initial and maximum will always be available.

The memory area described by a LTMemory instance does not exist in the Java heap, and is not subject to garbage collection. Thus, it is safe to use a LTMemory object as the initial memory area associated with a NoHeapRealtimeThread¹⁰⁴, or to enter the memory area using the ScopedMemory.enter¹⁰⁵ method within a NoHeapRealtimeThread¹⁰⁶.

Enough memory must be committed by the completion of the constructor to satisfy the initial memory requirement. (Committed means that this memory must always be available for allocation). The initial memory allocation must behave, with respect to successful allocation, as if it were contiguous; i.e., a correct implementation must guarantee that any sequence of object allocations that could ever succeed without exceeding a specified initial memory size will always succeed without exceeding that initial memory size and succeed for any instance of LTMemory with that initial memory size. (Note: to ensure that all requested memory is available set initial and maximum to the same value) Methods from LTMemory should be overridden only by methods that use super.

See Section MemoryArea

See Section ScopedMemory

See Section RealtimeThread

See Section NoHeapRealtimeThread

Available since RTSJ 2.0 in this package

Inheritance

java.lang.Object javax.realtime.MemoryArea javax.realtime.ScopedMemory javax.realtime.memory.LTMemory

 $^{^{104}}$ Section 15.3.3.3

 $^{^{105}}$ Section 11.4.2.5.2

 $^{^{106}}$ Section 15.3.3.3

11.5.3.1.1 Constructors

LTMemory(long, long)

Create an LTMemory of the given size.

Signature

```
public
```

LTMemory(long initial, long maximum)

Parameters 1

initial The size in bytes of the memory to allocate for this area. This memory must be committed before the completion of the constructor.

maximum The size in bytes of the memory to allocate for this area.

Throws

IllegalArgumentException when initial is greater than maximum, or when initial or maximum is less than zero.

OutOfMemoryError when there is insufficient memory for the LTMemory object or for the backing memory.

LTMemory(long, long, Runnable)

Create an LTMemory of the given size.

Signature

```
public
```

LTMemory(long initial, long maximum, Runnable logic)

Parameters

initial The size in bytes of the memory to allocate for this area. This memory must be committed before the completion of the constructor.

maximum The size in bytes of the memory to allocate for this area.

logic The run() of the given Runnable will be executed using this as its initial memory area. When logic is null, this constructor is equivalent to LTMemory(long initial, long maximum)¹⁰⁷.

Throws

IllegalArgumentException when initial is greater than maximum, or when initial or maximum is less than zero.

OutOfMemoryError when there is insufficient memory for the LTMemory object or for the backing memory.

IllegalAssignmentError when storing logic in this would violate the assignment rules.

LTMemory(SizeEstimator, SizeEstimator)

Create an LTMemory of the given size.

Signature

public

LTMemory(SizeEstimator initial, SizeEstimator maximum)

Parameters

initial An instance of SizeEstimator¹⁰⁸ used to give an estimate of the initial size. This memory must be committed before the completion of the constructor.

maximum An instance of SizeEstimator¹⁰⁹ used to give an estimate for the maximum bytes to allocate for this area.

Throws

IllegalArgumentException when initial is null, maximum is null, initial.getEstimate() is greater than maximum.getEstimate(), or when initial.getEstimate() is less than zero.

OutOfMemoryError when there is insufficient memory for the LTMemory object or for the backing memory.

LTMemory(SizeEstimator, SizeEstimator, Runnable)

¹⁰⁷Section 11.5.3.1.1

¹⁰⁸Section 11.4.2.6

 $^{^{109}}$ Section 11.4.2.6

Create an LTMemory of the given size.

Signature

public

LTMemory(SizeEstimator initial, SizeEstimator maximum, Runnable logic)

initial An instance of SizeEstimator¹¹⁰ used to give an estimate of the initial size. This memory must be committed before the completion of the constructor.

maximum An instance of SizeEstimator¹¹¹ used to give an estimate for the maximum bytes to allocate for this area.

logic The run() of the given Runnable will be executed using this as its initial memory area. When logic is null, this constructor is equivalent to LTMemory(SizeEstimator initial, SizeEstimator maximum)¹¹².

Throws

IllegalArgumentException when initial is null, maximum is null, initial.getEstimate() is greater than maximum.getEstimate(), or when initial.getEstimate() is less than zero.

OutOfMemoryError when there is insufficient memory for the LTMemory object or for the backing memory.

IllegalAssignmentError when storing logic in this would violate the assignment rules.

LTMemory(long)

Create an LTMemory of the given size. This constructor is equivalent to LTMemory(size, size)

Available since RTSJ 1.0.1

Signature

public

 $^{^{110}}$ Section 11.4.2.6

¹¹¹Section 11.4.2.6

¹¹²Section 11.5.3.1.1

LTMemory(long size)

Parameters

size The size in bytes of the memory to allocate for this area. This memory must be committed before the completion of the constructor.

Throws

IllegalArgumentException when size is less than zero.

OutOfMemoryError when there is insufficient memory for the LTMemory object or for the backing memory.

LTMemory(long, Runnable)

Create an LTMemory of the given size. This constructor is equivalent to LTMemory(size, size, logic).

Available since RTSJ 1.0.1

Signature

public

LTMemory(long size, Runnable logic)

Parameters

size The size in bytes of the memory to allocate for this area. This memory must be committed before the completion of the constructor.

logic The run() of the given Runnable will be executed using this as its initial memory area. When logic is null, this constructor is equivalent to LTMemory(long size)¹¹³.

Throws

IllegalArgumentException when size is less than zero.

OutOfMemoryError when there is insufficient memory for the LTMemory object or for the backing memory.

IllegalAssignmentError when storing logic in this would violate the assignment rules.

 $^{^{113}}$ Section 11.5.3.1.1

LTMemory(SizeEstimator)

Create an LTMemory of the given size. This constructor is equivalent to LTMemory(size, size).

Available since RTSJ 1.0.1

Signature

```
public
  LTMemory(SizeEstimator size)
```

Parameters

size An instance of SizeEstimator¹¹⁴ used to give an estimate of the initial size. This memory must be committed before the completion of the constructor.

Throws

IllegalArgumentException when size is null, or size.getEstimate() is less than zero.

OutOfMemoryError when there is insufficient memory for the LTMemory object or for the backing memory.

LTMemory(SizeEstimator, Runnable)

Create an LTMemory of the given size.

Available since RTSJ 1.0.1

Signature

```
public
```

LTMemory(SizeEstimator size, Runnable logic)

Parameters

¹¹⁴Section 11.4.2.6

size An instance of SizeEstimator¹¹⁵ used to give an estimate of the initial size. This memory must be committed before the completion of the constructor.

logic The run() of the given Runnable will be executed using this as its initial memory area. When logic is null, this constructor is equivalent to LTMemory(SizeEstimator initial)¹¹⁶.

Throws

IllegalArgumentException when size is null, or size.getEstimate() is less than zero.

OutOfMemoryError when there is insufficient memory for the LTMemory object or for the backing memory.

IllegalAssignmentError when storing logic in this would violate the assignment rules.

11.5.3.1.2 Methods

toString

Create a string representation of this object. The string is of the form (LTMemory) Scoped memory # num where num uniquely identifies the LTMemory area.

```
Signature
    public
    java.lang.String toString()
```

Returns

A string representing the value of this.

11.5.3.2 PhysicalMemoryFactory

Both associate memory ranges, in the form of ${\tt PhysicalMemoryRegion}^{117}$ instances

```
<sup>115</sup>Section 11.4.2.6

<sup>116</sup>Section 11.5.3.1.1

<sup>117</sup>Section 11.5.3.3
```

with physical memory characteristics in the form of PhysicalMemoryCharacteristic¹¹⁸ instances, and create memory areas in those modules.

Each physical memory module can have more than one physical memory characteristic. A physical memory characteristic can apply to many physical memory modules. The range of physical addresses of modules shall not overlap. A memory that spans more than one physical memory module may not be create.

The PhysicalMemoryFactory determines the physical addresses from the modules and keeps a relation between instances of PhysicalMemoryRegion and Physical Memory Addresses. The range of physical addresses of modules shall not overlap. A created memory are may not span more than one physical memory module. To find a memory range that supports PMC A and PMC B uses set intersection modules(A) \$

cap\$ modules(B)

Available since RTSJ 2.0

Inheritance

java.lang.Object javax.realtime.memory.PhysicalMemoryFactory

11.5.3.2.1 Constructors

PhysicalMemoryFactory

```
Signature

public

PhysicalMemoryFactory()
```

11.5.3.2.2 Methods

¹¹⁸Section 11.5.1.1

associate(PhysicalMemoryCharacteristic, PhysicalMemoryRegion)

Associates a programmer-defined name with a physical address range.

Signature

public static
void associate(PhysicalMemoryCharacteristic name,
PhysicalMemoryRegion module)
throws IllegalArgumentException, IllegalStateException

Parameters

name is the physical memory characteristic. e.g STATIC_RAM. module is the object representing a range of contiguous physical addresses

Throws

IllegalArgumentException when either name or module is null IllegalStateException when module overlaps a previously associated PhysicalMemoryRegion instance.

associate (javax.real time.memory. Physical Memory Characteristic [], Physical Memory Region)

Associates am array of programmer-defined names with a physical address range.

Signature

public static
void
associate(javax.realtime.memory.PhysicalMemoryCharacteristic[]
names, PhysicalMemoryRegion module)
throws IllegalArgumentException, IllegalStateException

Parameters

names is the array of physical memory characteristics. e.g STATIC_RAM. module is the object representing a range of contiguous physical addresses

Throws

IllegalArgumentException when either names or module is null IllegalStateException when module overlaps a previously associated PhysicalMemoryRegion instance.

associate(PhysicalMemoryCharacteristic, javax.realtime.memory.Physical

Associates a programmer-defined name with an array of physical address ranges.

Signature

```
public static
void associate(PhysicalMemoryCharacteristic name,
javax.realtime.memory.PhysicalMemoryRegion[] modules)
throws IllegalArgumentException, IllegalStateException
```

Parameters

name is the physical memory characteristic. e.g STATIC_RAM.

modules is an array of objects each representing a range of contiguous physical addresses

Throws

IllegalArgumentException when either name or modules is null IllegalStateException when module overlaps a previously associated PhysicalMemoryRegion instance.

createStackedMemory(javax.realtime.memory.PhysicalMemorySelector[] long, long, Runnable)

Instantiate a StackedMemory¹¹⁹ object in a PhysicalMemoryRegion¹²⁰ matching the PhysicalMemoryCharacteristic¹²¹ in selector and then with virtual memory parameters of selector applied.

Signature

```
public
javax.realtime.memory.StackedMemory createStackedMem-
ory(javax.realtime.memory.PhysicalMemorySelector[] selector,
long scopeSize, long backingSize, Runnable logic)
throws SecurityException, SizeOutOfBoundsException,
UnsupportedPhysicalMemoryException, MemoryTypeConflictException,
IllegalArgumentException
```

Parameters

¹¹⁹Section 11.5.3.6 ¹²⁰Section 11.5.3.3

¹²¹Section 11.5.1.1

selector to use to choose the memory module and set the virtual mapping scopeSize is the size of the scope to be created

backingSize is the size of the backing store to take out of the selected module logic the logic to execute on entry (may be null

Throws

SecurityException when the application does not have permissions to access physical memory or the given range of memory.

SizeOutOfBoundsException when the implementation detects that size extends beyond a physically addressable memory module.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryCharacteristic has been registered with this PhysicalMemoryFactory.

Memory Type Conflict Exception when the specified base does not point to memory that matches the requested type, or when type specifies incompatible memory attributes.

 ${\it IllegalArgumentException}$ when scopeSize or backingSize is less than zero.

Returns

the new memory area

createPinnableMemory(javax.realtime.memory.PhysicalMemorySelector[], long, Runnable)

Instantiate a PinnableMemory¹²³ object in a PhysicalMemoryRegion¹²⁴ matching the PhysicalMemoryCharacteristic¹²⁵ in selector and then with virtual memory parameters of selector applied.

```
Signature
```

```
public
javax.realtime.memory.PinnableMemory createPinnableMem-
ory(javax.realtime.memory.PhysicalMemorySelector[] selector,
long size, Runnable logic)
throws SecurityException, SizeOutOfBoundsException,
UnsupportedPhysicalMemoryException, MemoryTypeConflictException,
IllegalArgumentException
```

Parameters

```
122 Section 11.5.1.1

123 Section 11.5.3.5

124 Section 11.5.3.3

125 Section 11.5.1.1
```

selector to use to choose the memory module and set the virtual mapping size is the size of memory to be taken out of the selected module logic to execute on entry (may be null

Throws

SecurityException when the application does not have permissions to access physical memory or the given range of memory.

SizeOutOfBoundsException when the implementation detects that size extends beyond a physically addressable memory module.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryCharacteristic has been registered with this PhysicalMemoryFactory.

MemoryTypeConflictException when the specified base does not point to memory that matches the requested type, or when type specifies incompatible memory attributes.

IllegalArgumentException when size is less than zero.

Returns

the new memory area

createImmortalMemory(javax.realtime.memory.PhysicalMemorySelectorlong, Runnable)

Instantiate a ImmortalMemory¹²⁷ object in a PhysicalMemoryRegion¹²⁸ matching the PhysicalMemoryCharacteristic¹²⁹ in selector and then with virtual memory parameters of selector applied.

Signature

```
public
javax.realtime.ImmortalMemory createImmortalMem-
ory(javax.realtime.memory.PhysicalMemorySelector[] selector,
long size, Runnable logic)
throws SecurityException, SizeOutOfBoundsException,
UnsupportedPhysicalMemoryException, MemoryTypeConflictException,
IllegalArgumentException
```


selector to use to choose the memory module and set the virtual mapping

```
<sup>126</sup>Section 11.5.1.1

<sup>127</sup>Section 11.4.2.2

<sup>128</sup>Section 11.5.3.3

<sup>129</sup>Section 11.5.1.1
```

size is the size of memory to be taken out of the selected module logic the logic to execute on entry (may be null

Throws

SecurityException when the application does not have permissions to access physical memory or the given range of memory.

SizeOutOfBoundsException when the implementation detects that size extends beyond a physically addressable memory module.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryCharacteristic¹³⁰ has been registered with this PhysicalMemoryFactory.

Memory Type Conflict Exception when the specified base does not point to memory that matches the requested type, or when type specifies incompatible memory attributes.

IllegalArgumentException when size is less than zero.

Returns

the new memory area

11.5.3.3 Physical Memory Region

Enable an application to define a range of physical memory addresses.

Available since RTSJ 2.0

Inheritance

java.lang.Object javax.realtime.memory.PhysicalMemoryRegion

11.5.3.3.1 Constructors

PhysicalMemoryRegion(long, long)

Creates an instance representing a range of contiguous physical memory.

Signature	
¹³⁰ Section 11.5.1.1	

```
public
   PhysicalMemoryRegion(long base, long length)
```

Parameters

base is a physical address length is size of contiguous memory from that base

Throws

IllegalArgumentException when length is less than or equal to 0, or when base is less than 0 or when this module overlaps with another memory module. SizeOutOfBounds when base + length is greater than the physical address range of the processor

11.5.3.3.2 Methods

getBase

Gets the base address of the contiguous memory represented by this.

```
Signature

public
long getBase()

Returns

the base address
```

getLength

Gets the length of the contiguous memory represented by this.

```
Signature

public
long getLength()

Returns
the length
```

11.5.3.4 PhysicalMemorySelector

Provides both characteristics both for physical memory, used to select a memory range from a memory module, and for virtual memory to be used for setting the characteristics of the mapped pages.

Available since RTSJ 2.0

Inheritance

java.lang.Object javax.realtime.memory.PhysicalMemorySelector

11.5.3.4.1 Constructors

PhysicalMemorySelector (javax.realtime.memory.PhysicalMemoryCharacterijavax.realtime.memory.VirtualMemoryCharacteristic[], PhysicalMemorySelector.CachingBehavior, PhysicalMemorySelector.PagingBehavior)

Signature

public

 $Physical \texttt{MemorySelector}(javax.real time.memory.Physical \texttt{MemoryCharacteristic[]} \ pmc, \ javax.real time.physical \texttt{MemoryCharacteristic[]} \ pmc, \ pmc,$

11.5.3.4.2 Methods

getSupportedCachingBehavior

Get the caching behaviors that are supported by this JVM

Signature

```
public static
  javax.realtime.memory.PhysicalMemorySelector.CachingBehavior[]
  getSupportedCachingBehavior()
Returns
  an array of the supported caching behaviors.
```

getSupportedPagingBehavior

Get the paging behaviors that are supported by this JVM

```
Signature

public static
 javax.realtime.memory.PhysicalMemorySelector.PagingBehavior[]
 getSupportedPagingBehavior()

Returns

an array of the supported paging behaviors.
```

getPhysicalMemoryCharacteristics

A getter for the PhysicalMemoryCharacteristic list to be requested

```
Signature

public
 javax.realtime.memory.PhysicalMemoryCharacteristic[]
 getPhysicalMemoryCharacteristics()

Returns

the PhysicalMemoryCharacteristic list
```

getVirtualMemoryCharateristics

A getter for the VirtualMemoryCharacteristic list to be requested

```
Signature
    public
    javax.realtime.memory.VirtualMemoryCharacteristic[]
    getVirtualMemoryCharateristics()
Returns
```

the VirtualMemoryCharacteristic list

getCachingBehavior

A getter for the CachingBehavior to be requested

```
Signature

public
 javax.realtime.memory.PhysicalMemorySelector.CachingBehavior
 getCachingBehavior()

Returns
 the CachingBehavior
```

getPagingPagingBehavior

A getter for the PagingBehavior to be requested

```
Signature

public
 javax.realtime.memory.PhysicalMemorySelector.PagingBehavior
 getPagingPagingBehavior()

Returns
 the PagingBehavior
```

11.5.3.5 PinnableMemory

This class is for passing information between different threads as in the producer consumer pattern. One thread can enter an empty PinnableMemory, allocate some data structure, put a reference in the portal, pin the scope, exit it, and then pass it to another thread for further processing or consumption. Once the last thread is done, the memory can be unpinned, causing its contents to be freed.

Inheritance

```
java.lang.Object
javax.realtime.MemoryArea
javax.realtime.ScopedMemory
javax.realtime.memory.PinnableMemory
```

11.5.3.5.1 Constructors

PinnableMemory(long)

Create a scope of fixed size.

Signature

```
public
```

PinnableMemory(long size)

Parameters 1

size is the number of bytes in the memory area.

PinnableMemory(SizeEstimator)

Create a scope of fixed size.

Signature

```
public
```

PinnableMemory(SizeEstimator size)

Parameters

size is an estimator for determining the number of bytes in the memory area.

11.5.3.5.2 Methods

pin

Prevent the contents from being freed.

Signature

```
public
void pin()
```

unpin

Allow the contents to be freed the next time no $Schedulable^{131}$ or $AbstractA-syncEvent^{132}$ is active withing the scope.

```
Signature

public

void unpin()
```

isPinned

Determin whether the scope may be cleared on last exit.

```
Signature

public
boolean isPinned()

Returns

true when yes, otherwise false.
```

getPinCount

Find out how many times the scope has been pinned, but not unpinned.

```
public int getPinCount()

Returns
the number of outstanding pins.

131 Section 6.4.1.2
132 Section 8.4.3.1
```

joinPinned

Wait until the scope has been cleared and then pin it.

```
Signature

public

void joinPinned()

throws InterruptedException
```

joinPinned(javax.realtime.HighResolutionTime<T>)

Wait until the scope has been cleared and then pin it, within a specified time frame.

```
public
     void joinPinned(javax.realtime.HighResolutionTime<T> limit)
     throws InterruptedException
Parameters
     limit is the maximum time to wait
```

joinPinnedAndEnter(Runnable)

Wait until the scope has been cleared and then pin it and enter it.

```
Signature

public

void joinPinnedAndEnter(Runnable logic)

throws InterruptedException, ScopedCycleException

Parameters

logic is the logic to execute upon entry
```

joinPinnedAndEnter(Runnable, javax.realtime.HighResolutionTime<T>

Wait until the scope has been cleared and then pin it and enter it, within a specified time frame.

```
public
void joinPinnedAndEnter(Runnable logic,
javax.realtime.HighResolutionTime<T> timeIn)
throws InterruptedException, ScopedCycleException

Parameters
logic is the logic to execute upon entry
limit is the maximum time to wait.
```

joinPinnedAndEnter

Wait until the scope has been cleared and then pin it and enter it.

```
public
    void joinPinnedAndEnter()
    throws InterruptedException, IllegalThreadStateException,
    ThrowBoundaryError, ScopedCycleException, MemoryAccessError
```

joinPinnedAndEnter(javax.realtime.HighResolutionTime<T>)

Wait until the scope has been cleared and then pin it and enter it, within a specified time frame.

```
Signature

public

void joinPinnedAndEnter(javax.realtime.HighResolutionTime<T>
time)

throws InterruptedException, IllegalThreadStateException,
IllegalArgumentException, UnsupportedOperationException,
ThrowBoundaryError, ScopedCycleException, MemoryAccessError

Parameters

limit is the maximum time to wait.
```

11.5.3.6 StackedMemory

StackedMemory implements a scoped memory allocation area and backing store management system. It is designed to allow for safe, fragmentation-free management of scoped allocation with certain strong guarantees provided by the virtual machine and runtime libraries.

Each StackedMemory instance represents a single object allocation area and additional memory associated with it in the form of a *backing store*. The backing store associated with a StackedMemory is a fixed-size memory area allocated at or before instantiation of the StackedMemory. The object allocation area is taken from the associated backing store, and the backing store may be further subdivided into additional StackedMemory allocation areas or backing stores by instantiating additional StackedMemory objects.

When a StackedMemory is created with a backing store, the backing store may be taken from a notional global backing store, in which case it is effectively immortal, or it may be taken from the enclosing StackedMemory's backing store when the scope in which it is created is also a StackedMemory, in which case it is returned to its enclosing scope's backing store when the object is finalized. Implementations are not required to return the space occupied by backing stores taken from the global backing store when their associated StackedMemory object is finalized.

These backing store semantics divide instances of **StackedMemory** into two categories:

- *Host* this denotes a **StackedMemory** with an object allocation area created in a new backing store, allocated either from the global store or from a parent **StackedMemory**'s backing store.
- guest this in turn indicates a StackedMemory with an object allocation area taken directly from a parent StackedMemory's backing store without creating a sub-store.

In addition, there is one distinguished status for StackedMemory objects, *root*. A root StackedMemory is a host StackedMemory created with a backing store drawn directly from the global backing store, created in an allocation context of some type other than StackedMemory.

Allocations from a StackedMemory object allocation area are guaranteed to run in time linear in the size of the allocation. All memory for the backing store must be reserved at object construction time.

StackedMemory memory areas have two additional stacking constraints in addition to the single parent rule, designed to enable fragmentation-free manipulation:

• A StackedMemory that is created when another StackedMemory is the current allocation context can only be entered from the same allocation context in

which it was created.

• A guest StackedMemory cannot be created from a StackedMemory that currently has another child area that is also a guest StackedMemory. (That is, a StackedMemory can have at most one direct child that is a guest Stacked-Memory.)

The StackedMemory constructor semantics also enforce the property that a Stacked-Memory cannot be created from another StackedMemory allocation context unless it is allocated from that context's backing store as either a host or guest area.

The backing store of a StackedMemory behaves as if any StackedMemory object allocation areas are at the "bottom" of the backing store, while the backing stores for enclosed StackedMemory areas are taken from the "top" of the backing store.

There may be an implementation-specific memory overhead for creating a backing store of a given size. This means that creating a StackedMemory with a backing store of exactly the remaining available backing store of the current StackedMemory may fail with an OutOfMemoryError. This overhead must be bounded by a constant.

Available since RTSJ 2.0

Inheritance

java.lang.Object javax.realtime.MemoryArea javax.realtime.ScopedMemory javax.realtime.memory.StackedMemory

11.5.3.6.1 Constructors

StackedMemory(long, long)

Create a host StackedMemory with an object allocation area and backing store of the specified sizes. The backing store is allocated from the currently active memory area when it is also a StackedMemory, and the global backing store otherwise. The object allocation area is allocated from the backing store.

```
Signature
```

```
public
   StackedMemory(long scopeSize, long backingSize)
```

Parameters

scopeSize Size of the allocation area backingSize Size of the total backing store

Throws

IllegalArgumentException when either scopeSize or backingSize is less than zero, or when scopeSize is too large to be allocated from a backing store of size backingSize.

OutOfMemoryError when there is insufficient memory available to reserve the requested backing store.

StackedMemory(long, long, Runnable)

Create a host StackedMemory with an object allocation area and backing store of the specified sizes, bound to the specified Runnable. The backing store is allocated from the currently active memory area when it is also a StackedMemory, and the global backing store otherwise. The object allocation area is allocated from the backing store.

Signature

public

StackedMemory(long scopeSize, long backingSize, Runnable logic)

Parameters

scopeSize Size of the allocation area

backingSize Size of the total backing store

logic Runnable to be entered using this as its current memory area when enter()¹³³ is called.

Throws

IllegalArgumentException when either scopeSize or backingSize is less than zero, or when scopeSize is too large to be allocated from a backing store of size backingSize.

OutOfMemoryError when there is insufficient memory available to reserve the requested backing store.

StackedMemory(SizeEstimator, SizeEstimator)

¹³³Section 11.5.3.6.2

Create a host StackedMemory with an object allocation area and backing store of the sizes estimated by the specified SizeEstimators. The backing store is allocated from the currently active memory area when it is also a StackedMemory, and the global backing store otherwise. The object allocation area is allocated from the backing store.

Signature

public

StackedMemory(SizeEstimator scopeSize, SizeEstimator backingSize)

Parameters

scopeSize SizeEstimator indicating the size of the object allocation area backingSize SizeEstimator indicating the size of the total backing store Throws

IllegalArgumentException when either scopeSize or backingSize is less than zero, or when scopeSize is too large to be allocated from a backing store of size backingSize.

OutOfMemoryError when there is insufficient memory available to reserve the requested backing store.

StackedMemory(SizeEstimator, SizeEstimator, Runnable)

Create a host StackedMemory with an object allocation area and backing store of the sizes estimated by the specified SizeEstimators, bound to the specified Runnable. The backing store is allocated from the currently active memory area when it is also a StackedMemory, and the global backing store otherwise. The object allocation area is allocated from the backing store.

Signature

public

StackedMemory(SizeEstimator scopeSize, SizeEstimator backingSize, Runnable logic)

Parameters 1

scopeSize SizeEstimator indicating the size of the object allocation area backingSize SizeEstimator indicating the size of the total backing store

logic Runnable to be entered using this as its current memory area when enter()¹³⁴ is called.

Throws

IllegalArgumentException when either scopeSize or backingSize is less than zero, or when scopeSize is too large to be allocated from a backing store of size backingSize.

OutOfMemoryError when there is insufficient memory available to reserve the requested backing store.

StackedMemory(long)

Create a guest StackedMemory with an object allocation area of the specified size. The object allocation area is drawn from the same backing store as the parent scope's object allocation area. The parent scope must be a StackedMemory.

Signature

```
public
```

StackedMemory(long scopeSize)

Parameters

scopeSize Size of the allocation area

Throws

IllegalStateException when the parent memory area is not a StackedMemory, or when the parent StackedMemory already has a child that is also a guest StackedMemory.

IllegalArgumentException when scopeSize is less than zero.

OutOfMemoryError when there is insufficient memory available in the backing store of the parent StackedMemory's object allocation area to reserve the requested object allocation area.

StackedMemory(SizeEstimator)

Create a guest StackedMemory with an object allocation area of the size estimated by the specified SizeEstimator. The object allocation area is drawn from the same backing store as the parent scope's object allocation area. The parent scope must be a StackedMemory.

¹³⁴Section 11.5.3.6.2

Signature

public

StackedMemory(SizeEstimator scopeSize)

Parameters 1 4 1

scopeSize SizeEstimator indicating the size of the object allocation area Throws

IllegalStateException when the parent memory area is not a StackedMemory, or when the parent StackedMemory already has a child that is also a guest StackedMemory.

IllegalArgumentException when scopeSize is less than zero.

OutOfMemoryError when there is insufficient memory available in the backing store of the parent StackedMemory's object allocation area to reserve the requested object allocation area.

StackedMemory(long, Runnable)

Create a guest StackedMemory with an object allocation area of the specified size, bound to the specified Runnable. The object allocation area is drawn from the same backing store as the parent scope's object allocation area. The parent scope must be a StackedMemory.

Signature

public

StackedMemory(long scopeSize, Runnable logic)

scopeSize Size of the allocation area

logic Runnable to be entered using this as its current memory area when enter()¹³⁵ is called.

Throws

IllegalStateException when the parent memory area is not a StackedMemory, or when the parent StackedMemory already has a child that is also a guest StackedMemory.

 $^{^{135}}$ Section 11.5.3.6.2

IllegalArgumentException when scopeSize is less than zero.

OutOfMemoryError when there is insufficient memory available in the backing store of the parent StackedMemory's object allocation area to reserve the requested object allocation area.

StackedMemory(SizeEstimator, Runnable)

Create a guest StackedMemory with an object allocation area of the size estimated by the specified SizeEstimator, bound to the specified Runnable. The object allocation area is drawn from the same backing store as the parent scope's object allocation area. The parent scope must be a StackedMemory.

Signature

public

StackedMemory(SizeEstimator scopeSize, Runnable logic)

Parameters

scopeSize SizeEstimator indicating the size of the object allocation area logic Runnable to be entered using this as its current memory area when enter()¹³⁶ is called.

Throws

IllegalStateException when the parent memory area is not a StackedMemory, or when the parent StackedMemory already has a child that is also a guest StackedMemory.

IllegalArgumentException when scopeSize is less than zero.

OutOfMemoryError when there is insufficient memory available in the backing store of the parent StackedMemory's object allocation area to reserve the requested object allocation area.

11.5.3.6.2 Methods

resize(long)

¹³⁶Section 11.5.3.6.2

Change the size of the object allocation area for this scope. This method may be used to either grow or shrink the allocation area when there are no objects allocated in the scope and no Schedulable object has this area as its current allocation context. It may be used to shrink the allocation area down to the size of its current usage when the calling Schedulable object is the only object that has this area on its scope stack and there are no guest StackedMemory object allocation areas created after this area in the same backing store but not yet finalized.

```
Signature

public

void resize(long scopeSize)

Parameters

scopeSize The new allocation area size for this scope

Throws
```

IllegalStateException when the caller is not permitted to perform the requested adjustment or there are additional guest StackedMemory allocation areas after this one in the backing store.

OutOfMemoryException when the remaining backing store is insufficient for the requested adjustment.

getMaximumSize

Get the maximum size this memory area can attain. The value returned by this function is the maximum size that can currently be passed to resize(long)¹³⁷ without triggering an OutOfMemoryException.

```
Signature

public
long getMaximumSize()

Returns

The maximum size attainable.
```

enter

Associate this memory area with the current Schedulable object for the duration of the run() method of the instance of Runnable given in this object's constructor.

 $^{^{137}}$ Section 11.5.3.6.2

During this period of execution, this memory area becomes the default allocation context until another default allocation context is selected.

This method may only be called from the memory area in which this scope was created.

See Section ScopedMemory.enter()

```
Signature

public

void enter()
```

Throws

IllegalStateException when the currently active memory area is a Stacked-Memory and is not the area in which this scope was created, or the current memory area is not a StackedMemory and this StackedMemory is not a root area.

 $\label{local_continuity} Throw Boundary Error @inherit Doc\\ Il legal Thread State Exception @inherit Doc\\ Memory Access Error @inherit Doc\\$

enter(Runnable)

Associate this memory area with the current **Schedulable** object for the duration of the run() method of the given Runnable. During this period of execution, this memory area becomes the default allocation context until another default allocation context is selected.

This method may only be called from the memory area in which this scope was created.

See Section ScopedMemory.enter(Runnable)

```
Signature
public
void enter(Runnable logic)
Throws
```

IllegalStateException when the currently active memory area is a Stacked-Memory and is not the area in which this scope was created, or the current memory area is not a StackedMemory and this StackedMemory is not a root area.

ThrowBoundaryError @inheritDoc

IllegalThreadStateException @inheritDoc MemoryAccessError @inheritDoc

joinAndEnter

@inheritDoc

Signature

public void joinAndEnter()

Throws

IllegalStateException when the currently active memory area is a Stacked-Memory and is not the area in which this scope was created, or the current memory area is not a StackedMemory and this StackedMemory is not a root area.

 $Interrupted Exception @inherit Doc \\ Illegal Thread State Exception @inherit Doc \\ Throw Boundary Error @inherit Doc \\ Scoped Cycle Exception @inherit Doc \\ Memory Access Error @inherit Doc \\$

joinAndEnter(javax.realtime.HighResolutionTime<?>)

@inheritDoc

Signature

public
void joinAndEnter(javax.realtime.HighResolutionTime<?> time)

Throws

IllegalStateException when the currently active memory area is a Stacked-Memory and is not the area in which this scope was created, or the current memory area is not a StackedMemory and this StackedMemory is not a root area.

 $Interrupted Exception @inherit Doc \\ Il legal Thread State Exception @inherit Doc \\ Throw Boundary Error @inherit Doc \\ Scoped Cycle Exception @inherit Doc \\ Memory Access Error @inherit Doc \\$

joinAndEnter(Runnable)

@inheritDoc

```
Signature
```

public
void joinAndEnter(Runnable logic)

Throws

IllegalStateException when the currently active memory area is a Stacked-Memory and is not the area in which this scope was created, or the current memory area is not a StackedMemory and this StackedMemory is not a root area.

 $Interrupted Exception @inherit Doc \\ Illegal Thread State Exception @inherit Doc \\ Throw Boundary Error @inherit Doc \\ Scoped Cycle Exception @inherit Doc \\ Memory Access Error @inherit Doc \\$

joinAndEnter(Runnable, javax.realtime.HighResolutionTime<?>)

@inheritDoc

Signature

public
void joinAndEnter(Runnable logic,
javax.realtime.HighResolutionTime<?> time)

Throws

IllegalStateException when the currently active memory area is a Stacked-Memory and is not the area in which this scope was created, or the current memory area is not a StackedMemory and this StackedMemory is not a root area.

 $Interrupted Exception @inherit Doc \\ Il legal Thread State Exception @inherit Doc \\ Throw Boundary Error @inherit Doc \\ Scoped Cycle Exception @inherit Doc \\ Memory Access Error @inherit Doc \\$

2.0 (Draft 20)

488 11.6 The Rationale

11.6 The Rationale

11.6.1 The scoped memory model

Languages that employ automatic reclamation of blocks of memory allocated in what is conventionally called the heap by program logic also typically use an algorithm called a garbage collector. Garbage collection algorithms and implementations vary in the amount of non-determinacy they add to the execution of program logic. Rather than require a garbage collector, and require it to meet realtime constraints that would necessarily be a compromise, this specification constructs alternative systems for "safe" management of memory. The scoped and immortal memory areas allow program logic to allocate objects in a Java-like style, ignore the reclamation of those objects, and not incur the latency of the implemented garbage collection algorithm.

The term *scope stack* might mislead a reader to infer that it contains only scoped memory areas. This is incorrect. Although the scope stack may contain scoped memory references, it may also contain heap and immortal memory areas. Also, although the scope stack's behavior is specified as a stack, an implementation is free to use any data structure that preserves the stack semantics.

This specification does not specifically address the lifetime of objects allocated in immortal memory areas. If they were reclaimed while they were still referenced, the referential integrity of the JVM would be compromised which is not permissible. Recovering immortal objects only at the termination of the application, or never recovering them under any circumstances is consistent with this specification.

If a scoped memory area is used by both heap and non-heap SOs, there could be cases where a finalizer executed in non-heap context could attempt to use a heap reference left by a heap-using SO. The code in the finalizer would throw a memory access error. If that exception is not caught in the finalizer, it will be handled by the implementation so finalization will continue undisturbed, but the problem in finalizer that caused the illegal memory access could be hard to locate. So, catch clauses in finalizers for objects allocated in scoped memory are even more useful than they are for normal finalizers.

Support for scoped non-default initial memory areas (SNDIMAs) for schedulables has repercussions. These repercussions include:

- The SNDIMA's parent is set when the SO is constructed, but its reference count is not incremented until the realtime thread is started or the async event handler becomes fireable. This lets a scope with a zero reference count have a parent. This may cause unexpected scoped cycle exceptions. The most surprising are from the joinAndEnter family of methods.
- Finalization of a scoped memory (when its reference count goes to zero) can cause finalization of SNDIMAs of AEHs whose AEs are in the finalizing scope.

This can cause finalization of one scope to trigger finalization of numerous other scopes including scopes that are descendants of the scope whose finalization started the process.

- Any action that makes an AEH non-fireable (directly disassociating it from all AEs, or indirectly disassociating it by finalizing the scopes containing those AEs) must block until all all the resulting finalization completes.
- Any action that makes an AEH fireable must block until any ongoing finalization of its SNDIMA completes.

These semantics are complicated (and so prone to bugs in use and in implementation), they may use significant CPU time at unexpected times, CPU time used for this finalization is not controlled by cost enforcement and it is hard to include in feasibility analysis. **Open issue:** This will not encourage the reader! **End of open issue**

Entering the scoped memory when the AEH is fired or the realtime thread starts has almost the same effect as using the scope as an initial memory area with much less complexity that is recommended practice. A future release may deprecate support for SNDIMAs. **Open issue:** *** End of open issue

Using heap or immortal memory as the non-default initial memory area of an SO is benign.

11.6.2 The physical memory model

Embedded systems may have many different types of directly addressable memory available to them. Each type has its own characteristics [2] that determine whether it is

- volatile whether it maintains its state when the power is turned off;
- writable whether it can be written at all, written once or written many times and whether writing is under program control,
- synchronous or asynchronous whether the memory is synchronized with the system bus,
- erasable at the byte level if the memory can be overwritten whether this is done at the byte level or whether whole sectors of the memory need to be erased,
- fast to access both for reading and writing.

Examples include the following [2]:

• Dynamic Random Access Memory (DRAM) and Static Random Access Memory (SRAM) – these are volatile memory types that are usually writable at the byte level. There are no limits on the number of times the memory contents can be written. From the embedded systems designer's view point, the main differences between the two are their access times and their costs per byte. SRAM has faster access times and is more expensive. Both DRAM

490 11.6 The Rationale

and SRAM are example of asynchronous memory, SDRAM and SSRAM are their synchronized counterparts. Another important difference is that DRAM requires periodic refresh operations, which may interfere with execution time determinism.

- Read-Only Memory (for example, *Erasable Programmable Read-Only Memory* (EPROM)) these are nonvolatile memory types that once initialized with data can not be overwritten by the program (without recourse to some external effect, usually ultraviolet light as in EPROM). They are fast to access and cost less per byte than DRAM.
- Hybrid Memory (for example, *Electrically Erasable Programmable Read-Only Memory* (EEPROM), and Flash) these have some properties of both random access and read-only memory.
 - EEPROM this is nonvolatile memory that is writable at the byte level.
 However, there are typically limits on how many time the same location can be overwritten. EEPROMs are expensive to manufacture, fast to read but slow to write.
 - FLASH memory this is nonvolatile that is writable at the sector level. Like EEPROM there are limits on how many times the same location can be overwritten and they are fast to read but slow to write. Flash memory is cheaper to manufacture than EEPROM.

Some embedded systems may have multiple types of random-access memory, and multiple ways of accessing memory. For instance, there may be a small amount of very fast RAM on the processor chip, memory that is on the same board as the processor, memory that may be added and removed from the system dynamically, memory that is accessed across a bus, access to memory that is mediated by a cache, access where the cache is partially disabled so all stores are "write through", memory that is demand paged, and other types of memory and memory-access attributes only limited by physics and the imagination of electrical engineers. Some of these memory types will have no impact on the programmer, others will.

Individual computers are often targeted at a particular application domain. This domain will often dictate the cost and performance requirements, and therefore, the memory type used. Some embedded systems are highly optimized and need to explore different options in memory to meet their performance requirements. Here are five example scenarios.

- Ninety percent of performance-critical memory access is to a set of objects that could fit in a half the total memory.
- The system enables the locking of a small amount of data in the cache, and a small number of pages in the translation lookaside buffer (TLB). A few very frequently accessed objects are to be locked in the cache and a larger number of objects that have jitter requirements can be TLB-locked to avoid TLB faults.

- The boards accept added memory on daughter boards, but that memory is not accessible to DMA from the disk and network controllers and it cannot be used for video buffers. Better performance is obtained if we ensure that all data that might interact with disk, network, or video is not stored on the daughter board.
- Improved video performance can be obtained by using an array as a video buffer. This will only be effective if a physically contiguous, non-pageable, DMA-accessible block of RAM is used for the buffer and all stores forced to write through the cache. Of course, such an approach is dependent on the way the JVM lays out arrays in memory, and it breaks the JVM abstraction by depending on that layout.
- The system has banks of SRAM and saves power by automatically putting them to "sleep" whenever they stay unused for 100 ms or so. To exploit this, the objects used by each phase of our program can be collected in a separate bank of this special memory.

To be clear, few embedded systems are this aggressive in their hardware optimization. The majority of embedded systems have only ROM, RAM, and maybe flash memory. Configuration-controlled memory attributes (such as page locking, and TLB behavior) are more common.

As well as having different types of memory, many computers map input and output devices so that their registers can be accessed as if they were resident within the computer memory (see Section 12.3.1). Hence, some parts of the processor's address space map to real memory and other parts map to device registers. Logically, even a device's memory can be considered part of the memory hierarchy, even where the device's interface is accessed through special assembly instructions. Multiprocessor systems add a further dimension to the problem of memory access. Memory may be local to a CPU, tightly shared between CPUs, or remotely accessible from the CPU (but with a delay).

Traditionally, Java programmers are not concerned with these low-level issues; they program at a higher level of abstraction and assume the JVM makes judicious use of the underlying resources provided by the execution platform¹³⁸. Embedded systems programmers cannot afford this luxury. Consequently, any Java environment that wishes to facilitate the programming of embedded systems must enable the programmer to exercise more control over memory.

¹³⁸This is reflected by the OS support provided. For example, most POSIX systems only offer programs a choice of demand paged or page-locked memory.

492 11.6 The Rationale

11.6.2.1 Problems with the current RTSJ 1.0.2 Physical Memory Framework

The RTSJ 1.0.2 supports three ways to allocate objects that can be placed in particular types of memory:

- ImmortalPhysicalMemory allocates immortal objects in memory with specified characteristics.
- LTPhysicalMemory allocates scoped memory objects in a memory with specified characteristics using a linear time memory allocation algorithm.
- VTPhysicalMemory allocates scoped memory objects in memory with specified characteristics using an algorithm that may be worse than linear time but could offer extra services (such as extensibility).

The only difference between the physical memory classes and the corresponding non-physical classes is that the ordinary memory classes give access to normal system RAM and the physical memory classes offer access to particular types of memory.

The RTSJ 1.0.2 supports access to physical memory via a memory manager and one or more memory filters. The goal of the memory manager is to provide a single interface with which the programmer can interact in order to access memory with a particular characteristic. A memory filter enables access to a particular type of physical memory. Memory filters may be dynamically added and removed from the system, and there can only be a single filter for each memory type. The memory manager is unaware of the physical addresses of each type of memory. This is encapsulated by the filters. The filters also know the virtual memory characteristics that have been allocated to their memory type. For example, whether the memory is readable or writable.

In theory, any developer can create a new physical memory filter and register it with the PMM. However, the programming of filters is difficult for the following reasons.

- Physical memory type filters include a memory allocation function that must respond to allocation requests with whether a requested range of physical memory is free and if it is not, the physical address of the next free physical memory of the requested type. This is complex because requests for compound types of physical memory must find a free segment that satisfies all attributes of the compound type.
- The Java runtime must continue to behave correctly under the Java memory model when it is using physical memory. This is not a problem when a memory type behaves like the system's normal RAM with respect to the properties addressed by the memory model, or is more restricted than normal RAM (as, for instance, write-through cache is more restricted than copy-back cache). If a new memory type does not obey the memory model using the same instruction sequences as normal RAM, the memory filter must cooperate with the inter-

preter, the JIT, and any ahead-of-time compilation to modify those instruction sequences when accessing the new type of memory. That task is difficult for someone who can easily modify the Java runtime and nearly impossible for anyone else.

Hence, the utility of the physical memory filter framework at Version 1.0.2 is questionable, and hence is replaced in 2.0 with an easier to use framework.

11.6.2.2 The RTSJ 2.0 Physical Memory Framework

The main problem with the 1.0.2 framework is that it places too greater a burden on the JVM implementer. Even for embedded systems, the JVM implementer requires the VM to be portable between systems within the same processor family. It, therefore, cannot have detailed knowledge of the underlying memory architecture. It is only concerned with the standard RAM provided to it by the host operating system.

The design of 2.0 model is based on two constraints.

- Java objects can only be allocated in a memory area if the physical backing store supports the Java Memory Model without the JVM having to perform any operation addition to those that it performs when accessing as the main RAM for the host machine. No extra compiler or JVM interactions shall be required. Hence memory types (such as EEPROM), which potentially require special hardware instructions to perform write operations, cannot be used as the backing store for physical memory areas. Similarly, non-volatile memory can be used any objects store therein may contain references to objects in volatile memory. Although these memory types are prohibited from being used as backing stores, they contain objects of primitive Java types and be accessed via the RTSJ Raw Memory facilities (see Section 12.3.1).
- Any API must delegates detailed knowledge of the memory architecture to the programmer of the specific embedded system to be implemented. There is less requirement for portability here, as embedded systems are usually optimized for their host environment. The model assumes that the programmer is aware of the memory map, either through some native operating system interface or from some property file read at program initialization time.

When accessing physical memory, there are two main considerations:

- 1. the characteristics of the required physical memory, and
- 2. how that memory is to be mapped into the virtual memory of the application.

¹³⁹For example, the Advanced Configuration and Power Interface (ACPI) specification is an open standard for device configuration and power management by the operating system. The ACPI defines platform-independent interfaces for hardware discovery, configuration, power management and monitoring. See http://www.acpi.info/

494 11.6 The Rationale

2.0 requires the program to identify (and inform the RTSJ's physical memory manager of) the physical memory characteristics and the range of physical addresses those characteristic apply to. For example, that there is SRAM between physical address range 0x100000000 and 0xA0000000.

The physical memory manager supports a range of options for mapping physical memory into the virtual memory of the application. Examples of such options are whether the range is to be permanently resident in memory (the default is that it may be subject to paging/swapping), and whether data is written to the cache and the main memory simultaneously (i.e., a write through cache).

Given the required physical and virtual memory characteristics, the programmer requests that the PMM creates a memory filter for accessing this memory. This filter can then be used with new constructors on the physical memory classes. For example,

1 public ImmortalPhysicalMemory(PhysicalMemoryFilter filter, long size)

Use of this constructor enables the programmer to specify the allocation of the backing store in a particular type of memory with a particular virtual memory characteristic. The filter is used to locate an area in physical memory with the required physical memory characteristics and to direct its mapping into the virtual address space. Other constructors allow multiple filters to be passed.

Hence, once the filters have been created, physical memory areas can be created and objects can be allocated within those memory areas using the usual RTSJ mechanisms for changing the allocation context of the new operator.

11.6.2.3 An example

Consider an example of a system that has a SRAM physical memory module configured at a physical base address of 0x10000000 and of length 0x20000000. Another module (base address of 0xA0000000 and of length 0x10000000) also supports SRAM, but this module has been configured so that it saves power by sleeping when not in use. The following subsections illustrate how the embedded programmer informs the PMM about the structure during the program's initialization phase, and how the memory may be subsequently used after this. The example assumes that the PMM supports the virtual memory characteristics defined above.

Program Initialization

For simplicity, the example requires that the address of the memory modules are known, rather than being read from a property file. The program needs to have a

class that implements the PhysicalMemoryCharacteristic. In this simple example, this is empty.

```
1 public class MyMemoryType implements PhysicalMemoryCharacteristic {}
```

The initialization method must now create instances of the PhysicalMemory-Region class to represent the physical memory module memory modules to represent

```
PhysicalMemoryRegion staticRam =

new PhysicalMemoryRegion(0x10000000L, 0x100000000L);

PhysicalMemoryRegion staticSleepableRam =

new PhysicalMemoryRegion(0xA0000000L, 0x100000000L);
```

It then creates names for the characteristics that the program wants to associate with each memory module.

```
 1 \  \, \text{PhysicalMemoryCharacteristic STATIC\_RAM} = \textbf{new} \  \, \text{MyMemoryType()}; \\ 2 \  \, \text{PhysicalMemoryCharacteristic AUTO\_SLEEPABLE} = \textbf{new} \  \, \text{MyMemoryType()}; \\
```

It then informs the PMM of the appropriate associations:

```
1 PhysicalMemoryFactory.associate(STATIC_RAM, staticRam);
2 PhysicalMemoryFactory.associate(STATIC_RAM, staticSleepableRam);
3 PhysicalMemoryFactory.associate(AUTO_SLEEPABLE, staticSleepableRam);
```

Once this is done, the program can now create a filter with the required properties. In this case it is for some SRAM that must be auto sleepable.

```
PhysicalMemoryCharacteristic [] PMC =

new PhysicalMemoryCharacteristic[2];

PMC[0] = STATIC_RAM;

PMC[1] = AUTO_SLEEPABLE;

PhysicalMemorySelector selector =

new PhysicalMemorySelectory(PMC, null, DISABLED, FIXED);
```

If the program had just asked for SRAM then either of the memory modules could satisfy the request.

The initialization is now complete, and the programmer can use the memory for storing objects, as shown below.

496 11.6 The Rationale

Using Physical Memory

Once the programmer has configured the JVM so that it is aware of the physical memory modules, and the programmer names for characteristics of those memory modules, using the physical memory is straight forward. Here is an example.

```
ImmortalMemory IM = factory.createImmortalMemory(selector, 0x1000);
 2
     IM.enter(new Runnable()
 3
 4
       public void run()
 5
 6
         // The code executing here is running with its allocation
 7
         // context set to a physical immortal memory area that is
 8
         // mapped to RAM which is auto sleepable.
 9
         // Any objects created will be placed in that
10
         // part of physical memory.
11
12
     });
```

It is the appropriate constructor of the physical memory classes that now interfaces with the PMM. The physical memory manager keeps track of previously allocated memory and is able to determine if memory is available with the appropriate characteristics. Of course, the PMM has no knowledge of what these names mean; it is merely providing a look-up service.

Chapter 12

Devices and Triggering

12.1 Overview

Interacting with the external environment in a timely manner is an important requirement for realtime, embedded systems. From an embedded systems' perspective, all interactions with the physical world are performed by input and output devices. Hence, the problem is one of controlling and monitoring of devices. This is an area insufficiently addressed by other Java standards. A conventional Java Virtual Machine is not designed to support device access and interrupt handling. Programs that need this functionality must resort to code written in another language and called via the Java Native Interface (JNI). This specification addresses the problem by providing APIs for interrupt handling and direct memory access without resorting to JNI.

In contrast to earlier versions of this specification, 2.0 has extended the goals of the device interfaces to be type safe and user extensible, so that the user can defined new devices without changing the underlying virtual machine.

There are at least four execution (runtime) environments for the RTSJ:

- 1. on a realtime operating system where the Java application runs in user mode;
- 2. on a realtime operating system where the Java application runs in a context with a user space device driver;
- 3. as a "kernel module" incorporated into a realtime kernel where both kernel and application run in supervisor mode; and
- 4. as part of an embedded device where the Java application runs stand-alone on a hardware machine.

In execution environment 1, interaction with the embedded environment is usually via operating system calls using Java's connection-oriented APIs. The Java program will typically have no direct access to the I/O devices. Although some limited access to physical memory may be provided, it is unlikely that interrupts

498 12.3 Definitions

can be directly handled. However, asynchronous interaction with the environment is still possible, for example, via POSIX signals.

In execution environments 2, 3, and 4, the Java program may be able to directly access devices and handle interrupts.

A device can be anything from a simple set of registers wired to sensors and actuators to a full processor performing some fixed task. The interface to a device is usually through a set of device registers. Depending on the I/O architecture of the processor, the programmer can either access these registers via predetermined memory location (called memory mapped I/O) or via special assembler instructions (called port-mapped I/O).

A computer system with processing devices can be considered to be a collection of parallel threads. The device 'thread' can communicate and synchronize with the tasks executing inside the main processor either by having the main processor poll registers of the device or via a signal from the device. This signal is usually referred to as an interrupt. All high-level models of device programming must provide [3]

- 1. facilities for representing, addressing and manipulating device registers; and
- 2. a suitable representation of interrupts (if interrupts are to be handled).

Version 1.0 of the RTSJ went some way towards supporting this model through the notion of *happenings* and the *physical and raw memory* access facilities. Unfortunately, happenings were under defined and the mechanisms for physical and raw memory were overly complex with no clear delineation of the separations of concerns between application developers and JVM implementers.

2.0 has significantly enhanced the support for happenings, and has provided a clearer separation between physical and raw memory. The interfaces for Happening, Timer, and POSIXSignal are now unified under ActiveEvent. This means that both Happening and POSIXSignal, like Timer are now subclasses of AsyncEvent-Handler. As described in Chapter 8, ActiveEvent provides a common light-weight means of notifying that its event has occurred. Unlike fire(), where dispatching of the associated handlers is done in context of the caller, an ActiveEvent separates this notification that the event occurred, its triggering, from the dispatching by providing its own execution context for the dispatching. As with Timer, each class has its own ActiveEventDispatcher: HappeningDispatcher, POSIXSignalDispatcher, and TimeDispatcher. Finally, support for POSIX realtime signals is provided by POSIXRealtimeSignal with its associated dispatcher.

12.2 Definitions

A happening is an event that takes place outside the Java runtime environment. The triggers for happenings depend on the external environment, but happenings might include signals and interrupts.

12.3 Semantics

There are several aspects of the API for supporting devices. Raw Memory provides the means of accessing the I/O register of a device. Direct Memory Access (DMA) support provide a means of transferring data using a DMA controller. Active events and dispatchers support releasing event handlers based on external events. Interrupt service routines and application-defined clocks are for linking external events to the active events.

12.3.1 Raw Memory

Raw Memory provides means of accessing particular physical memory addresses as variables of Java's primitive data types, and thereby provides an application with direct access to physical memory, for example, for memory-mapped I/O.

Java objects or references therefore *cannot* be stored in raw memory. The following specifies the RTSJ's facilities for raw memory access.

- Each area of memory supporting raw memory access is identified by a subclass of RawMemoryRegion.
 - The raw memory region RawMemoryFactory.MEMORY_MAPPED_REGION facilitates access to memory location that are outside the main memory used by the JVM. It is used to access input and output device registers when such registers are memory mapped.
 - The raw memory region RawMemoryFactory.IO_PORT_MAPPED_REGION facilitates access to locations that are outside the main memory used by the JVM. It is used to access input and output device registers when such registers are port-based and can only be accessed by special hardware instructions.
 - The application developer can define and register additional regions to support things like emulated access to devices or access to a bus over a bus controller.
- Access to raw memory is controlled by implementation-defined objects, called accessor objects. These implement specification-defined interfaces (e.g., Raw-Byte, RawShort, RawInt, etc.) and are created by implementation-defined factory objects. Each factory implements the RawMemoryRegionFactory interface, and is identified by its RawMemoryRegion.
- The RawMemoryFactory class defines the applications programmers interface to the raw memory facilities.
- The RawMemoryRegionFactory interface defines the interface that all factories must support for creating accessor objects.

500 12.3 Semantics




Figure 12.1: Raw Memory Interface




Figure 12.2: Event Classes

12.3.1.1 Raw Memory Region

Raw memory is designed to support arbitrary I/O address spaces. The simplest is through the processor address space and is accessible via standard memory access instructions, such as load and store. This provide access to memory mapped I/O devices, but there are others address spaces as well. Each of these address spaces is referred to as a *Raw Memory Region*.

There are two raw memory regions that can be supported generically. Memory mapped I/O is one. The other is port mapped I/O. The most common instance is the I/O space provided by Intel x86 compatible processors through their **in** and **out** instructions. The memory mapped I/O raw memory region must be supported by all implementations, but the port mapped I/O raw memory region must only be supported on processors that support it.

All other raw memory regions are optional and may be provided by a system integrator or an application developer. The API provides an interface, RawMemoryRegionFactory, that can be implemented to provide a means of creating accessor objects for that region. These additional regions can be anything from an I/O space provided by a memory mapped device, using memory mapped I/O to implement it, to a purely synthetic I/O space to emulated hardware that has not yet been built.

Each raw memory region is identified by its raw memory region object. These

502 12.3 Semantics

"types" are defined by instances of RawMemoryRegion: RawMemoryFactory.MEMORY_MAPPED_REGION for memory mapped devices and RawMemoryFactory.IO_PORT_MAPPED_REGION for port mapped devices for processors that have instructions for reading and writing an I/O bus directly. The instances are used to get accessors of a region instead of using a RawMemoryRegionFactory directly.

12.3.1.2 Raw Memory Factory

In order to support a variety of device address spaces efficiently, raw memory objects are created using the factory methods provided by RawMemoryFactory. This factory provides static methods to get accessors for a region via a region's type. Regions created during runtime can be provided by registering their factory with the main raw memory factory, so the application code only needs to have a reference to the object identifying the required region. For instance, one could create an I2C raw memory region by implementing a factory for it using a memory mapped I2C controller.

12.3.1.3 Stride

Since the word size of devices do not always match the word size of the memory or I/O bus, the interface provides for the notion of stride. Stride defines the distance between elements in a raw memory area. Normally elements of a memory area are mapped sequentially, without any space between the elements. This is a stride of one. A stride of two, means that every other element in physical memory is mapped into the raw memory area.

For example, it is often easier to map a 16 bit device into a 32 bit system by mapping the 16 bit registers at 32 bit intervals. This enables 16 bit accesses to the device to be atomic on 32 bit addressed systems, even when the bus always does 32 bit transfers. One can create a RawShort area with a stride of two. Then the area can be accessed as if the registers where contiguous.

Since stride is designed to support mapping devices that have a smaller word size than the host machine, the implementation is allowed to assume that the padding between values is "do not care" data, and can be overwritten arbitrarily.

12.3.2 Direct Memory Access Support

Many embedded systems provide a means of moving data without direct involvement of the main processor. This is typically programmed with a special device called a DMA controller. DMA controllers are treated specially since they are central to bulk transfer in device drivers. The data to be transferred is not in device registers, but in normal RAM. Java already provides an API form managing this kind of memory

in java.nio. The DMA API defined here provides a seamless means of integrating those features into a device driver for DMA.

There are various architectures for DMA controllers, each requiring its own programming paradigm, so only common low level support is provided by this specification. Raw memory can be used to program the DMA controller, but there needs to be a means of representing bulk data. The <code>java.nio.ByteBuffer</code> provides just such a representation. The only difference is that the restrictions on the memory behind byte buffer objects is a bit different than for other <code>java.nio</code> mechanisms.

These differences are covered with a special byte buffer factory: RawBufferFactory. An instance of this factory can produce direct byte buffers within a given memory range. This range can be chosen by the programmer to be within the range of a given DMA controller. The factory also provides methods for getting the start address of a buffer's memory and checking if a buffer's memory is within a given range. These addresses should be compatible with DMA controllers in the system, though for controllers with a smaller address space than the processor, the DMA address may have fixed offset from the processor physical address. The RawBuffer-Factory class also provides static methods for ensuring that Java-generated changes to DMA-mapped memory buffers are visible to native code, and vice-versa.

12.3.3 External Triggering

It is not enough to be able to read from and write to devices; many applications, need a means of being interrupted when an event happens. This specification provides a two-level interrupt mechanism. For predefined interfaces, such as POSIX signals, the first level handler is provided by the virtual machine and asynchronous events provide the second level event handling. For external events and additional clocks, where the programmer needs to be able to define new instances and provide for their triggering, additional classes are provided to manage both the first level, as well as the second level handling. In all cases, the user can control the priority and affinity of the dispatching between the first level and second level handling.

12.3.3.1 Happenings

Whereas, in previous versions of this specification, happenings were represented as a String, as of 2.0 they have become an object in their own right. This makes it easier to properly type methods that use them and for the user to define new happening for an application without the need to change the JVM. Furthermore, indirection is minimized by making the new Happening class a subclass of AsyncEvent.

Since a Happening needs to be triggerrable from an external event, such as an interrupt, the Happening class also implements ActiveEvent. As with other active events, Happening has its own dispatcher class: HappeningDispatcher. There is a

504 12.3 Semantics




Figure 12.3: Happening State Transition Diagram

default happening dispatcher that is used when none is provided at creation time, otherwise, the programmer can provide one to change the priority and affinity of dispatching.

Normally, happenings are triggered either from an InterruptServiceRoutine or from JNI code. For the later, the interface provides a means of linking a happening by name. This enables native code to get a handle for triggering a happening without have a direct reference. The given name must follow the Java naming conventions. A happening name defined outside of this specification should not begin with java. or javax..

Figure 12.3 illustrates the sequence of actions necessary for defining and using a Happening. When using an application defined dispatcher, it must be created first (1). When using an InterruptServiceRoutine to trigger the happening, it may be created before (2) or after the happening is create. After creating the happening (3), the happening must be started to be registered with it dispatcher to be triggered from native code. Of course, the JVM must have direct access to an interrupt, either by being directly bound in the kernel or by some other means, such as a system call, for setting up user-space device drivers. Only after both an

InterruptServiceRoutine is registered and a Happening with the same name is started, can that happening be triggered (6–8).




Figure 12.4: Interrupt servicing

There are three main differences between this mechanism and the string based API.

- The Happening class is now a first-class entity, rather than being buried in the implementation and identified only by a String object.
- They include the trigger(int) method that enables a happening to be explicitly triggered by Java code, and at the implementation's option, a native code function that permits native application code to trigger the happening.
- Finally, Happening is a subclass of AsyncEvent just as with Timer instead of having a happening attached to an AsyncEvent.

12.3.4 Interrupt Service Routines

In Java-based systems, JNI is typically used to transfer control between the assembler/C interrupt service routine (ISR) and the program. 2.0 of the RTSJ supports

506 12.3 Semantics

the possibility of the ISR containing Java code. This is clearly an area where it is difficult to maintain the portability goal of Java. Furthermore, not all RTSJ deployments can support InterruptServiceRoutine. A JVM that runs in user space does not generally have access to interrupts.

The JVM must either be standalone, running in a kernel module, or running in a special I/O partition on a partitioning OS where interrupts are passed through using some virtualization technique. Hence, JVM support for ISR is not required for RTSJ compliance.

Interrupt handling is necessarily machine dependent. However, the RTSJ provides an abstract model that can be implemented on top of all architectures.

The following semantic model shall be supported by the RTSJ:

- An occurrence of an interrupt consists of its generation and delivery.
- Generation of the interrupt is the mechanism in the underlying hardware or system that makes the interrupt available to the Java program.
- Delivery is the action that invokes an interrupt service routine (ISR) in response to the occurrence of the interrupt. This may be performed by the JVM or application native code linked with the JVM, or directly by the hardware interrupt mechanism.
- Between generation and delivery, the interrupt is *pending*.
- Some or all interrupt occurrences may be inhibited. While an interrupt occurrence is inhibited, all occurrences of that interrupt shall be prevented from being delivered. Whether such occurrences remain pending or are lost is implementation defined, but it is expected that the implementation shall make a best effort to avoid losing pending interrupts.
- Certain implementation-defined interrupts are reserved. Reserved interrupts are either interrupts for which application-defined ISRs are not supported, or those that already have ISRs by some other implementation-defined means. For example, a clock interrupt, which is used for internal time keeping by the JVM, is a reserved interrupt.
- An application-defined ISR can be registered with one or more non-reserved interrupts. Registering an ISR for an interrupt shall implicitly deregister any already registered ISR for that interrupt. Any daisy-chaining of interrupt handlers shall be performed explicitly by the application interrupt handlers.
- While an ISR is registered to an interrupt, the handle method shall be called once for each delivery of that interrupt. For locking out further interrupts during interrupt handling, the handle method must be synchronized with a priority high enough to lock out the requisite interrupts. This synchronized uses priority ceiling emulation to inhibit the corresponding interrupt (and all lower priority interrupts). The default allocation context of the handle method is the memory area passed during construction.

Any exception propagated from the handle method shall be caught by the JVM and ignored.

• Code running in the context of an ISR may only attempt to acquire a lock that has priority ceiling emulation as its monitor control policy. The behavior is undefined, when an ISR attempt to acquire a lock that has a monitor control policy other than priority ceiling emulation. **Open issue:** jjh: Do we want to support a mechanism of static checking here? **End of open issue**

The model assumes that

- the processor has a (logical) interrupt controller that monitors a number of interrupt lines;
- the interrupt controller may associate each interrupt line with a particular interrupt priority;
- associated with the interrupt lines is a (logical) interrupt vector that contains the addresses of the ISRs;
- the processor has instructions that allow interrupts from a particular line to be disabled/masked irrespective of whether (or the type of) device attached;
- disabling interrupts from a specific line may disables the interrupts from lines of lower priority;
- a device can be connected to an arbitrary interrupt line;
- when an interrupt is signalled on an interrupt line by a device, the processor uses the identity of the interrupt line to index into the interrupt vector and jumps to the address of the ISR; the hardware automatically disables further interrupts (either of the same priority and lower or, possibly, all interrupts);
- on return from the ISR, interrupts are automatically re-enabled.

For each of the interrupt, the RTSJ has an associated hardware priority that can be used to set the ceiling of an ISR object. The RTSJ virtual machine may use this to disable the interrupts from the associated interrupt line and lower priority interrupts, when it is executing a synchronized method of the interrupt-handling object. On a multicore system, the situation is more complex, since there may be other cores available to handle other interrupts, even at lower priorities, and some other locking mechanism may be necessary as well.

Though synchronization is not required in general, it is required to enforce visibility of changes made to any variables shared between some normal Schedulable and a handle method. For the handle method, this may be done automatically by the hardware interrupt handling mechanism or it may require added support from the realtime Java virtual machine. However, for clarity of the model, RTSJ recommends that the handle method should be defined as synchronized.

Support for interrupt handling is encapsulated in the InterruptServiceRoutine abstract class that has two main methods. The first is the final register method that will register an instance of the class with the system so that the appropriate

508 12.3 Semantics

interrupt vector can be initialized. The second is the abstract handle method that provides the code to be executed in response to the interrupt occurring. An individual real-time JVM may place restrictions of the code that can be written in this method. The process is illustrated in Figure 12.4, and is described below.

- 1. The ISR is created by some application real-time thread.
- 2. The created ISR is registered with the JVM, the interrupt id is passed as a parameter.
- 3. As part of the registration process, some internal interface is used to set up the code that will set the underlying interrupt vectors to some C/assembler code that will provide the necessary linkage to allow the callback to the Java handler.
- 4. When the interrupt occurs, the handler is called.

In order to integrate further the interrupt handling with the Java application, the handle method may trigger a happening or fire an event.

Typically an implementation of the RTSJ that supports first-level interrupt handling will document the following items:

- 1. For each interrupt, its identifying integer value, the priority at which the interrupt occurs and whether it can be inhibited or not, and the effects of registering ISRs to non inhibitable interrupts (if this is permitted).
- 2. Which run-time stack the handle method uses when it executes.
- 3. Any implementation- or hardware-specific activity that happens before the handle method is invoked (e.g., reading device registers, acknowledging devices).
- 4. The state (inhibited/uninhibited) of the nonreserved interrupts when the program starts; if some interrupts are uninhibited, what the mechanism is that a program can use to protect itself before it can register the corresponding ISR.
- 5. The treatment of interrupt occurrences that are generated while the interrupt is inhibited; i.e., whether one or more occurrences are held for later delivery, or all are lost.
- 6. Whether predefined or implementation-defined exceptions are raised as a result of the occurrence of any interrupt (for example, a hardware trap resulting from a segmentation error), and the mapping between the interrupt and the predefined exceptions.
- 7. On a multiprocessor, the rules governing the delivery of an interrupt occurrence to a particular processor. For example, whether execution of the handle method may spin if the lock of the associated object is held by another processor.

12.4 Package javax.realtime.device

12.4.1 Interfaces

12.4.1.1 RawByte

A marker for an object that can be used to access to a single byte. Read and write access to that byte is checked by the factory that creates the instance; therefore, no access checking is provided by this interface, only bounds checking.

Available since RTSJ 2.0

Interfaces
RawByteReader
RawByteWriter

12.4.1.2 RawByteReader

A marker for a byte accessor object encapsulating the protocol for reading bytes from raw memory. A byte accessor can always access at least one byte. Each byte is transfered in a single atomic operation. Groups of bytes may be transfered together; however, this is not required.

Objects of this type are created with the method RawMemoryFactory.createRawByteReader¹ and RawMemoryFactory.createRawByte². Each object references a range of elements in the RawMemoryRegion³ starting at the *base address* provided to the factory method. The size provided to the factor method determines the number of elements accessable.

Caching of the memory access is controlled by the factory that created this object. If the memory is not cached, this method guarantees serialized access. In other words, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.

Available since RTSJ 2.0

Interfaces
RawMemory

¹Section 12.4.3.5.3

²Section 12.4.3.5.3

³Section 12.4.3.6

12.4.1.2.1 Methods

getByte

Get the value at the first position referenced by this instance, i.e., the value at its start address. This operation must be atomic with respect to all other raw memory accesses to the address.

```
Signature
    public
    byte getByte()
```

Returns

the value at the *base address* provided to the factory method that created this object.

getByte(int)

Get the value of the n^{th} element referenced by this instance, where n is offset and the address is $base\ address + (offset * stride * element\ size\ in\ bytes)$. When an exception is thrown, no data is transferred.

```
Signature
```

```
public
byte getByte(int offset)
throws OffsetOutOfBoundsException
```

Parameters

offset of byte in the memory region starting from the address specified in the associated factory method.

Throws

OffsetOutOfBoundsException when offset is negative or greater than or equal to the number of elements in the raw memory region.

Returns

the value at the address specified.

get(int, byte[])

Fill the values starting at the address referenced by this instance plus the offset scaled by the element size in bytes and the object's stride. Only the bytes in the intersection of the start and end of values and the base address and the end of the memory region are transferred. When an exception is thrown, no data is transferred.

```
Signature
    public
    int get(int offset, byte[] values)
    throws OffsetOutOfBoundsException, NullPointerException
```

Parameters

offset of the first byte in the memory region to transfere values the array to received the bytes

Throws

OffsetOutOfBoundsException when offset is negative or greater than or equal to the number of elements in the raw memory region.

NullPointerException when values is null.

Returns

the number of elements copied to values

get(int, byte[], int, int)

Fill values with data from the memory region, where offset is first byte in the memory region and start is the first index in values. The number of bytes transfered is the minimum of count, the *size* of the memory region minus offset, and length of values minus start. When an exception is thrown, no data is transfered.

```
public int get(int offset, byte[] values, int start, int count) throws OffsetOutOfBoundsException,
ArrayIndexOutOfBoundsException, NullPointerException

Parameters
offset of the first byte in the memory region to transfere values the array to received the bytes start the first index in array to fill count the maximum number of bytes to copy

Throws
```

OffsetOutOfBoundsException when offset is negative or either offset or offset + count is greater than or equal to the size of this raw memory area. ArrayIndexOutOfBoundsException when start is negative or either start or start + count is greater than or equal to the size of values.

NullPointerException when values is null or count is negative.

Returns

the number of bytes actually transfered.

12.4.1.3 RawByteWriter

A marker for a byte accessor object encapsulating the protocol for writing bytes from raw memory. A byte accessor can always access at least one byte. Each byte is transfered in a single atomic operation. Groups of bytes may be transfered together; however, this is not required.

Objects of this type are created with the method RawMemoryFactory.createRawByteWriter⁴ and RawMemoryFactory.createRawByte⁵. Each object references a range of elements in the RawMemoryRegion⁶ starting at the *base address* provided to the factory method. The size provided to the factor method determines the number of elements accessable.

Caching of the memory access is controlled by the factory that created this object. If the memory is not cached, this method guarantees serialized access. In other words, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.

Available since RTSJ 2.0

Interfaces

RawMemory

12.4.1.3.1 Methods

setByte(byte)

⁴Section 12.4.3.5.3

⁵Section 12.4.3.5.3

 $^{^6\}mathrm{Section}\ 12.4.3.6$

Set the value at the first position referenced by this instance, i.e., the value at its start address. This operation must be atomic with respect to all other raw memory accesses to the address. When an exception is thrown, no data is transfered.

```
Signature

public

void setByte(byte value)
```

setByte(int, byte)

Set the value of the n^{th} element referenced by this instance, where n is offset and the address is base address + offset * size of Byte. This operation must be atomic with respect to all other raw memory accesses to the address. When an exception is thrown, no data is transferred.

```
Signature

public

void setByte(int offset, byte value)

throws OffsetOutOfBoundsException

Parameters

offset of byte in the memory region.

Throws
```

OffsetOutOfBoundsException when offset is negative or greater than or equal to the number of elements in the raw memory region.

set(int, byte[])

Copy values to the raw memory starting at the address referenced by this instance plus the offset scaled by the element size in bytes and the objects stride. Only the bytes in the intersection of values and the end of the memory region are transfered. When an exception is thrown, no data is transfered.

```
Signature
    public
    int set(int offset, byte[] values)
    throws OffsetOutOfBoundsException, NullPointerException
Throws
```

OffsetOutOfBoundsException when offset is negative or greater than or equal to the number of elements in the raw memory region.

NullPointerException when values is null.

Returns

the number of elements copied to values

set(int, byte[], int, int)

Copy values to the memory region, where offset is first byte in the memory region to write and start is the first index in values from which to read. The number of bytes transfered is the minimum of count, the *size* of the memory region minus offset, and length of values minus start. When an exception is thrown, no data is transfered.

```
Signature
```

```
public
int set(int offset, byte[] values, int start, int count)
throws OffsetOutOfBoundsException,
```

 ${\tt ArrayIndexOutOfBoundsException,\ NullPointerException}$

offset of the first byte in the memory region to set values the array from which to retrieve the bytes start the first index in array to fill count the maximum number of bytes to copy

Throws

OffsetOutOfBoundsException when offset is negative or either offset or offset + count is greater than or equal to the size of this raw memory area. ArrayIndexOutOfBoundsException when start is negative or either start or start + count is greater than or equal to the size of values.

NullPointerException when values is null.

Returns

the number of bytes actually transfered.

12.4.1.4 RawDouble

A marker for an object that can be used to access to a single double. Read and write access to that double is checked by the factory that creates the instance; therefore, no access checking is provided by this interface, only bounds checking.

Available since RTSJ 2.0

Interfaces
RawDoubleReader
RawDoubleWriter

12.4.1.5 RawDoubleReader

A marker for a double accessor object encapsulating the protocol for reading doubles from raw memory. A double accessor can always access at least one double. Each double is transfered in a single atomic operation. Groups of doubles may be transfered together; however, this is not required.

Objects of this type are created with the method RawMemoryFactory.createRawDoubleReader⁷ and RawMemoryFactory.createRawDouble⁸. Each object references a range of elements in the RawMemoryRegion⁹ starting at the *base address* provided to the factory method. The size provided to the factor method determines the number of elements accessable.

Caching of the memory access is controlled by the factory that created this object. If the memory is not cached, this method guarantees serialized access. In other words, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.

Available since RTSJ 2.0

Interfaces
RawMemory

12.4.1.5.1 Methods

getDouble

Get the value at the first position referenced by this instance, i.e., the value at its start address. This operation must be atomic with respect to all other raw memory accesses to the address.

⁷Section 12.4.3.5.3

⁸Section 12.4.3.5.3

⁹Section 12.4.3.6

```
Signature

public

double getDouble()
```

Returns

the value at the *base address* provided to the factory method that created this object.

getDouble(int)

Get the value of the \mathbf{n}^{th} element referenced by this instance, where \mathbf{n} is offset and the address is base address + (offset * stride * element size in bytes). When an exception is thrown, no data is transferred.

Signature

```
public
double getDouble(int offset)
throws OffsetOutOfBoundsException
```

Parameters

offset of double in the memory region starting from the address specified in the associated factory method.

Throws

OffsetOutOfBoundsException when offset is negative or greater than or equal to the number of elements in the raw memory region.

Returns

the value at the address specified.

get(int, double[])

Fill the values starting at the address referenced by this instance plus the offset scaled by the element size in bytes and the object's stride. Only the doubles in the intersection of the start and end of values and the base address and the end of the memory region are transfered. When an exception is thrown, no data is transfered.

2.0 (Draft 20)

Signature

```
public
int get(int offset, double[] values)
```

throws OffsetOutOfBoundsException, NullPointerException

Parameters

offset of the first double in the memory region to transfere values the array to received the doubles

Throws

OffsetOutOfBoundsException when offset is negative or greater than or equal to the number of elements in the raw memory region.

NullPointerException when values is null.

Returns

the number of elements copied to values

get(int, double[], int, int)

Fill values with data from the memory region, where offset is first double in the memory region and start is the first index in values. The number of bytes transfered is the minimum of count, the *size* of the memory region minus offset, and length of values minus start. When an exception is thrown, no data is transfered.

Signature

```
public
int get(int offset, double[] values, int start, int count)
throws OffsetOutOfBoundsException,
ArrayIndexOutOfBoundsException, NullPointerException
```


offset of the first double in the memory region to transfere values the array to received the doubles start the first index in array to fill count the maximum number of doubles to copy

Throws

OffsetOutOfBoundsException when offset is negative or either offset or offset + count is greater than or equal to the size of this raw memory area. ArrayIndexOutOfBoundsException when start is negative or either start or start + count is greater than or equal to the size of values.

NullPointerException when values is null or count is negative.

Returns

the number of doubles actually transfered.

12.4.1.6 RawDoubleWriter

A marker for a double accessor object encapsulating the protocol for writing doubles from raw memory. A double accessor can always access at least one double. Each double is transfered in a single atomic operation. Groups of doubles may be transfered together; however, this is not required.

Objects of this type are created with the method RawMemoryFactory.createRawDoubleWriter¹⁰ and RawMemoryFactory.createRawDouble¹¹. Each object references a range of elements in the RawMemoryRegion¹² starting at the *base address* provided to the factory method. The size provided to the factor method determines the number of elements accessable.

Caching of the memory access is controlled by the factory that created this object. If the memory is not cached, this method guarantees serialized access. In other words, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.

Available since RTSJ 2.0

 $\begin{array}{c} Interfaces \\ {\rm RawMemory} \end{array}$

12.4.1.6.1 Methods

setDouble(double)

Set the value at the first position referenced by this instance, i.e., the value at its start address. This operation must be atomic with respect to all other raw memory accesses to the address. When an exception is thrown, no data is transferred.

Signature

public
void setDouble(double value)

¹⁰Section 12.4.3.5.3

¹¹Section 12.4.3.5.3

 $^{^{12}}$ Section 12.4.3.6

setDouble(int, double)

Set the value of the nth element referenced by this instance, where n is offset and the address is base address + offset * size of Double. This operation must be atomic with respect to all other raw memory accesses to the address. When an exception is thrown, no data is transferred.

```
Signature
    void setDouble(int offset, double value)
    throws OffsetOutOfBoundsException
offset of double in the memory region.
```

Throws

OffsetOutOfBoundsException when offset is negative or greater than or equal to the number of elements in the raw memory region.

set(int, double[])

Copy values to the raw memory starting at the address referenced by this instance plus the offset scaled by the element size in bytes and the objects stride. Only the doubles in the intersection of values and the end of the memory region are transfered. When an exception is thrown, no data is transfered.

```
Signature
    public
    int set(int offset, double[] values)
    throws OffsetOutOfBoundsException, NullPointerException
```

Throws

OffsetOutOfBoundsException when offset is negative or greater than or equal to the number of elements in the raw memory region.

NullPointerException when values is null.

Returns

the number of elements copied to values

```
set(int, double[], int, int)
```

Copy values to the memory region, where offset is first double in the memory region to write and start is the first index in values from which to read. The number of bytes transfered is the minimum of count, the *size* of the memory region minus offset, and length of values minus start. When an exception is thrown, no data is transfered.

Signature

public
int set(int offset, double[] values, int start, int count)
throws OffsetOutOfBoundsException,
ArrayIndexOutOfBoundsException, NullPointerException

Parameters 1 4 1

offset of the first double in the memory region to set values the array from which to retrieve the doubles start the first index in array to fill count the maximum number of doubles to copy

Throws

OffsetOutOfBoundsException when offset is negative or either offset or offset + count is greater than or equal to the size of this raw memory area. ArrayIndexOutOfBoundsException when start is negative or either start or start + count is greater than or equal to the size of values. NullPointerException when values is null.

Returns

the number of doubles actually transfered.

12.4.1.7 RawFloat

A marker for an object that can be used to access to a single float. Read and write access to that float is checked by the factory that creates the instance; therefore, no access checking is provided by this interface, only bounds checking.

Available since RTSJ 2.0

Interfaces

RawFloatReader RawFloatWriter

12.4.1.8 RawFloatReader

A marker for a float accessor object encapsulating the protocol for reading floats from raw memory. A float accessor can always access at least one float. Each float is transfered in a single atomic operation. Groups of floats may be transfered together; however, this is not required.

Objects of this type are created with the method RawMemoryFactory.createRawFloatReader¹³ and RawMemoryFactory.createRawFloat¹⁴. Each object references a range of elements in the RawMemoryRegion¹⁵ starting at the *base address* provided to the factory method. The size provided to the factor method determines the number of elements accessable.

Caching of the memory access is controlled by the factory that created this object. If the memory is not cached, this method guarantees serialized access. In other words, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.

Available since RTSJ 2.0

Interfaces
RawMemory

12.4.1.8.1 Methods

getFloat

Get the value at the first position referenced by this instance, i.e., the value at its start address. This operation must be atomic with respect to all other raw memory accesses to the address.

```
Signature

public
float getFloat()

Returns

13Section 12.4.3.5.3
14Section 12.4.3.5.3
15Section 12.4.3.6
```

the value at the *base address* provided to the factory method that created this object.

getFloat(int)

Get the value of the n^{th} element referenced by this instance, where n is offset and the address is base address + (offset * stride * element size in bytes). When an exception is thrown, no data is transferred.

```
Signature
```

```
public
float getFloat(int offset)
throws OffsetOutOfBoundsException
```

Parameters

offset of float in the memory region starting from the address specified in the associated factory method.

Throws

OffsetOutOfBoundsException when offset is negative or greater than or equal to the number of elements in the raw memory region.

Returns

the value at the address specified.

get(int, float[])

Fill the values starting at the address referenced by this instance plus the offset scaled by the element size in bytes and the object's stride. Only the floats in the intersection of the start and end of values and the base address and the end of the memory region are transfered. When an exception is thrown, no data is transfered.

```
Signature
```

```
public
int get(int offset, float[] values)
throws OffsetOutOfBoundsException, NullPointerException
```

Parameters

offset of the first float in the memory region to transfere values the array to received the floats

Throws

OffsetOutOfBoundsException when offset is negative or greater than or equal to the number of elements in the raw memory region.

NullPointerException when values is null.

Returns

the number of elements copied to values

get(int, float[], int, int)

Fill values with data from the memory region, where offset is first float in the memory region and start is the first index in values. The number of bytes transfered is the minimum of count, the *size* of the memory region minus offset, and length of values minus start. When an exception is thrown, no data is transfered.

Signature

public

int get(int offset, float[] values, int start, int count)

throws OffsetOutOfBoundsException,

ArrayIndexOutOfBoundsException, NullPointerException

Parameters 1

 $\it offset$ of the first float in the memory region to transfere

values the array to received the floats

start the first index in array to fill

count the maximum number of floats to copy

Throws

OffsetOutOfBoundsException when offset is negative or either offset or offset + count is greater than or equal to the size of this raw memory area. ArrayIndexOutOfBoundsException when start is negative or either start or start + count is greater than or equal to the size of values.

NullPointerException when values is null or count is negative.

Returns

the number of floats actually transfered.

12.4.1.9 RawFloatWriter

A marker for a float accessor object encapsulating the protocol for writing floats from raw memory. A float accessor can always access at least one float. Each

float is transferred in a single atomic operation. Groups of floats may be transferred together; however, this is not required.

Objects of this type are created with the method RawMemoryFactory.createRawFloatWriter¹⁶ and RawMemoryFactory.createRawFloat¹⁷. Each object references a range of elements in the RawMemoryRegion¹⁸ starting at the *base address* provided to the factory method. The size provided to the factor method determines the number of elements accessable.

Caching of the memory access is controlled by the factory that created this object. If the memory is not cached, this method guarantees serialized access. In other words, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.

Available since RTSJ 2.0

 $\begin{array}{c} Interfaces \\ Raw Memory \end{array}$

12.4.1.9.1 Methods

setFloat(float)

Set the value at the first position referenced by this instance, i.e., the value at its start address. This operation must be atomic with respect to all other raw memory accesses to the address. When an exception is thrown, no data is transfered.

```
Signature

public

void setFloat(float value)
```

setFloat(int, float)

Set the value of the \mathbf{n}^{th} element referenced by this instance, where \mathbf{n} is offset and the address is base address + offset * size of Float. This operation must be atomic with respect to all other raw memory accesses to the address. When an exception is thrown, no data is transferred.

¹⁶Section 12.4.3.5.3

 $^{^{17}}$ Section 12.4.3.5.3

 $^{^{18}}$ Section 12.4.3.6

```
Signature

public

void setFloat(int offset, float value)

throws OffsetOutOfBoundsException

Parameters

offset of float in the memory region.
```

Throws

OffsetOutOfBoundsException when offset is negative or greater than or equal to the number of elements in the raw memory region.

set(int, float[])

Copy values to the raw memory starting at the address referenced by this instance plus the offset scaled by the element size in bytes and the objects stride. Only the floats in the intersection of values and the end of the memory region are transfered. When an exception is thrown, no data is transfered.

```
Signature
    public
    int set(int offset, float[] values)
    throws OffsetOutOfBoundsException, NullPointerException
Throws
```

OffsetOutOfBoundsException when offset is negative or greater than or equal to the number of elements in the raw memory region.

NullPointerException when values is null.

Returns

the number of elements copied to values

set(int, float[], int, int)

Copy values to the memory region, where offset is first float in the memory region to write and start is the first index in values from which to read. The number of bytes transfered is the minimum of count, the *size* of the memory region minus offset, and length of values minus start. When an exception is thrown, no data is transfered.

Signature

public
int set(int offset, float[] values, int start, int count)
throws OffsetOutOfBoundsException,

ArrayIndexOutOfBoundsException, NullPointerException

Parameters

offset of the first float in the memory region to set values the array from which to retrieve the floats start the first index in array to fill count the maximum number of floats to copy

Throws

OffsetOutOfBoundsException when offset is negative or either offset or offset + count is greater than or equal to the size of this raw memory area. ArrayIndexOutOfBoundsException when start is negative or either start or start + count is greater than or equal to the size of values.

NullPointerException when values is null.

Returns

the number of floats actually transfered.

12.4.1.10 RawInt

A marker for an object that can be used to access to a single int. Read and write access to that int is checked by the factory that creates the instance; therefore, no access checking is provided by this interface, only bounds checking.

Available since RTSJ 2.0

Interfaces

RawIntReader RawIntWriter

12.4.1.11 RawIntReader

A marker for a int accessor object encapsulating the protocol for reading ints from raw memory. A int accessor can always access at least one int. Each int is transfered in a single atomic operation. Groups of ints may be transfered together; however, this is not required.

Objects of this type are created with the method RawMemoryFactory.createRawIntReader¹⁹ and RawMemoryFactory.createRawInt²⁰. Each object references a range of elements in the RawMemoryRegion²¹ starting at the *base address* provided to the factory method. The size provided to the factor method determines the number of elements accessable.

Caching of the memory access is controlled by the factory that created this object. If the memory is not cached, this method guarantees serialized access. In other words, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.

Available since RTSJ 2.0

```
Interfaces
RawMemory
```

12.4.1.11.1 Methods

getInt

Get the value at the first position referenced by this instance, i.e., the value at its start address. This operation must be atomic with respect to all other raw memory accesses to the address.

```
Signature
    public
    int getInt()
```

Returns

the value at the *base address* provided to the factory method that created this object.

getInt(int)

Get the value of the n^{th} element referenced by this instance, where n is offset and the address is $base\ address + (offset * stride * element\ size\ in\ bytes)$. When an exception is thrown, no data is transferred.

¹⁹Section 12.4.3.5.3

 $^{^{20}}$ Section 12.4.3.5.3

 $^{^{21}}$ Section 12.4.3.6

Signature

```
public
int getInt(int offset)
throws OffsetOutOfBoundsException
```

Parameters

offset of int in the memory region starting from the address specified in the associated factory method.

Throws

OffsetOutOfBoundsException when offset is negative or greater than or equal to the number of elements in the raw memory region.

Returns

the value at the address specified.

get(int, int[])

Fill the values starting at the address referenced by this instance plus the offset scaled by the element size in bytes and the object's stride. Only the ints in the intersection of the start and end of values and the base address and the end of the memory region are transfered. When an exception is thrown, no data is transfered.

Signature

```
public
int get(int offset, int[] values)
throws OffsetOutOfBoundsException, NullPointerException
```

Parameters 1 4 1

offset of the first int in the memory region to transfere values the array to received the ints

Throws

OffsetOutOfBoundsException when offset is negative or greater than or equal to the number of elements in the raw memory region.

NullPointerException when values is null.

Returns

the number of elements copied to values

get(int, int[], int, int)

Fill values with data from the memory region, where offset is first int in the memory region and start is the first index in values. The number of bytes transfered is the minimum of count, the *size* of the memory region minus offset, and length of values minus start. When an exception is thrown, no data is transfered.

Signature

public
int get(int offset, int[] values, int start, int count)
throws OffsetOutOfBoundsException,
ArrayIndexOutOfBoundsException, NullPointerException

Parameters

offset of the first int in the memory region to transfere values the array to received the ints start the first index in array to fill count the maximum number of ints to copy

Throws

OffsetOutOfBoundsException when offset is negative or either offset or offset + count is greater than or equal to the size of this raw memory area. ArrayIndexOutOfBoundsException when start is negative or either start or start + count is greater than or equal to the size of values.

NullPointerException when values is null or count is negative.

Returns

the number of ints actually transfered.

12.4.1.12 RawIntWriter

A marker for a int accessor object encapsulating the protocol for writing ints from raw memory. A int accessor can always access at least one int. Each int is transfered in a single atomic operation. Groups of ints may be transfered together; however, this is not required.

Objects of this type are created with the method RawMemoryFactory.createRawIntWriter²² and RawMemoryFactory.createRawInt²³. Each object references a range of elements in the RawMemoryRegion²⁴ starting at the *base address* provided to the factory

²²Section 12.4.3.5.3

 $^{^{23}}$ Section 12.4.3.5.3

 $^{^{24}\}mathrm{Section}\ 12.4.3.6$

method. The size provided to the factor method determines the number of elements accessable.

Caching of the memory access is controlled by the factory that created this object. If the memory is not cached, this method guarantees serialized access. In other words, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.

Available since RTSJ 2.0

Interfaces
RawMemory

12.4.1.12.1 Methods

setInt(int)

Set the value at the first position referenced by this instance, i.e., the value at its start address. This operation must be atomic with respect to all other raw memory accesses to the address. When an exception is thrown, no data is transfered.

```
public
    void setInt(int value)

setInt(int, int)
```

Set the value of the \mathbf{n}^{th} element referenced by this instance, where \mathbf{n} is offset and the address is base address + offset * size of Int. This operation must be atomic with respect to all other raw memory accesses to the address. When an exception is thrown, no data is transferred.

```
public
void setInt(int offset, int value)
throws OffsetOutOfBoundsException

Parameters
offset of int in the memory region.

2.0 (Draft 20)
```

Throws

OffsetOutOfBoundsException when offset is negative or greater than or equal to the number of elements in the raw memory region.

set(int, int[])

Copy values to the raw memory starting at the address referenced by this instance plus the offset scaled by the element size in bytes and the objects stride. Only the ints in the intersection of values and the end of the memory region are transfered. When an exception is thrown, no data is transfered.

```
Signature
```

```
public
int set(int offset, int[] values)
throws OffsetOutOfBoundsException, NullPointerException
```

Throws

OffsetOutOfBoundsException when offset is negative or greater than or equal to the number of elements in the raw memory region.

NullPointerException when values is null.

Returns

the number of elements copied to values

set(int, int[], int, int)

Copy values to the memory region, where offset is first int in the memory region to write and start is the first index in values from which to read. The number of bytes transfered is the minimum of count, the *size* of the memory region minus offset, and length of values minus start. When an exception is thrown, no data is transfered.

Signature

```
public
  int set(int offset, int[] values, int start, int count)
  throws OffsetOutOfBoundsException,
  ArrayIndexOutOfBoundsException, NullPointerException

Parameters
  offset of the first int in the memory region to set
  values the array from which to retrieve the ints
```

start the first index in array to fill count the maximum number of ints to copy

Throws

OffsetOutOfBoundsException when offset is negative or either offset or offset + count is greater than or equal to the size of this raw memory area. ArrayIndexOutOfBoundsException when start is negative or either start or start + count is greater than or equal to the size of values.

NullPointerException when values is null.

Returns

the number of ints actually transfered.

12.4.1.13 RawLong

A marker for an object that can be used to access to a single long. Read and write access to that long is checked by the factory that creates the instance; therefore, no access checking is provided by this interface, only bounds checking.

Available since RTSJ 2.0

Interfaces
RawLongReader

RawLongReader RawLongWriter

12.4.1.14 RawLongReader

A marker for a long accessor object encapsulating the protocol for reading longs from raw memory. A long accessor can always access at least one long. Each long is transfered in a single atomic operation. Groups of longs may be transfered together; however, this is not required.

Objects of this type are created with the method RawMemoryFactory.createRawLongReader²⁵ and RawMemoryFactory.createRawLong²⁶. Each object references a range of elements in the RawMemoryRegion²⁷ starting at the *base address* provided to the factory method. The size provided to the factor method determines the number of elements accessable.

 $^{^{25}}$ Section 12.4.3.5.3

 $^{^{26}}$ Section 12.4.3.5.3

 $^{^{27}}$ Section 12.4.3.6

Caching of the memory access is controlled by the factory that created this object. If the memory is not cached, this method guarantees serialized access. In other words, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.

Available since RTSJ 2.0

Interfaces
RawMemory

12.4.1.14.1 Methods

getLong

Get the value at the first position referenced by this instance, i.e., the value at its start address. This operation must be atomic with respect to all other raw memory accesses to the address.

```
Signature

public
long getLong()

Returns
```

the value at the *base address* provided to the factory method that created this object.

getLong(int)

Get the value of the n^{th} element referenced by this instance, where n is offset and the address is base address + (offset * stride * element size in bytes). When an exception is thrown, no data is transferred.

```
Signature

public
long getLong(int offset)
throws OffsetOutOfBoundsException
Parameters
```

offset of long in the memory region starting from the address specified in the associated factory method.

Throws

OffsetOutOfBoundsException when offset is negative or greater than or equal to the number of elements in the raw memory region.

Returns

the value at the address specified.

get(int, long[])

Fill the values starting at the address referenced by this instance plus the offset scaled by the element size in bytes and the object's **stride**. Only the longs in the intersection of the start and end of values and the *base address* and the end of the memory region are transfered. When an exception is thrown, no data is transfered.

```
Signature
```

```
public
int get(int offset, long[] values)
throws OffsetOutOfBoundsException, NullPointerException
```

Parameters 1 4 1

offset of the first long in the memory region to transfere values the array to received the longs

Throws

OffsetOutOfBoundsException when offset is negative or greater than or equal to the number of elements in the raw memory region.

NullPointerException when values is null.

Returns

the number of elements copied to values

get(int, long[], int, int)

Fill values with data from the memory region, where offset is first long in the memory region and start is the first index in values. The number of bytes transfered is the minimum of count, the *size* of the memory region minus offset, and length of values minus start. When an exception is thrown, no data is transfered.

Signature

public
int get(int offset, long[] values, int start, int count)
throws OffsetOutOfBoundsException,
ArrayIndexOutOfBoundsException, NullPointerException

Parameters

offset of the first long in the memory region to transfere values the array to received the longs start the first index in array to fill count the maximum number of longs to copy

Throws

OffsetOutOfBoundsException when offset is negative or either offset or offset + count is greater than or equal to the size of this raw memory area. ArrayIndexOutOfBoundsException when start is negative or either start or start + count is greater than or equal to the size of values.

NullPointerException when values is null or count is negative.

Returns

the number of longs actually transferred.

12.4.1.15 RawLongWriter

A marker for a long accessor object encapsulating the protocol for writing longs from raw memory. A long accessor can always access at least one long. Each long is transfered in a single atomic operation. Groups of longs may be transfered together; however, this is not required.

Objects of this type are created with the method RawMemoryFactory.createRawLongWriter²⁸ and RawMemoryFactory.createRawLong²⁹. Each object references a range of elements in the RawMemoryRegion³⁰ starting at the *base address* provided to the factory method. The size provided to the factor method determines the number of elements accessable.

Caching of the memory access is controlled by the factory that created this object. If the memory is not cached, this method guarantees serialized access. In other words, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.

Available since RTSJ 2.0

Interfaces

 28 Section 12.4.3.5.3

 $^{^{29}}$ Section 12.4.3.5.3

RawMemory

12.4.1.15.1 Methods

setLong(long)

Set the value at the first position referenced by this instance, i.e., the value at its start address. This operation must be atomic with respect to all other raw memory accesses to the address. When an exception is thrown, no data is transferred.

```
Signature

public

void setLong(long value)
```

setLong(int, long)

Set the value of the \mathbf{n}^{th} element referenced by this instance, where \mathbf{n} is offset and the address is base address + offset * size of Long. This operation must be atomic with respect to all other raw memory accesses to the address. When an exception is thrown, no data is transferred.

```
Signature

public

void setLong(int offset, long value)

throws OffsetOutOfBoundsException

Parameters

offset of long in the memory region.

Throws
```

OffsetOutOfBoundsException when offset is negative or greater than or equal to the number of elements in the raw memory region.

set(int, long[])

Copy values to the raw memory starting at the address referenced by this instance plus the offset scaled by the element size in bytes and the objects stride.

2.0 (Draft 20)

Only the longs in the intersection of values and the end of the memory region are transfered. When an exception is thrown, no data is transfered.

```
Signature
```

```
public
int set(int offset, long[] values)
throws OffsetOutOfBoundsException, NullPointerException
```

Throws

OffsetOutOfBoundsException when offset is negative or greater than or equal to the number of elements in the raw memory region.

NullPointerException when values is null.

Returns

the number of elements copied to values

set(int, long[], int, int)

Copy values to the memory region, where offset is first long in the memory region to write and start is the first index in values from which to read. The number of bytes transfered is the minimum of count, the *size* of the memory region minus offset, and length of values minus start. When an exception is thrown, no data is transfered.

Signature

```
public
int set(int offset, long[] values, int start, int count)
throws OffsetOutOfBoundsException,
```

ArrayIndexOutOfBoundsException, NullPointerException

Parameters 1 4 1

```
offset of the first long in the memory region to set values the array from which to retrieve the longs start the first index in array to fill count the maximum number of longs to copy
```

Throws

OffsetOutOfBoundsException when offset is negative or either offset or offset + count is greater than or equal to the size of this raw memory area. ArrayIndexOutOfBoundsException when start is negative or either start or start + count is greater than or equal to the size of values.

NullPointerException when values is null.

Returns

the number of longs actually transfered.

12.4.1.16 RawMemory

A marker for all raw memory accessor objects.

Available since RTSJ 2.0

12.4.1.16.1 Methods

getAddress

Get the base physical address of this object.

```
Signature

public

long getAddress()

Returns
```

the first physical address this raw memory object can access.

getSize

Get the number of bytes that this object spans.

```
Signature

public

int getSize()

Returns

the size of this raw memory
```

getStride

Get the distance between elements in multiples of element size.

2.0 (Draft 20)

```
Signature

public

int getStride()

Returns

the span between elements of this raw memory
```

12.4.1.17 RawMemoryRegionFactory

A class to give an application the ability to provide support for a RawMemoryRegion³¹ that is not already provided by the standard. An instance of this call can be registered with a RawMemoryFactory³² and provides the object that that factory should return for a given

Available since RTSJ 2.0

12.4.1.17.1 Methods

getRegion

Get the region for which this factory creates raw memory objects.

```
Signature
    public
    javax.realtime.device.RawMemoryRegion getRegion()
```

getName

Get the name of the region for which this factory creates raw memory objects.

Signature

³¹Section 12.4.3.6 ³²Section 12.4.3.5

```
public
java.lang.String getName()
```

createRawByte(long, int, int)

Create an instance of a class that implements RawByte³³ and accesses memory of getRegion³⁴ in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of RawByte * count. The object is allocated in the current memory area of the calling thread.

Available since RTSJ 2.0

Signature

```
public
javax.realtime.device.RawByte createRawByte(long base, int
count, int stride)
throws SecurityException, OffsetOutOfBoundsException,
SizeOutOfBoundsException, UnsupportedRawMemoryRegionException,
MemoryTypeConflictException
```

Parameters

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

stride The distance to the next element in mulitple of element count, where a value of 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is not greater than zero.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

Memory Type Conflict Exception when base does not point to memory that matches the type served by this factory.

Returns

an object that implements RawByte³⁵ and supports access to the specified

³³Section 12.4.1.1 ³⁴Section 12.4.1.17.1

³⁵Section 12.4.1.1

range in the memory region.

createRawByteReader(long, int, int)

MemoryTypeConflictException

Create an instance of a class that implements RawByteReader³⁶ and accesses memory of getRegion³⁷ in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of Raw-ByteReader * count. The object is allocated in the current memory area of the calling thread.

Available since RTSJ 2.0

Signature

```
public
javax.realtime.device.RawByteReader createRawByteReader(long
base, int count, int stride)
throws SecurityException, OffsetOutOfBoundsException,
SizeOutOfBoundsException, UnsupportedRawMemoryRegionException,
```

Parameters 1

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

stride The distance to the next element in mulitple of element count, where a value of 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is not greater than zero.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

Memory Type Conflict Exception when base does not point to memory that matches the type served by this factory.

Returns

³⁶Section 12.4.1.2 ³⁷Section 12.4.1.17.1

an object that implements RawByteReader³⁸ and supports access to the specified range in the memory region.

createRawByteWriter(long, int, int)

Create an instance of a class that implements RawByteWriter³⁹ and accesses memory of $getRegion^{40}$ in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of Raw-ByteWriter * count. The object is allocated in the current memory area of the calling thread.

Available since RTSJ 2.0

Signature

public

javax.realtime.device.RawByteWriter createRawByteWriter(long base, int count, int stride)

throws SecurityException, OffsetOutOfBoundsException,

 ${\tt SizeOutOfBoundsException,\ UnsupportedRawMemoryRegionException,}$

MemoryTypeConflictException

Parameters

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance

stride The distance to the next element in mulitple of element count, where a value of 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is not greater than zero.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

Memory Type Conflict Exception when base does not point to memory that matches the type served by this factory.

 $^{^{38}}$ Section 12.4.1.2

 $^{^{39}}$ Section 12.4.1.3

⁴⁰Section 12.4.1.17.1

Returns

an object that implements RawByteWriter⁴¹ and supports access to the specified range in the memory region.

createRawShort(long, int, int)

Create an instance of a class that implements $RawShort^{42}$ and accesses memory of $getRegion^{43}$ in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of RawShort * count. The object is allocated in the current memory area of the calling thread.

Available since RTSJ 2.0

Signature

```
public
javax.realtime.device.RawShort createRawShort(long base, int
count, int stride)
throws SecurityException, OffsetOutOfBoundsException,
SizeOutOfBoundsException, UnsupportedRawMemoryRegionException,
MemoryTypeConflictException
```

Parameters

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance

stride The distance to the next element in mulitple of element count, where a value of 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is not greater than zero.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

MemoryTypeConflictException when base does not point to memory that matches the type served by this factory.

⁴¹Section 12.4.1.3

⁴²Section 12.4.1.18

⁴³Section 12.4.1.17.1

Returns

an object that implements $RawShort^{44}$ and supports access to the specified range in the memory region.

createRawShortReader(long, int, int)

Create an instance of a class that implements RawShortReader⁴⁵ and accesses memory of getRegion⁴⁶ in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of Raw-ShortReader * count. The object is allocated in the current memory area of the calling thread.

Available since RTSJ 2.0

Signature

```
public
javax.realtime.device.RawShortReader createRawShortReader(long
base, int count, int stride)
throws SecurityException, OffsetOutOfBoundsException,
SizeOutOfBoundsException, UnsupportedRawMemoryRegionException,
MemoryTypeConflictException
```


base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

stride The distance to the next element in mulitple of element count, where a value of 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is not greater than zero.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

⁴⁴Section 12.4.1.18

 $^{^{45}}$ Section 12.4.1.19

 $^{^{46}}$ Section 12.4.1.17.1

MemoryTypeConflictException when base does not point to memory that matches the type served by this factory.

Returns

an object that implements RawShortReader⁴⁷ and supports access to the specified range in the memory region.

createRawShortWriter(long, int, int)

Create an instance of a class that implements RawShortWriter⁴⁸ and accesses memory of getRegion⁴⁹ in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of Raw-ShortWriter * count. The object is allocated in the current memory area of the calling thread.

Available since RTSJ 2.0

Signature

```
public
javax.realtime.device.RawShortWriter createRawShortWriter(long
base, int count, int stride)
throws SecurityException, OffsetOutOfBoundsException,
SizeOutOfBoundsException, UnsupportedRawMemoryRegionException,
MemoryTypeConflictException
```


base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

stride The distance to the next element in mulitple of element count, where a value of 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is not greater than zero.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

⁴⁷Section 12.4.1.19 ⁴⁸Section 12.4.1.20

⁴⁹Section 12.4.1.17.1

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

Memory Type Conflict Exception when base does not point to memory that matches the type served by this factory.

Returns

an object that implements RawShortWriter⁵⁰ and supports access to the specified range in the memory region.

createRawInt(long, int, int)

Create an instance of a class that implements \mathtt{RawInt}^{51} and accesses memory of $\mathtt{getRegion}^{52}$ in the address range described by base, \mathtt{stride} , and \mathtt{count} . The actual extent of the memory addressed by the object is $\mathtt{stride} * \mathit{size}$ of $RawInt * \mathtt{count}$. The object is allocated in the current memory area of the calling thread.

Available since RTSJ 2.0

Signature

```
public
javax.realtime.device.RawInt createRawInt(long base, int count,
int stride)
throws SecurityException, OffsetOutOfBoundsException,
SizeOutOfBoundsException, UnsupportedRawMemoryRegionException,
MemoryTypeConflictException
```

Parameters

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

stride The distance to the next element in mulitple of element count, where a value of 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is not greater than zero.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

```
<sup>50</sup>Section 12.4.1.20
<sup>51</sup>Section 12.4.1.10
```

⁵²Section 12.4.1.17.1

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

Memory Type Conflict Exception when base does not point to memory that matches the type served by this factory.

Returns

an object that implements ${\tt RawInt}^{53}$ and supports access to the specified range in the memory region.

createRawIntReader(long, int, int)

Create an instance of a class that implements RawIntReader⁵⁴ and accesses memory of getRegion⁵⁵ in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of RawIntReader * count. The object is allocated in the current memory area of the calling thread.

Available since RTSJ 2.0

Signature

```
public
javax.realtime.device.RawIntReader createRawIntReader(long base,
int count, int stride)
throws SecurityException, OffsetOutOfBoundsException,
SizeOutOfBoundsException, UnsupportedRawMemoryRegionException,
MemoryTypeConflictException
```

Parameters

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

stride The distance to the next element in mulitple of element count, where a value of 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is not greater than zero.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

⁵³Section 12.4.1.10 ⁵⁴Section 12.4.1.11

⁵⁵Section 12.4.1.17.1

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

Memory Type Conflict Exception when base does not point to memory that matches the type served by this factory.

Returns

an object that implements RawIntReader⁵⁶ and supports access to the specified range in the memory region.

createRawIntWriter(long, int, int)

Create an instance of a class that implements RawIntWriter⁵⁷ and accesses memory of getRegion⁵⁸ in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of RawIntWriter * count. The object is allocated in the current memory area of the calling thread.

Available since RTSJ 2.0

Signature

```
public
javax.realtime.device.RawIntWriter createRawIntWriter(long base,
int count, int stride)
throws SecurityException, OffsetOutOfBoundsException,
SizeOutOfBoundsException, UnsupportedRawMemoryRegionException,
MemoryTypeConflictException
```

Parameters

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

stride The distance to the next element in mulitple of element count, where a value of 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is not greater than zero.

⁵⁶Section 12.4.1.11 ⁵⁷Section 12.4.1.12 ⁵⁸Section 12.4.1.17.1

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

Memory Type Conflict Exception when base does not point to memory that matches the type served by this factory.

Returns

an object that implements RawIntWriter⁵⁹ and supports access to the specified range in the memory region.

createRawLong(long, int, int)

Create an instance of a class that implements RawLong⁶⁰ and accesses memory of getRegion⁶¹ in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of RawLong * count. The object is allocated in the current memory area of the calling thread.

Available since RTSJ 2.0

Signature

```
public
javax.realtime.device.RawLong createRawLong(long base, int
count, int stride)
throws SecurityException, OffsetOutOfBoundsException,
SizeOutOfBoundsException, UnsupportedRawMemoryRegionException,
MemoryTypeConflictException
```

Parameters

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

stride The distance to the next element in mulitple of element count, where a value of 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is not greater than zero.

⁵⁹Section 12.4.1.12 ⁶⁰Section 12.4.1.13 ⁶¹Section 12.4.1.17.1

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

Memory Type Conflict Exception when base does not point to memory that matches the type served by this factory.

Returns

an object that implements $RawLong^{62}$ and supports access to the specified range in the memory region.

createRawLongReader(long, int, int)

Create an instance of a class that implements $RawLongReader^{63}$ and accesses memory of $getRegion^{64}$ in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of Raw-LongReader * count. The object is allocated in the current memory area of the calling thread.

Available since RTSJ 2.0

Signature

```
public
javax.realtime.device.RawLongReader createRawLongReader(long
base, int count, int stride)
throws SecurityException, OffsetOutOfBoundsException,
SizeOutOfBoundsException, UnsupportedRawMemoryRegionException,
MemoryTypeConflictException
```

Parameters

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

stride The distance to the next element in mulitple of element count, where a value of 1 means the elements are adjacent in memory.

Throws

⁶²Section 12.4.1.13 ⁶³Section 12.4.1.14 ⁶⁴Section 12.4.1.17.1 IllegalArgumentException when base is negative, count is not greater than zero, or stride is not greater than zero.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

MemoryTypeConflictException when base does not point to memory that matches the type served by this factory.

Returns

an object that implements RawLongReader⁶⁵ and supports access to the specified range in the memory region.

createRawLongWriter(long, int, int)

Create an instance of a class that implements RawLongWriter⁶⁶ and accesses memory of getRegion⁶⁷ in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of Raw-LongWriter * count. The object is allocated in the current memory area of the calling thread.

Available since RTSJ 2.0

Signature

```
public
javax.realtime.device.RawLongWriter createRawLongWriter(long
base, int count, int stride)
throws SecurityException, OffsetOutOfBoundsException,
SizeOutOfBoundsException, UnsupportedRawMemoryRegionException,
MemoryTypeConflictException
```

Parameters

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

stride The distance to the next element in mulitple of element count, where a value of 1 means the elements are adjacent in memory.

⁶⁵Section 12.4.1.14 ⁶⁶Section 12.4.1.15

⁶⁷Section 12.4.1.17.1

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is not greater than zero.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

Memory Type Conflict Exception when base does not point to memory that matches the type served by this factory.

Returns

an object that implements RawLongWriter⁶⁸ and supports access to the specified range in the memory region.

createRawFloat(long, int, int)

Create an instance of a class that implements RawFloat⁶⁹ and accesses memory of getRegion⁷⁰ in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of RawFloat * count. The object is allocated in the current memory area of the calling thread.

Available since RTSJ 2.0

Signature

```
public
javax.realtime.device.RawFloat createRawFloat(long base, int
count, int stride)
throws SecurityException, OffsetOutOfBoundsException,
SizeOutOfBoundsException, UnsupportedRawMemoryRegionException,
MemoryTypeConflictException
```

Parameters

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

stride The distance to the next element in mulitple of element count, where a value of 1 means the elements are adjacent in memory.

⁶⁸Section 12.4.1.15

 $^{^{69}}$ Section 12.4.1.7

⁷⁰Section 12.4.1.17.1

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is not greater than zero.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

Memory Type Conflict Exception when base does not point to memory that matches the type served by this factory.

Returns

an object that implements RawFloat⁷¹ and supports access to the specified range in the memory region.

createRawFloatReader(long, int, int)

Create an instance of a class that implements $RawFloatReader^{72}$ and accesses memory of $getRegion^{73}$ in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride*size of RawFloatReader*count. The object is allocated in the current memory area of the calling thread.

Available since RTSJ 2.0

Signature

```
public
```

javax.realtime.device.RawFloatReader createRawFloatReader(long base, int count, int stride)

throws SecurityException, OffsetOutOfBoundsException,

 ${\tt SizeOutOfBoundsException,\ UnsupportedRawMemoryRegionException,}$

MemoryTypeConflictException

Parameters 1

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

⁷¹Section 12.4.1.7

 $^{^{72}}$ Section 12.4.1.8

 $^{^{73}}$ Section 12.4.1.17.1

stride The distance to the next element in mulitple of element count, where a value of 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is not greater than zero.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

Memory Type Conflict Exception when base does not point to memory that matches the type served by this factory.

Returns

an object that implements $RawFloatReader^{74}$ and supports access to the specified range in the memory region.

createRawFloatWriter(long, int, int)

Create an instance of a class that implements RawFloatWriter 75 and accesses memory of getRegion 76 in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of RawFloatWriter * count. The object is allocated in the current memory area of the calling thread.

Available since RTSJ 2.0

Signature

public javax.realtime.device.RawFloatWriter createRawFloatWriter(long base, int count, int stride) throws SecurityException, OffsetOutOfBoundsException, SizeOutOfBoundsException, UnsupportedRawMemoryRegionException, MemoryTypeConflictException

Parameters

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

⁷⁴Section 12.4.1.8

⁷⁵Section 12.4.1.9

⁷⁶Section 12.4.1.17.1

stride The distance to the next element in mulitple of element count, where a value of 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is not greater than zero.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

Memory Type Conflict Exception when base does not point to memory that matches the type served by this factory.

Returns

an object that implements RawFloatWriter⁷⁷ and supports access to the specified range in the memory region.

createRawDouble(long, int, int)

Create an instance of a class that implements RawDouble⁷⁸ and accesses memory of getRegion⁷⁹ in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of RawDouble * count. The object is allocated in the current memory area of the calling thread.

Available since RTSJ 2.0

Signature

```
public
javax.realtime.device.RawDouble createRawDouble(long base, int
count, int stride)
throws SecurityException, OffsetOutOfBoundsException,
SizeOutOfBoundsException, UnsupportedRawMemoryRegionException,
MemoryTypeConflictException
```


base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

⁷⁷Section 12.4.1.9

⁷⁸Section 12.4.1.4

⁷⁹Section 12.4.1.17.1

stride The distance to the next element in mulitple of element count, where a value of 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is not greater than zero.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

Memory Type Conflict Exception when base does not point to memory that matches the type served by this factory.

Returns

an object that implements RawDouble⁸⁰ and supports access to the specified range in the memory region.

createRawDoubleReader(long, int, int)

Create an instance of a class that implements RawDoubleReader⁸¹ and accesses memory of getRegion⁸² in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of Raw-DoubleReader * count. The object is allocated in the current memory area of the calling thread.

Available since RTSJ 2.0

Signature

```
public
  javax.realtime.device.RawDoubleReader createRawDoubleReader(long
  base, int count, int stride)
  throws SecurityException, OffsetOutOfBoundsException,
  SizeOutOfBoundsException, UnsupportedRawMemoryRegionException,
  MemoryTypeConflictException
```

Parameters

base The starting physical address accessible through the returned instance.

⁸⁰Section 12.4.1.4 ⁸¹Section 12.4.1.5 ⁸²Section 12.4.1.17.1

^{2.0 (}Draft 20)

count The number of memory elements accessible through the returned instance.

stride The distance to the next element in mulitple of element count, where a value of 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is not greater than zero.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

Memory Type Conflict Exception when base does not point to memory that matches the type served by this factory.

Returns

an object that implements RawDoubleReader⁸³ and supports access to the specified range in the memory region.

createRawDoubleWriter(long, int, int)

Create an instance of a class that implements RawDoubleWriter⁸⁴ and accesses memory of getRegion⁸⁵ in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of Raw-DoubleWriter * count. The object is allocated in the current memory area of the calling thread.

Available since RTSJ 2.0

```
Signature
```

```
public
javax.realtime.device.RawDoubleWriter createRawDoubleWriter(long
base, int count, int stride)
throws SecurityException, OffsetOutOfBoundsException,
SizeOutOfBoundsException, UnsupportedRawMemoryRegionException,
MemoryTypeConflictException
```

Parameters

⁸³ Section 12.4.1.5 84 Section 12.4.1.6 85 Section 12.4.1.17.1

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

stride The distance to the next element in mulitple of element count, where a value of 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is not greater than zero.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

Memory Type Conflict Exception when base does not point to memory that matches the type served by this factory.

Returns

an object that implements RawDoubleWriter⁸⁶ and supports access to the specified range in the memory region.

12.4.1.18 RawShort

A marker for an object that can be used to access to a single short. Read and write access to that short is checked by the factory that creates the instance; therefore, no access checking is provided by this interface, only bounds checking.

Available since RTSJ 2.0

Interfaces

RawShortWriter RawShortWriter

12.4.1.19 RawShortReader

A marker for a short accessor object encapsulating the protocol for reading shorts from raw memory. A short accessor can always access at least one short. Each short is transfered in a single atomic operation. Groups of shorts may be transfered together; however, this is not required.

⁸⁶Section 12.4.1.6

Objects of this type are created with the method RawMemoryFactory.createRawShortReader⁸⁷ and RawMemoryFactory.createRawShort⁸⁸. Each object references a range of elements in the RawMemoryRegion⁸⁹ starting at the *base address* provided to the factory method. The size provided to the factor method determines the number of elements accessable.

Caching of the memory access is controlled by the factory that created this object. If the memory is not cached, this method guarantees serialized access. In other words, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.

Available since RTSJ 2.0

Interfaces
RawMemory

12.4.1.19.1 Methods

getShort

Get the value at the first position referenced by this instance, i.e., the value at its start address. This operation must be atomic with respect to all other raw memory accesses to the address.

```
Signature

public

short getShort()

Returns
```

the value at the $base\ address$ provided to the factory method that created this object.

getShort(int)

Get the value of the n^{th} element referenced by this instance, where n is offset and the address is base address + (offset * stride * element size in bytes). When an exception is thrown, no data is transferred.

⁸⁷Section 12.4.3.5.3 ⁸⁸Section 12.4.3.5.3

⁸⁹Section 12.4.3.6

Signature

```
public
short getShort(int offset)
throws OffsetOutOfBoundsException
```

Parameters

offset of short in the memory region starting from the address specified in the associated factory method.

Throws

OffsetOutOfBoundsException when offset is negative or greater than or equal to the number of elements in the raw memory region.

Returns

the value at the address specified.

get(int, short[])

Fill the values starting at the address referenced by this instance plus the offset scaled by the element size in bytes and the object's stride. Only the shorts in the intersection of the start and end of values and the base address and the end of the memory region are transfered. When an exception is thrown, no data is transfered.

Signature

```
public
int get(int offset, short[] values)
throws OffsetOutOfBoundsException, NullPointerException
```

Parameters

 $o\!f\!f\!set$ of the first short in the memory region to transfere values the array to received the shorts

Throws

OffsetOutOfBoundsException when offset is negative or greater than or equal to the number of elements in the raw memory region.

NullPointerException when values is null.

Returns

the number of elements copied to values

get(int, short[], int, int)

Fill values with data from the memory region, where offset is first short in the memory region and start is the first index in values. The number of bytes transfered is the minimum of count, the *size* of the memory region minus offset, and length of values minus start. When an exception is thrown, no data is transfered.

Signature

public int get(int offset, short[] values, int start, int count) throws OffsetOutOfBoundsException, ArrayIndexOutOfBoundsException, NullPointerException

Parameters

offset of the first short in the memory region to transfere values the array to received the shorts start the first index in array to fill count the maximum number of shorts to copy

Throws

OffsetOutOfBoundsException when offset is negative or either offset or offset + count is greater than or equal to the size of this raw memory area. ArrayIndexOutOfBoundsException when start is negative or either start or start + count is greater than or equal to the size of values.

NullPointerException when values is null or count is negative.

Returns

the number of shorts actually transfered.

12.4.1.20 RawShortWriter

A marker for a short accessor object encapsulating the protocol for writing shorts from raw memory. A short accessor can always access at least one short. Each short is transfered in a single atomic operation. Groups of shorts may be transfered together; however, this is not required.

Objects of this type are created with the method RawMemoryFactory.createRawShortWriter⁹⁰ and RawMemoryFactory.createRawShort⁹¹. Each object references a range of elements in the RawMemoryRegion⁹² starting at the *base address* provided to the factory

⁹⁰Section 12.4.3.5.3

⁹¹Section 12.4.3.5.3

 $^{^{92}}$ Section 12.4.3.6

method. The size provided to the factor method determines the number of elements accessable.

Caching of the memory access is controlled by the factory that created this object. If the memory is not cached, this method guarantees serialized access. In other words, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.

Available since RTSJ 2.0

Interfaces
RawMemory

12.4.1.20.1 Methods

setShort(short)

Set the value at the first position referenced by this instance, i.e., the value at its start address. This operation must be atomic with respect to all other raw memory accesses to the address. When an exception is thrown, no data is transfered.

```
Signature

public

void setShort(short value)
```

setShort(int, short)

Set the value of the n^{th} element referenced by this instance, where n is offset and the address is base address + offset * size of Short. This operation must be atomic with respect to all other raw memory accesses to the address. When an exception is thrown, no data is transferred.

2.0 (Draft 20)

```
public
    void setShort(int offset, short value)
    throws OffsetOutOfBoundsException
Parameters
    offset of short in the memory region.
```

Throws

OffsetOutOfBoundsException when offset is negative or greater than or equal to the number of elements in the raw memory region.

set(int, short[])

Copy values to the raw memory starting at the address referenced by this instance plus the offset scaled by the element size in bytes and the objects stride. Only the shorts in the intersection of values and the end of the memory region are transfered. When an exception is thrown, no data is transfered.

```
Signature
```

```
public
int set(int offset, short[] values)
throws OffsetOutOfBoundsException, NullPointerException
```

Throws

OffsetOutOfBoundsException when offset is negative or greater than or equal to the number of elements in the raw memory region.

NullPointerException when values is null.

Returns

the number of elements copied to values

set(int, short[], int, int)

Copy values to the memory region, where offset is first short in the memory region to write and start is the first index in values from which to read. The number of bytes transfered is the minimum of count, the *size* of the memory region minus offset, and length of values minus start. When an exception is thrown, no data is transfered.

```
Signature
```

```
public
  int set(int offset, short[] values, int start, int count)
  throws OffsetOutOfBoundsException,
  ArrayIndexOutOfBoundsException, NullPointerException

Parameters
  offset of the first short in the memory region to set
  values the array from which to retrieve the shorts
```

start the first index in array to fill count the maximum number of shorts to copy

Throws

OffsetOutOfBoundsException when offset is negative or either offset or offset + count is greater than or equal to the size of this raw memory area. ArrayIndexOutOfBoundsException when start is negative or either start or start + count is greater than or equal to the size of values.

NullPointerException when values is null.

Returns

the number of shorts actually transfered.

12.4.2 Exceptions

12.4.2.1 UnsupportedRawMemoryRegionException

Inheritance

```
java.lang.Object
    java.lang.Throwable
    java.lang.Exception
    java.lang.RuntimeException
    javax.realtime.device.UnsupportedRawMemoryRegionException
```

12.4.2.1.1 Constructors

Unsupported Raw Memory Region Exception

```
\label{eq:signature} Signature \\ \\ \text{public} \\ \\ \text{UnsupportedRawMemoryRegionException()}
```

2.0 (Draft 20)

UnsupportedRawMemoryRegionException(String)

```
Signature

public

UnsupportedRawMemoryRegionException(String s)
```

UnsupportedRawMemoryRegionException(Throwable)

```
Signature

public

UnsupportedRawMemoryRegionException(Throwable ex)
```

UnsupportedRawMemoryRegionException(String, Throwable)

```
Signature

public

UnsupportedRawMemoryRegionException(String s, Throwable ex)
```

12.4.3 Classes

12.4.3.1 Happening

This class provides second level handling for external events such as interrupts. A happening can be triggered by an InterruptServiceRoutine⁹³ or from native code. Application defined Happenings can be identified by an application provided

⁹³Section 12.4.3.3

name or a system provided id, both of which must be unique. A system Happening has a name provide by the system which is a string beginning with @.

Available since RTSJ 2.0

Inheritance

```
java.lang.Object
javax.realtime.AbstractAsyncEvent
javax.realtime.AsyncEvent
javax.realtime.device.Happening
Interfaces
ActiveEvent
```

12.4.3.1.1 Constructors

Happening(String, HappeningDispatcher)

Create a Happening with the given name.

```
Signature
```

```
public
```

Happening(String name, HappeningDispatcher dispatcher)

```
throws IllegalArgumentException
```

Parameters

name of the happening.

dispatcher to use when being triggered.

Throws

IllegalArgumentException when name does not match the pattern full identifier naming convention, i.e., package plus name. An implementation may throw this exception for all names starting with java. and javax.

Happening(String)

Create a Happening with the given name.

```
Signature
```

```
public
   Happening(String name)
```

throws IllegalArgumentException

name of the happening.

Throws

IllegalArgumentException when name does not match the pattern full type naming convention, i.e., package plus name. An implementation may throw this exception for all names starting with java. and javax.

12.4.3.1.2 Methods

getHappening(String)

Find an active happening by its name. A Happening is only registered when it is active. When it is stopped, it is automatically deregistered.

```
Signature
```

```
public static
javax.realtime.device.Happening getHappening(String name)
```

name of the happening to get.

Returns

a reference to the happening with name name, or null if no happening is found.

isHappening(String)

Is there an active happening with name name?

```
Signature
```

```
public static
boolean isHappening(String name)
Parameters
```

2.0 (Draft 20)

name A string that might name an active happening.

Returns

True only when there is a registered happening with the name name.

createId(String)

Sets up a mapping between a name and a system dependent ID. This can be called either in the constructor of an instance of InterruptServiceRoutine⁹⁴ or in native code that sets up an interrupt service routine to link it with a Happening. Once created, it cannot be removed.

This must take no more than linear time in the number of ID (n) registered, but should be O(log2(n)).

```
Signature
```

```
public static
int createId(String name)
throws IllegalStateException
```

Parameters

name is a happing name string.

Throws

IllegalStateException when name is already registered.

Returns

an ID assigned by the system

getId(String)

Return the ID of name, when one exists or -1, when name is not registered.

This must take no more than linear time in the number of ID (n) registered, but should be O(log2(n)).

```
Signature
```

```
public static
int getId(String name)
```

Parameters

name is a happening name string.

Returns

The ID, or -1 if no happening is found by that name.

⁹⁴Section 12.4.3.3

get(int)

Get the external event corresponding to a given id.

```
Signature

public static
javax.realtime.device.Happening get(int id)

Parameters
id of a registered signal

Returns
the signal corresponding to id.
```

trigger(int)

Causes the event dispatcher corresponding to happeningId to be scheduled for execution. The implementation should be simple enough so that it can be done in the context of an InterrruptServiceRoutine.handle⁹⁵ method.

trigger() and any native code analog to it interact with other ActiveEvent⁹⁶ code effectively as if trigger() signals a POSIX counting semaphore that the happening is waiting on.

The implementation is encouraged to create (and document) a native code analog to this method that can be used without a Java context.

This method must execute in constant time.

```
Signature public static
```

boolean trigger(int id)
Parameters

id identifies which happening to trigger.

Returns

true if a happening with id happeningId was found, false otherwise.

getId

Get the number of this happening.

```
<sup>95</sup>Section ??

<sup>96</sup>Section 8.4.1.1
```

```
Signature

public final
int getId()

Returns

the happening number or -1, when not registered.
```

getName

Get the name of this happening.

```
Signature

public
 java.lang.String getName()

Returns

the name of this happening.
```

start

Start this Happening, i.e., change to the active and enabled state. Once a happening is started the first time, when it is in a scoped memory it increments the scope count of that scope; otherwise, it becomes a member of the root set. An active and enabled happening dispatches its handlers when fired.

```
See Section stop()
```

```
Signature
    public
    void start()
    throws IllegalStateException
Throws
```

IllegalStateException when this Happening has already been started or its name is already in use by another happening that has been started.

start(boolean)

Start this Happening, but leave it in the disabled state. When fired before being enabled, it does not dispatch its handlers.

```
See Section stop()
```

```
Signature

public

void start(boolean disabled)

throws IllegalStateException

Parameters

disabled true for starting in a disabled state.

Throws

IllegalStateException when this Happening has already been started.
```

stop

Stop this happening from responding to the fire and trigger methods.

```
public
    boolean stop()
    throws IllegalStateException
Throws
    IllegalStateException when this Happening is not active.
Returns
    true when this is in the enabled state false otherwise.
```

isActive

Determine the activation state of this happening, i.e., it has been started.

```
Signature

public
boolean isActive()

Returns

true when active, false otherwise.
```

2.0 (Draft 20)

isRunning

Determine whether or not this Happening is both active an enabled.

```
Signature

public
boolean isRunning()

Returns

true when this Happening is both active and enables, false otherwise.
```

getDispatcher

```
Signature

public

javax.realtime.device.HappeningDispatcher getDispatcher()
```

12.4.3.2 HappeningDispatcher

This class provides a means of dispatching a set of Happening⁹⁷. The process() method is called each time the signal is triggered.

Inheritance

```
javax.realtime.ActiveEventDispatcher
javax.realtime.device.HappeningDispatcher
```

12.4.3.2.1 Constructors

HappeningDispatcher(SchedulingParameters)

Create a new dispatcher, whose dispatching thread runs with the given scheduling parameters.

⁹⁷Section 12.4.3.1

```
Signature
```

```
public
```

HappeningDispatcher(SchedulingParameters schedule)

Parameters

schedule give the parameters for scheduling this dispatcher

12.4.3.2.2 Methods

register(Happening)

Register a Happening⁹⁸ with this dispatcher.

Signature

```
public synchronized
void register(Happening happening)
throws RegistrationException, IllegalStateException,
IllegalArgumentException
```

Parameters

happening to register

Throws

RegistrationException when happening is already registered. IllegalStateException when this object has been destroyed. IllegalArgumentException when happening is not stopped.

unregister(Happening)

Deregister a Happening⁹⁹ form this dispatcher.

Signature

⁹⁸Section 12.4.3.1 ⁹⁹Section 12.4.3.1

```
public synchronized
void unregister(Happening happening)
throws DeregistrationException, IllegalStateException,
IllegalArgumentException

Parameters
happening to unregister

Throws
DeregistrationException when happening is not already registered.
IllegalStateException when this object has been destroyed.
IllegalArgumentException when happening is not stopped.
```

destroy

Release all reasources thereby making the dispatcher unusable.

```
Signature

public

void destroy()

throws IllegalStateException

Throws
```

IllegalStateException when called on a dispatcher that has one or more registered $Happening^{100}$ objects.

12.4.3.3 InterruptServiceRoutine

A class for defining a first level interrupt handler. The implementation must override the handle¹⁰¹ method to provide the code to be run when an interrupt occurs. This class must always be present in the Device module, but may do nothing in a context that does not provide direct access to interrupts, e.g., in user space on an operating system that does not support user space device drivers.

Inheritance

12.4.3.3.1 Constructors

InterruptServiceRoutine(MemoryArea)

Create an interrupt service routine with a particular memory area.

```
Signature
```

```
public
```

InterruptServiceRoutine(MemoryArea area)

 $throws \ {\tt NullPointerException}, \ {\tt IllegalArgumentException}$

Parameters

area the allocation context in which the handle 102 method runs.

Throws

 $NullPointerException \ when \ {\tt initial_area} \ {\tt is} \ {\tt null}.$

IllegalArgumentException when id is not a valid interrupt id.

12.4.3.3.2 Methods

getHandler(int)

Find the InterruptServiceRoutine that is handling a given interrupt.

Signature

```
public static
javax.realtime.device.InterruptServiceRoutine getHandler(int
interrupt)
```

Parameters

interrupt for which to find the InterruptServiceRoutine

Returns

the InterruptServiceRoutine registered to the given interrupt. Null is returned when nothing is registered for that interrupt.

 $^{^{102}}$ Section 12.4.3.3.2

getMaximumInterruptPriority

Retrieve the maximum interrupt priority. It must be greater than or equal to the result of getMinimumInterruptPriority¹⁰³.

```
Signature

public static

int getMaximumInterruptPriority()

Returns

the maximum interrupt priority.
```

getMinimumInterruptPriority

Retrieve the minimum interrupt priority. It must be higher than all other priorities provided by the system.

```
Signature

public static

int getMinimumInterruptPriority()

Returns

the minimum interrupt priority.
```

getInterruptPriority(int)

Get the interrupt priority of a given interrupt.

```
Signature

public static
int getInterruptPriority(int interruptId)
throws IllegalArgumentException

Throws

IllegalArgumentException when there is no interrupt corresponding to interruptId

Returns

103Section 12.4.3.3.2
```

the priority at which the handle¹⁰⁴ method is involked. The returned value is always greater than PriorityScheduler.getMaxPriority()¹⁰⁵.

isRegistered

A predicate for the registration state.

```
Signature

public final
boolean isRegistered()

Returns

true when registered, otherwise false.
```

register(int)

Register this interrupt service routine with the system so that it can be triggered.

```
Signature

public

void register(int interrupt)

throws RegistrationException

Parameters

interrupt a system dependent identifier for the interrupt.

Throws
```

RegistrationException when this is already registered or some other InterruptServiceRoutine¹⁰⁶ is registered for interrupt.

unregister

Deregister this interrupt service routine with the system so that it can no longer be triggered.

```
Signature
public

104 Section 12.4.3.3.2
105 Section 6.4.2.7.3
106 Section 12.4.3.3
```

```
void unregister()
throws DeregistrationException
```

Throws

DeregistrationException when this interrupt service routine is not registered.

handle

The code to execute for first level interrupt handling. A subclass defines this to give the required behavior. RawMemory¹⁰⁷ classes may be used to access the associated device registers and a Happening¹⁰⁸ may be triggered for second level interrupt handling.

The code used to implement this method should not block itself for an unbound amount of time or induce a context switch, e.g., sleeping. The effects of unbound blocking and inducing a context switch here are undefined and could result in dead-locking the machine. Object.notify() and Object.notifyAll() may be called, but Object.wait() should not be called.

Unless the overridden method is synchronized, the infrastructure shall provide no synchronization for the execution of this method. When the MemoryArea¹⁰⁹ provided at creation is a ScopedMemory¹¹⁰, its count is incremented on entry to this method and decremented on exit.

```
Signature protected abstract void handle()
```

12.4.3.4 RawBufferFactory

A factory class for generating raw byte buffers. This enables the infrastructure to limit the address ranges from which a buffer may be taken.

Inheritance

```
java.lang.Object
javax.realtime.device.RawBufferFactory
```

```
<sup>107</sup>Section 12.4.1.16

<sup>108</sup>Section 12.4.3.1

<sup>109</sup>Section 11.4.2.3

<sup>110</sup>Section 11.4.2.5
```

12.4.3.4.1 Constructors

RawBufferFactory(long, long)

Create a factory for allocating buffers in a particular address range. Whether the address is physical or virtual is system dependent.

Open issue: jjh—I am not sure how to handle the issue of mapping addresses that the system knows about to ones that can be used in a DMA controller or other driver that requires buffers. Alternatives include providing more information to the factory or having a translation function to get the "right" address. An implementation may need or need to provide a means of mapping a physical page into virtual memory. End of open issue

Signature

public

RawBufferFactory(long base, long size)

throws MemoryInUseException

base is the base address of a memory range for buffer allocation size is the number of bytes in the memory range

Throws

MemoryInUseException when the memory area provide is already in use by or reserved for a MemoryArea¹¹¹, program code, or other system or VM structure.

12.4.3.4.2 Methods

allocate Direct Byte Buffer (int)

Create a direct byte buffer with the given capacity within the range of this factory.

¹¹¹Section 11.4.2.3

Open issue: jjh—what if a subclass is needed? One could add a reflection call, but it would be hard to implement in general. **End of open issue**

```
public
    java.nio.ByteBuffer allocateDirectByteBuffer(int capacity)
Parameters
    capacity the number of bytes in the buffer.
Returns
    the new buffer.
```

defineDirectByteBuffer(long, int)

Given a range of memory within the allocation area defined by this factory, create a direct byte buffer to represent that memory range.

```
public
    java.nio.ByteBuffer defineDirectByteBuffer(long start, int
    capacity)
    throws RangeOutOfBoundsException

Parameters
    start is the beginning of the memory range
    capacity is number of bytes in the range

Throws
    RangeOutOfBoundsException when start or start + capacity extends outside of the allocation area of this factory.

Returns
    the new buffer object
```

inRange(ByteBuffer)

Check to see if the buffer's data area is within the range of this factory.

```
Signature

public
boolean inRange(ByteBuffer buffer)

2.0 (Draft 20)
```

```
Parameters
```

buffer to check

Returns

true when and only when buffer's data area is within the range of this factory; otherwise false

RawBufferFactory

addressOf(ByteBuffer)

Give the location of this buffers data in memory. The address shall be in the address space of the DMA controller.

```
Signature

public
long addressOf(ByteBuffer buffer)

Parameters
buffer

Returns
the start address of the data range of this buffer
```

writeFence(ByteBuffer)

Ensures that all changes to the DirectByteBuffer buffer by the current thread have been flushed in a manner that makes them visible to other threads (including native threads), and behaves as a volatile store with respect to the Java Memory Model synchronization order.

This method shall invoke a memory barrier operation that is understood by the VM, runtime, native compiler, and platform to provide visibility to all changes to the associated buffer made before its invocation.

```
Signature

public static

void writeFence(ByteBuffer buffer)

Parameters

buffer the byte buffer which will be flushed
```

readFence(ByteBuffer)

Ensures that any previous changes to the memory represented by the given <code>DirectByteBuffer</code> by other threads (including native threads) will be visible when it is next accessed by the current thread, and behaves as a volatile load with respect to the Java Memory Model synchronization order.

This method shall invoke a memory barrier operation that is understood by the VM, runtime, native compiler, and platform to provide visibility for any changes to the associated buffer previously flushed with a call to writeFence(ByteBuffer buffer)¹¹² or its native equivalent on the buffer's memory.

```
Signature

public static

void readFence(ByteBuffer buffer)

Parameters

buffer the byte buffer which will be updated
```

12.4.3.5 RawMemoryFactory

This class is the hub of a system that constructs special purpose objects to access particular types and ranges of raw memory. This facility is supported by the register(RawMemoryRegionFactory)¹¹³ methods. An application developer can use this method to add support for additional memory regions.

Each create method returns an object of the corresponding type, e.g., the createRawByte(RawMemoryRegion, long, int, int)¹¹⁴ method returns a reference to an object that implements the RawByte¹¹⁵ interface and supports access to the requested type of memory and address range. Each create method is permitted to optimize error checking and access based on the requested memory type and address range.

The useage pattern for raw memory, assuming the necessary factory has been registered, is illustrated by this example.

```
// Get an accessor object that can access memory starting at
// baseAddress, for size bytes.
RawInt memory =

112Section 12.4.3.4.2
113Section 12.4.3.5.3
114Section 12.4.3.5.3
115Section 12.4.1.1
```

RawMemoryFactory.createRawInt(RawMemoryFactory.MEMORY_MAPPED_REGION, address, count, stride, false);

```
// Use the accessor to load from and store to raw memory. int loadedData = memory.getInt(someOffset);
```

memory.setInt(otherOffset, intVal); When an application needs to access a class of memory that is not already supported by a registered factory, the developer must define a memory region by implementing a factory which can create objects to access memory in that region. Thus, the application must implement a factory that implements the RawMemoryRegionFactory¹¹⁶ interface.

A raw memory region factory is identified by a RawMemoryRegion¹¹⁷ that is used by each create method, e.g., createRawByte(RawMemoryRegion, long, int, int)¹¹⁸, to locate the appropriate factory. The name is not passed to register(RawMemoryRegionFactory) as a separate argument, rather the name is provided to register(RawMemoryRegionFactory)¹²⁰ through the factory's RawMemoryRegionFactory.getName¹²¹ method.

The register(RawMemoryRegionFactory)¹²² method is only used when by application code when it needs to add support for a new type of raw memory.

Whether a give offset addresses a high-order or low-order byte of an aligned short in memory is determined by the value of the RealtimeSystem.BYTE_ORDER¹²³ static byte variable in class RealtimeSystem¹²⁴, the start address of the object, the offset given the stride of the object. Regardless of the byte ordering, accessor methods for by continue to select bytes starting at offset from the base address and continuing toward greater addresses.

The RawMemory class enables a realtime program to implement device drivers, memory-mapped I/O, flash memory, battery-backed RAM, and similar low-level software.

A raw memory region cannot contain references to Java objects. Such a capability would be unsafe (since it could be used to defeat Java's type checking) and error prone (since it is sensitive to the specific representational choices made by the Java compiler).

Atomic loads and stores on raw memory are defined in terms of physical memory. This memory may be accessible to threads outside the JVM and to non-programmed access (e.g., DMA). Consequently, atomic access must be supported by hardware.

```
116 Section 12.4.1.17

117 Section 12.4.3.6

118 Section 12.4.3.5.3

119 Section 12.4.3.5.3

120 Section 12.4.3.5.3

121 Section 12.4.1.17.1

122 Section 12.4.3.5.3

123 Section 13.3.1.7.1

124 Section 13.3.1.7
```

This specification is written with the assumption that all suitable hardware platforms support atomic loads from raw memory for aligned bytes, shorts, and ints. Atomic access beyond the specified minimum may be supported by the implementation.

Storing values into raw memory is more hardware-dependent than loading values. Many processor architectures do not support atomic stores of variables except for aligned stores of the processor's word size. For instance, storing a byte into memory might require reading a 32-bit quantity into a processor register, updating the register to reflect the new byte value, then restoring the whole 32-bit quantity. Changes to other bytes in the 32-bit quantity that take place between the load and the store are lost.

Some processors have mechanisms that can be used to implement an atomic store of a byte, but those mechanisms are often slow and not universally supported.

This class need not support unaligned access to data; but if it does, it is not require the implementation to make such access atomic. Accesses to data aligned on its natural boundary will be atomic if the processor implements atomic loads and stores of that data size.

Except where noted, accesses to raw memory are not atomic with respect to the memory or with respect to schedulable objects. A raw memory region could be updated by another schedulable object, or even unmapped in the middle of an access method, or even *removed* mid method.

The characteristics of raw-memory access are necessarily platform dependent. This specification provides a minimum requirement for the RTSJ platform, but it also supports optional system properties that identify a platform's level of support for atomic raw put and get. The properties represent a four-dimensional sparse array of access type, data type, alignment, and atomicity with boolean values indicating whether that combination of access attributes is atomic. The default value for array entries is false. The dimension are

Attribute	Values	Comment
Access type	read, write	
Data type Alignment	 byte, short, int, long, float, double 0 to 7	For each data type, the possible alignments range from • 0 == aligned • to data size - 1 == only the first byte of the data is alignment
Atomicity	processor,smp,memory	bytes away from natural alignment. • processor means access is atomic with respect to other schedulable objects on that processor. • smp means that access is processor atomic, and atomic across the processors in an SMP. • memory means that access is smp atomic, and atomic with respect to all access to the memory, including DMA hardware.

The true values in the table are represented by properties of the following form. javax.realtime.atomicaccess_<access>_<type>_<alignment>_atomicity=true for example,

 $javax.real time.atomic access_read_byte_0_memory = true$

Table entries with a value of false may be explicitly represented, but since false is the default value, such properties are redundant.

All raw memory access is treated as volatile, and *serialized*. The runtime must be

forced to read memory or write to memory on each call to a raw memory objects's getter or setter method, and to complete the reads and writes in the order they appear in the program order.

Available since RTSJ 2.0

Inheritance

java.lang.Object javax.realtime.device.RawMemoryFactory

12.4.3.5.1 Fields

MEMORY_MAPPED_REGION

public static final MEMORY_MAPPED_REGION

This raw memory name is predefined for use to request access to memory mapped I/O devices.

IO_PORT_MAPPED_REGION

public static final IO_PORT_MAPPED_REGION

This raw memory name is predefined for use to request access to I/O device space implemented by processor instructions, such as the x86 in and out instructions.

12.4.3.5.2 Constructors

RawMemoryFactory

Create an empty factory. For a factory with support for the platform defined RawMemoryRegion¹²⁵s, use getDefaultFactory¹²⁶ instead.

Signature

 $^{^{125}}$ Section 12.4.3.6

 $^{^{126}}$ Section 12.4.3.5.3

```
public
  RawMemoryFactory()
```

12.4.3.5.3 Methods

getDefaultFactory

Get the factory with support for the platform defined regions.

```
Signature

public static
javax.realtime.device.RawMemoryFactory getDefaultFactory()

Returns
the platform defined factory
```

register(RawMemoryRegionFactory)

Add support for a new memory region

```
Signature
    public
    void register(RawMemoryRegionFactory factory)
    throws RegistrationException
```

Parameters

factory is the RawMemoryRegionFactory 127 to use for creating RawMemory 128 objects for the RawMemoryRegion 129 it makes available.

Throws

RegistrationException when the RawMemoryRegion of factory already has a factory registered.

```
127 Section 12.4.1.17
128 Section 12.4.1.16
129 Section 12.4.3.6
```

deregister(RawMemoryRegionFactory)

Remove support for a new memory region

```
Signature

public

void deregister(RawMemoryRegionFactory factory)

throws DeregistrationException

Parameters

factory is the RawMemoryRegionFactory<sup>130</sup> to make unavailable.

Throws

RegistrationException when the factory is not registered.
```

createRawByte(RawMemoryRegion, long, int, int)

Create an instance of a class that implements RawByte¹³¹ and accesses memory of region in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of RawByte * count. The object is allocated in the current memory area of the calling thread.

```
Signature
```

```
public
javax.realtime.device.RawByte createRawByte(RawMemoryRegion
region, long base, int count, int stride)
throws SecurityException, OffsetOutOfBoundsException,
SizeOutOfBoundsException, MemoryTypeConflictException,
UnsupportedRawMemoryRegionException
```

Parameters

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

stride The distance to the next element as a mulitple of element size, where 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is less than one.

```
<sup>130</sup>Section 12.4.1.17

<sup>131</sup>Section 12.4.1.1
```

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

Memory Type Conflict Exception when base does not point to memory that matches the type served by this factory.

Returns

an object that implements $RawByte^{132}$ and supports access to the specified range in the memory region.

createRawByteReader(RawMemoryRegion, long, int, int)

Create an instance of a class that implements RawByteReader¹³³ and accesses memory of region in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of Raw-ByteReader * count. The object is allocated in the current memory area of the calling thread.

Signature

```
public
javax.realtime.device.RawByteReader createRawByte-
Reader(RawMemoryRegion region, long base, int count, int stride)
throws SecurityException, OffsetOutOfBoundsException,
SizeOutOfBoundsException, MemoryTypeConflictException,
UnsupportedRawMemoryRegionException
```

Parameters

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance

stride The distance to the next element as a mulitple of element size, where 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is less than one.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

```
<sup>132</sup>Section 12.4.1.1

<sup>133</sup>Section 12.4.1.2
```

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

Memory Type Conflict Exception when base does not point to memory that matches the type served by this factory.

Returns

an object that implements RawByteReader¹³⁴ and supports access to the specified range in the memory region.

createRawByteWriter(RawMemoryRegion, long, int, int)

Create an instance of a class that implements RawByteWriter¹³⁵ and accesses memory of region in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of Raw-ByteWriter * count. The object is allocated in the current memory area of the calling thread.

Signature

```
public
javax.realtime.device.RawByteWriter createRawByteWri-
ter(RawMemoryRegion region, long base, int count, int stride)
throws SecurityException, OffsetOutOfBoundsException,
SizeOutOfBoundsException, MemoryTypeConflictException,
UnsupportedRawMemoryRegionException
```

Parameters

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

stride The distance to the next element as a mulitple of element size, where 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is less than one.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

```
<sup>134</sup>Section 12.4.1.2

<sup>135</sup>Section 12.4.1.3
```

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

Memory Type Conflict Exception when base does not point to memory that matches the type served by this factory.

Returns

an object that implements RawByteWriter¹³⁶ and supports access to the specified range in the memory region.

createRawShort(RawMemoryRegion, long, int, int)

Create an instance of a class that implements RawShort¹³⁷ and accesses memory of region in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of RawShort * count. The object is allocated in the current memory area of the calling thread.

Signature

```
public
javax.realtime.device.RawShort createRawShort(RawMemoryRegion
region, long base, int count, int stride)
throws SecurityException, OffsetOutOfBoundsException,
SizeOutOfBoundsException, MemoryTypeConflictException,
UnsupportedRawMemoryRegionException
```


base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

stride The distance to the next element as a mulitple of element size, where 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is less than one.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

¹³⁶Section 12.4.1.3 ¹³⁷Section 12.4.1.18

MemoryTypeConflictException when base does not point to memory that matches the type served by this factory.

Returns

an object that implements RawShort¹³⁸ and supports access to the specified range in the memory region.

createRawShortReader(RawMemoryRegion, long, int, int)

Create an instance of a class that implements RawShortReader¹³⁹ and accesses memory of region in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of RawShort-Reader * count. The object is allocated in the current memory area of the calling thread.

Signature

public

javax.realtime.device.RawShortReader createRawShort-

Reader(RawMemoryRegion region, long base, int count, int stride)

throws SecurityException, OffsetOutOfBoundsException,

SizeOutOfBoundsException, MemoryTypeConflictException,

UnsupportedRawMemoryRegionException

Parameters

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

stride The distance to the next element as a mulitple of element size, where 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is less than one.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

MemoryTypeConflictException when base does not point to memory that matches the type served by this factory.

 $^{^{138}}$ Section 12.4.1.18

 $^{^{139}}$ Section 12.4.1.19

Returns

an object that implements RawShortReader¹⁴⁰ and supports access to the specified range in the memory region.

createRawShortWriter(RawMemoryRegion, long, int, int)

Create an instance of a class that implements RawShortWriter¹⁴¹ and accesses memory of region in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of RawShort-Writer * count. The object is allocated in the current memory area of the calling thread.

Signature

```
public
javax.realtime.device.RawShortWriter createRawShortWri-
ter(RawMemoryRegion region, long base, int count, int stride)
throws SecurityException, OffsetOutOfBoundsException,
SizeOutOfBoundsException, MemoryTypeConflictException,
UnsupportedRawMemoryRegionException
```

Parameters 1 4 1

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

stride The distance to the next element as a mulitple of element size, where 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is less than one.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

Memory Type Conflict Exception when base does not point to memory that matches the type served by this factory.

Returns

```
<sup>140</sup>Section 12.4.1.19

<sup>141</sup>Section 12.4.1.20
```

an object that implements RawShortWriter¹⁴² and supports access to the specified range in the memory region.

createRawInt(RawMemoryRegion, long, int, int)

Create an instance of a class that implements RawInt¹⁴³ and accesses memory of region in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of RawInt * count. The object is allocated in the current memory area of the calling thread.

Signature

```
public
javax.realtime.device.RawInt createRawInt(RawMemoryRegion
region, long base, int count, int stride)
throws SecurityException, OffsetOutOfBoundsException,
SizeOutOfBoundsException, MemoryTypeConflictException,
UnsupportedRawMemoryRegionException
```

Parameters

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

stride The distance to the next element as a mulitple of element size, where 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is less than one.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

Memory Type Conflict Exception when base does not point to memory that matches the type served by this factory.

Returns

an object that implements \mathtt{RawInt}^{144} and supports access to the specified range in the memory region.

¹⁴²Section 12.4.1.20 ¹⁴³Section 12.4.1.10

¹⁴⁴Section 12.4.1.10

createRawIntReader(RawMemoryRegion, long, int, int)

Create an instance of a class that implements $RawIntReader^{145}$ and accesses memory of region in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of RawIntReader * count. The object is allocated in the current memory area of the calling thread.

Signature

public

javax.realtime.device.RawIntReader createRawInt-

Reader(RawMemoryRegion region, long base, int count, int stride)

throws SecurityException, OffsetOutOfBoundsException,

SizeOutOfBoundsException, MemoryTypeConflictException,

 ${\tt UnsupportedRawMemoryRegionException}$

Parameters

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

stride The distance to the next element as a mulitple of element size, where 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is less than one.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

Memory Type Conflict Exception when base does not point to memory that matches the type served by this factory.

Returns

an object that implements RawIntReader¹⁴⁶ and supports access to the specified range in the memory region.

createRawIntWriter(RawMemoryRegion, long, int, int)

¹⁴⁵Section 12.4.1.11 ¹⁴⁶Section 12.4.1.11

Create an instance of a class that implements RawIntWriter¹⁴⁷ and accesses memory of region in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of RawIntWriter * count. The object is allocated in the current memory area of the calling thread.

Signature

```
public javax.realtime.device.RawIntWriter createRawIntWri-ter(RawMemoryRegion region, long base, int count, int stride) throws SecurityException, OffsetOutOfBoundsException, SizeOutOfBoundsException, MemoryTypeConflictException, UnsupportedRawMemoryRegionException
```

Parameters

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

stride The distance to the next element as a mulitple of element size, where 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is less than one.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

Memory Type Conflict Exception when base does not point to memory that matches the type served by this factory.

Returns

an object that implements RawIntWriter¹⁴⁸ and supports access to the specified range in the memory region.

createRawLong(RawMemoryRegion, long, int, int)

Create an instance of a class that implements RawLong¹⁴⁹ and accesses memory

 $^{^{147}}$ Section 12.4.1.12

¹⁴⁸Section 12.4.1.12

 $^{^{149}}$ Section 12.4.1.13

of region in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of RawLong * count. The object is allocated in the current memory area of the calling thread.

Signature

```
public
javax.realtime.device.RawLong createRawLong(RawMemoryRegion
region, long base, int count, int stride)
throws SecurityException, OffsetOutOfBoundsException,
SizeOutOfBoundsException, MemoryTypeConflictException,
UnsupportedRawMemoryRegionException
```

Parameters

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

stride The distance to the next element as a mulitple of element size, where 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is less than one.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

MemoryTypeConflictException when base does not point to memory that matches the type served by this factory.

Returns

an object that implements RawLong¹⁵⁰ and supports access to the specified range in the memory region.

createRawLongReader(RawMemoryRegion, long, int, int)

Create an instance of a class that implements $RawLongReader^{151}$ and accesses memory of region in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of RawLongReader * count. The object is allocated in the current memory area of the calling

¹⁵⁰Section 12.4.1.13 ¹⁵¹Section 12.4.1.14

thread.

```
Signature
```

```
public
javax.realtime.device.RawLongReader
createRawLongReader(RawMemoryRegion region, long base, int
count, int stride)
throws SecurityException, OffsetOutOfBoundsException,
SizeOutOfBoundsException, MemoryTypeConflictException,
UnsupportedRawMemoryRegionException
```

Parameters

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

stride The distance to the next element as a mulitple of element size, where 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is less than one.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

MemoryTypeConflictException when base does not point to memory that matches the type served by this factory.

Returns

an object that implements $RawLongReader^{152}$ and supports access to the specified range in the memory region.

createRawLongWriter(RawMemoryRegion, long, int, int)

Create an instance of a class that implements RawLongWriter¹⁵³ and accesses memory of region in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of RawLong-Writer * count. The object is allocated in the current memory area of the calling thread.

```
<sup>152</sup>Section 12.4.1.14

<sup>153</sup>Section 12.4.1.15
```

Signature

```
public
```

javax.realtime.device.RawLongWriter createRawLong-

Writer(RawMemoryRegion region, long base, int count, int stride)

throws SecurityException, OffsetOutOfBoundsException,

SizeOutOfBoundsException, MemoryTypeConflictException,

UnsupportedRawMemoryRegionException

Parameters

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

stride The distance to the next element as a mulitple of element size, where 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is less than one.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

MemoryTypeConflictException when base does not point to memory that matches the type served by this factory.

Returns

an object that implements RawLongWriter¹⁵⁴ and supports access to the specified range in the memory region.

createRawFloat(RawMemoryRegion, long, int, int)

Create an instance of a class that implements RawFloat¹⁵⁵ and accesses memory of region in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of RawFloat * count. The object is allocated in the current memory area of the calling thread.

Signature

¹⁵⁴Section 12.4.1.15 ¹⁵⁵Section 12.4.1.7

public javax.realtime.device.RawFloat createRawFloat(RawMemoryRegion region, long base, int count, int stride) throws SecurityException, OffsetOutOfBoundsException, SizeOutOfBoundsException, MemoryTypeConflictException, UnsupportedRawMemoryRegionException

Parameters

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

stride The distance to the next element as a mulitple of element size, where 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is less than one.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

Memory Type Conflict Exception when base does not point to memory that matches the type served by this factory.

Returns

an object that implements RawFloat¹⁵⁶ and supports access to the specified range in the memory region.

createRawFloatReader(RawMemoryRegion, long, int, int)

Create an instance of a class that implements $RawFloatReader^{157}$ and accesses memory of region in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of RawFloatReader * count. The object is allocated in the current memory area of the calling thread.

Signature	
public	
¹⁵⁶ Section 12.4.1.7 ¹⁵⁷ Section 12.4.1.8	

javax.realtime.device.RawFloatReader createRawFloat-Reader(RawMemoryRegion region, long base, int count, int stride) throws SecurityException, OffsetOutOfBoundsException, SizeOutOfBoundsException, MemoryTypeConflictException, UnsupportedRawMemoryRegionException

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

stride The distance to the next element as a mulitple of element size, where 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is less than one.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

Memory Type Conflict Exception when base does not point to memory that matches the type served by this factory.

Returns

an object that implements RawFloatReader¹⁵⁸ and supports access to the specified range in the memory region.

createRawFloatWriter(RawMemoryRegion, long, int, int)

Create an instance of a class that implements RawFloatWriter¹⁵⁹ and accesses memory of region in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of RawFloatWriter * count. The object is allocated in the current memory area of the calling thread.

Signature

```
public
javax.realtime.device.RawFloatWriter createRawFloatWri-
ter(RawMemoryRegion region, long base, int count, int stride)
```

¹⁵⁸Section 12.4.1.8 ¹⁵⁹Section 12.4.1.9

throws SecurityException, OffsetOutOfBoundsException, SizeOutOfBoundsException, MemoryTypeConflictException, UnsupportedRawMemoryRegionException

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

stride The distance to the next element as a mulitple of element size, where 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is less than one.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

MemoryTypeConflictException when base does not point to memory that matches the type served by this factory.

Returns

an object that implements RawFloatWriter¹⁶⁰ and supports access to the specified range in the memory region.

createRawDouble(RawMemoryRegion, long, int, int)

Create an instance of a class that implements RawDouble¹⁶¹ and accesses memory of region in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of RawDouble * count. The object is allocated in the current memory area of the calling thread.

Signature

public javax.realtime.device.RawDouble createRawDouble(RawMemoryRegion region, long base, int count, int stride) throws SecurityException, OffsetOutOfBoundsException, SizeOutOfBoundsException, MemoryTypeConflictException, UnsupportedRawMemoryRegionException

 $^{^{160}}$ Section 12.4.1.9

 $^{^{161}}$ Section 12.4.1.4

Parameters 1

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

stride The distance to the next element as a mulitple of element size, where 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is less than one.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

MemoryTypeConflictException when base does not point to memory that matches the type served by this factory.

Returns

an object that implements RawDouble¹⁶² and supports access to the specified range in the memory region.

createRawDoubleReader(RawMemoryRegion, long, int, int)

Create an instance of a class that implements RawDoubleReader¹⁶³ and accesses memory of region in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of RawDoubleReader * count. The object is allocated in the current memory area of the calling thread.

Signature

```
public
```

javax.realtime.device.RawDoubleReader createRawDouble-Reader(RawMemoryRegion region, long base, int count, int stride) throws SecurityException, OffsetOutOfBoundsException, SizeOutOfBoundsException, MemoryTypeConflictException, UnsupportedRawMemoryRegionException

Parameters

```
<sup>162</sup>Section 12.4.1.4

<sup>163</sup>Section 12.4.1.5
```

base The starting physical address accessible through the returned instance. count The number of memory elements accessible through the returned instance.

stride The distance to the next element as a mulitple of element size, where 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is less than one.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

Memory Type Conflict Exception when base does not point to memory that matches the type served by this factory.

Returns

an object that implements RawDoubleReader¹⁶⁴ and supports access to the specified range in the memory region.

createRawDoubleWriter(RawMemoryRegion, long, int, int)

Create an instance of a class that implements RawDoubleWriter¹⁶⁵ and accesses memory of region in the address range described by base, stride, and count. The actual extent of the memory addressed by the object is stride * size of RawDoubleWriter * count. The object is allocated in the current memory area of the calling thread.

Signature

```
public
javax.realtime.device.RawDoubleWriter createRawDoubleWri-
ter(RawMemoryRegion region, long base, int count, int stride)
throws SecurityException, OffsetOutOfBoundsException,
SizeOutOfBoundsException, MemoryTypeConflictException,
UnsupportedRawMemoryRegionException
```

Parameters

base The starting physical address accessible through the returned instance.

¹⁶⁴Section 12.4.1.5 ¹⁶⁵Section 12.4.1.6

count The number of memory elements accessible through the returned instance.

stride The distance to the next element as a mulitple of element size, where 1 means the elements are adjacent in memory.

Throws

IllegalArgumentException when base is negative, count is not greater than zero, or stride is less than one.

SecurityException when the caller does not have permissions to access the given memory region or the specified range of addresses.

OffsetOutOfBoundsException when base is invalid.

SizeOutOfBoundsException when the memory addressed by the object would extend into an invalid range of memory.

Memory Type Conflict Exception when base does not point to memory that matches the type served by this factory.

Returns

an object that implements RawDoubleWriter¹⁶⁶ and supports access to the specified range in the memory region.

12.4.3.6 RawMemoryRegion

RawMemoryRegion is a class for typing raw memory regions. It is returned by the RawMemoryRegionFactory.getRegion¹⁶⁷ methods of the raw memory region factory classes, and it is used with methods such as RawMemoryFactory.createRawByte(RawMemoryRegion, long, int, int)¹⁶⁸ and RawMemoryFactory.createRawDouble(RawMemoryRegion, long, int, int)¹⁶⁹ methods to identify the region from which the application wants to get an accessor instance.

Available since RTSJ 2.0

Inheritance

java.lang.Object javax.realtime.device.RawMemoryRegion

12.4.3.6.1 Methods

```
<sup>166</sup>Section 12.4.1.6

<sup>167</sup>Section 12.4.1.17.1

<sup>168</sup>Section 12.4.3.5.3

<sup>169</sup>Section 12.4.3.5.3
```

getRegion(String)

Get a region type when it already exists or creates a new one.

```
Signature

public static
javax.realtime.device.RawMemoryRegion getRegion(String name)

Parameters
name of the region

Returns
the region type object.
```

isRawMemoryRegion(String)

Ask whether or not there is a memory region type of a given name.

```
Signature

public static
boolean isRawMemoryRegion(String name)

Parameters

name for which to search

Returns

true when there is one and false otherwise.
```

getName

Obtains the name of this region type.

```
Signature

public final
java.lang.String getName()

Returns

the region types name
```

toString

Gets a printable representation for a Region.

2.0 (Draft 20)

```
public final
    java.lang.String toString()
Returns
    the name of this memory region type.
```

12.5 Rationale

12.5.1 Raw Memory

Raw memory in the RTSJ refers to any memory in which only objects of primitive types can be stored; Java objects or their references cannot be stored in raw memory. 2.0 of specification provides two categories:

- memory that is used to access memory-mapped device registers, and
- logical memory that can be used to access port-based device registers.

Each of these categories of memory is represented by an instance of RawMemoryRegion. In addition, the application can define other regions outside these two, either for accessing devices registers in some other address space or for other purposes, such as emulating device access.

Java's primitive types are partitioned into two groups: integral (short, int, long, byte) and real (float, double) types, including arrays of each type. For integral types, individual interfaces are also defined to facilitate greater type security during access. Objects that support these interfaces are created by factory methods, which again have predefined interfaces. Such objects are called *accessor* objects as they encapsulates the access protocol to the raw memory.

Control over all these objects is managed by the RawMemoryFactory class that provides a set of static methods, as shown in Figure 12.5. There are two groups of methods, those that

- enable a factory to be registered, and
- request the creation of *accessor* object for a particular memory type at a particular address.

The latter consists of methods to create Java-primitive-type accessor objets, which will throw exceptions if the appropriate addresses are not on correct boundaries to enable the underlying machine instructions to be used without causing hardware exceptions (e.g., createRawByteReader).

608 12.5 Rationale

Figure 12.5: Creating Raw Memory Accessors

javax.realtime::RawMemoryRegion RawMemoryRegion(String name) +toString(): String

+createRawLong(long base, int size, int stride): RawLong +createRawInt(long base, int size, int stride): RawInt +createRawShort(long base, int size, int stride): RawShort +createRawByte(long base, int size, int stride): RawByte +createRawFloat(long base, int size, int stride): RawFloat +createRawDouble(long base, int size, int stride): RawDouble ...

javax.realtime::RawMemoryFactory

- +getDefaultFactory(): RawMemoryFactory
- +register(RawMemoryRegionFactory creator)
- +createRawLong(RawMemoryRegion type, long base, int size, int stride): RawLong
- +createRawInt(RawMemoryRegion type, long base, int size, int stride): RawInt
- +createRawShort(RawMemoryRegion type, long base, int size, int stride): RawShort
- +createRawByte(RawMemoryRegion type, long base, int size, int stride): RawByte
- +createRawFloat(RawMemoryRegion type, long base, int size, int stride): RawFloat
- +createRawDouble(RawMemoryRegion type, long base, int size, int stride): RawDoub

. . .

As with interrupt handling, some realtime JVMs may not be able to support all of the memory categories. However, the expectation is that for all supported categories, they will also provide and register the associated factories for object creation.

For the case of IO_PORT_MAPPED raw memory, the accessor objects will need to arrange to execute the appropriate machine instructions to access the device registers.

Consider, the simple case where a device has a two device registers: a control/status register that is a 32 bits integer, and a data register that is a 64 bits long. The registers have been memory mapped to locations: 0x20 and 0x24 respectively. Assuming the realtime JVM has registered a factory for the IO_PORT_MAPPED_REGION raw memory name, then the following code will create the objects that facilitate the memory access

¹ RawMemoryFactory factor = RawMemoryFactory.getDefaultFactory();

```
2 RawInt controlReg =
3   factory.createRawInt(RawMemoryFactory.IO_PORT_MAPPED_REGION, 0x20);
4 RawLong dataReg =
5   factory.createRawLong(RawMemoryFactory.IO_PORT_MAPPED_REGION, 0x24);
```

The above definitions reflect the structure of the actual registers. The JVM will check that the memory locations are on the correct boundaries and that they can be accessed without any hardware exceptions being generated. If they cannot, the create methods will throw an appropriate exceptions. If successfully created, all future access to the controlReg and dataReg will be exception free. The registers can be manipulated by calling the appropriate methods, as in the following example.

```
1 dataReg.put(1);
2    // where I is of type long and is data to be sent to the device
3 controlReg.put(i);
4    // where i is of type int and is the command to the device
```

In the general case, programmers themselves may create their own memory categories and provide associated factories (that may use the implementation-defined factories). These factories are written in Java and are, therefore, constrained by what the language allows them to do. Typically, they will use the JVM-supplied raw memory types to facilitate access to a device's external memory.

Open issue: Andy: is the following still true? End of open issue In addition to the above facilities, the RTSJ also supports the notion of removable memory. When this memory is inserted or removed, an asynchronous event can be set up to fire, thereby alerting the application that the device has become active. Of course, any removable memory has to be treated with extreme caution by the realtime JVM. Hence, the RTSJ allows it only to be accessed as a raw memory device. An example of these latter facilities will be given in Section 12.5.3.

12.5.1.1 Direct memory access

DMA requires access to memory out side of the heap. It is often crucial for performance in embedded systems; however, it does cause problems both from a realtime analysis perspective and from a JVM-implementation perspective. The latter is the primary concern here.

There are a few crucial points to note about DMA and the RTSJ.

- The RTSJ does not address issues of persistent objects; so the input and output of Java objects to devices (other than by using the Java serialization mechanism) is not supported.
- The RTSJ requires that RTSJ programs can be compiled by regular Java compilers. Different bytecode compilers (and their supporting JVM) use different


610 12.5 Rationale

representation for objects. Java arrays (even of primitive types) are objects, and the data they contain might not be stored in contiguous memory.

• The package java.nio.channels provides a mechanism for I/O that was not specifically designed for DMA, but provides an applicable pattern for it.

For these reasons, without explicit knowledge of the compiler and JVM, allowing any DMA into any RTSJ memory area is a very dangerous action; therefore, the RTSJ provides some special support for DMA. Unfortunately, it would be difficult to find a general pattern to fit all DMA controllers. With raw memory and raw byte buffers, one could construct a higher level API that would cover most DMA controllers, but there will always odd cases that would still not fit the general pattern, especially for embedded systems. For this reason, only this low level API is provided.

Figure 12.6: Flash memory device



12.5.2 Interrupt Handling

Handling interrupts is a necessary part of many embedded systems. Interrupt handlers have traditionally been implemented in assembler code or C. With the growing popularity of high-level concurrent languages, there has been interest in better integration between the interrupt handling code and the application. Ada, for example, allows a "protected" procedure to be called directly from an interrupt [3].

Regehr [7] defines the terms used for the core components of interrupts and their handlers as follows.

- Interrupt—a hardware supported asynchronous transfer of control mechanism initiated by an event external to the processor. Control of the processor is transferred through an interrupt vector.
- Interrupt vector—a dedicated (or configurable) location that specifies the location of an interrupt handler.
- Interrupt handler—code that is reachable from the interrupt vector.

• An interrupt controller—a peripheral device that manages interrupts for the processor.

He further identifies the following problems with programming interrupt-driven software on single processors:

- Stack overflow—the difficulty determining how much call-chain stack is required to handle an interrupt. The problem is compounded if the stack is borrowed from the currently executing thread or process.
- Interrupt overload—the problem of ensuring that non-interrupt driven processing is not swamped by unexpected or misbehaving interrupts.
- Real-time analysis—the need to have appropriate schedulability analysis models to bound the impact of interrupt handlers.

The problems above are accentuated in multiprocessor systems where interrupts can be handled globally. Fortunately, many multiprocessor systems allow interrupts to be bound to particular processors. For example, the ARM Cortex A9-MPCore supports the Arm Generic Interrupt Controller¹⁷⁰. This enables a target list of CPUs to be specified for each hardware interrupt. Software generated interrupts can also be sent to the list or set up to be delivered to all but the requesting CPU or only the requesting CPU.

Regehr's problems are all generic and can be solved irrespective of the language used to implement the handlers. In general they can be addressed by a combination of techniques.

- Stack overflow—static analysis techniques can usually be used to determine the worst-case stack usage of all interrupt handlers. If stack is borrowed from the executing thread then this amount must be added to the worst-case stack usage of all threads.
- Interrupt overload—this is typically managed by aperiodic server technology in combination with interrupt masking (see Section 13.6 of [3]).
- Real-time analysis—again this can be catered for in modern schedulability analysis techniques, such as response-time analysis (see Section 14.6 of [3]).

From a RTSJ perspective, the following distinctions are useful

• The first-level interrupt handlers are the code that the platform executes in response to the hardware interrupts (or traps). A first-level interrupt is assumed to be executed at an execution eligibility (priority) and by a processor dictated by the underlying platform (which may be controllable at the platform level). On some RTSJ implementations it will not be possible to write Java code for these handlers. Implementations that do enable Java-level handlers may restrict the code that can be written. For example, the handler code should not suspend itself or throw unhandled exceptions. The RTSJ 2.0 optional InterruptServiceRoutine class supports first level interrupt handling.

 $^{^{170}~\}rm See~http://infocenter.arm.com/help/index.jsp?topic=/com.arm.doc.ddi0375a/Cegbfjhf.html$

612 12.5 Rationale

• The external event handler is the code that the JVM executes as a result of being notified that an external event (be it an operating system signal, an ISR or some other program) is targeted at the RTSJ application. The programmer should be able to specify the processor affinity and execution eligibility of this code. In RTSJ 2.0, all external events are represented by instances of the Happening interface. Every happening has an associated dispatcher which is responsible for the initial response to an occurrence of the event.

A happening dispatcher is able to find one or more associated RTSJ asynchronous events and fire them. This then releases the associated asynchronous event handlers.

12.5.3 An Illustrative Example

Consider an embedded system that has a simple flash memory device that supports a single type of removable flash memory stick, as illustrated in Figure 12.6.

When the memory stick is inserted or removed, an interrupt is generated. This interrupt is known to the realtime JVM. The interrupt is also generated when operations requested on the device are completed. For simplicity, it is assumed that realtime JVM has mapped this interrupt to an external happening called Flash-Happening with a default happening dispatcher.

The example illustrates how

- 1. a programmer can use the RTSJ facilities to write a device handler,
- 2. a factory class can be constructed and how the accessor objects police the access.
- 3. removable memory is handled.

The flash memory device is accessed via several associated registers, which are shown in Table 12.1. These have all been memory mapped to the indicated locations.

12.5.3.1 Software architecture

There are many ways in which the software architecture for the example could be constructed. Here, for simplicity of representation, an architecture is chosen with a minimal number of classes. It is illustrated in Figure 12.7. There are three key components.

- FlashHappening—This is the external happening that is associated with the flash device's interrupt. The RTSJ will provide a default dispatcher, which will fire the asynchronous event when the interrupt occurs.
- FMSocketController—This is the object that encapsulates the access to the flash memory device. In essence, it is the device driver; it is also the handler for the FlashHappening and is responsibly for firing the FMInserted and FM-Removed asynchronous events.
- FAController—This is the object that controls access to the flash memory, it

Register	Location	Bit Positions	Values
Command	0x20	0	0 = Disable device, 1 = Enable device
		4	0 = Disable interrupts, 1 = Enable interrupts
		5-8	1 = Read byte, 2 = Write byte
			3 = Read short, 4 = Write short
			5 = Read int, 6 = Write int
			7 = Read long, 8 = Write long
		9	0 = DMA Read, 1 = DMA
		31-63	Offset into flash memory
Data	0x28	0-63	Simple data or memory address if DMA
Length	0x30	0-31	Length of data transfer
Status	0x38	0	1 = Device enabled
		3	1 = Interrupts enabled
		4	1 = Device in error
		5	1 = Transfer complete
		6	1 = Memory stick present
			0 = Memory stick absent
		7	1 = Memory stick inserted
		8	0 = Memory stick removed

Table 12.1: Device registers

- acts as the factory for the creating objects that will facilitate access to the flash memory itself (using the mechanisms provided by the FMSocket-Controller),
- is the asynchronous event handler that responds to the firing of the FM-Inserted and FMRemoved asynchronous events, and
- also acts as the accessor object for the memory.

12.5.3.2 Device initialization

Figure 12.8 shows the sequence of operations that the program must perform to initialize the flash memory device. The main steps are as follows.


- 1 The external happening (FlashEvent) associated with the flash happening must be created.
- 2-3 The (FMSocketController) object is created and added as a handler for FlashEvent.
 - 4 An initialization method is called (initDevice) to perform all the operations necessary to configure the infrastructure and initialize the hardware device.
- 5-6 Two new asynchronous events are created to represent insertion and removal

614 12.5 Rationale

<<AsyncEventHandler>> FlashEvent: ExternalHappenin handler **FMSocketController** FMInserted: AsyncEvent name="FlashHappening" handler for FMRemoved: AsyncEvent handler for <<AsyncEventHandler>> **FAController** <<Interface>> <<Interface>> <<Interface>> RemovableMemory RawIntegralAccessFactory RawIntegralAccess

Figure 12.7: Flash memory classes

Figure 12.8: Sequence diagram showing initialization operations



of the flash memory stick.

- 7-9 The FAController class is created. It is added as the handler for the two events created in steps 5 and 6.
- 10 Setting up the device and registering the factory is shown in detail in Figure 12.9. It involves: registering the FAController object via the static methods in the RawMemory class, and creating and using the JVM-supplied factory to access the memory-mapped I/O registers.




Figure 12.9: Sequence diagrams showing operations to initialize the hardware device

12.5.3.3 Responding to external happenings

In the example, interrupts are handled by the JVM, which turns them into an external happening. The application code that indirectly responds to the happening is provided in the handleAsyncEvent method in the FMSocketController object. Figure 12.10 illustrates the approach. In this example, the actions in response to the memory stick inserted and memory stick removed flash events is simply shown as the execution of the FMInserted and FMRemoved handlers. These will inform the application. The memory accessor classes themselves will ensure that the stick is present when performing the required application accesses.

12.5.3.4 Access to the flash controller's device registers

Figure 12.11 shows the sequence of events that the application follows. First it must register a handler with the FMInserted asynchronous event. Here, the application itself is an asynchronous event handler. When this is released, the memory has been inserted.

616 12.5 Rationale




Figure 12.10: The FMSocketController.handleAsync method

In this simple example, the application simply reads a byte from an offset within the memory stick. It, therefore, creates an accessor to access the data. When this has been returned (it is the FAController itself), the application can now call the get method (called FA get, in the following, for clarity). This method must implement the sequence of raw memory access on the device's registers to perform the operation. In Figure 12.11, they are as follows.

- 1. FA get calls the get method of the status register's accessor object. This can check to make sure that the flash memory is present (bit 6, as shown in Table 12.1). If it is not, an exception can be thrown.
- 2. Assuming the memory is present, it then sets the control register with the offset required (bits 31–63, as shown in Table 12.1) and sets the read byte request bit (bits 5-8, as shown in Table 12.1).
- 3. The FA get method must then wait for indication that the requested operation




Figure 12.11: Application usage

has been completed by the device. This is detected by the handleAsyncEvent method of the FMController, which performs the necessary notify.

- 4. Once notified of completion, the FA get method, again reads the status register to make sure there were no errors on the device (bit 4 in Table 12.1) and that the memory is still present
- 5. The FA get then reads the data register to get the requested data, which it returns.

618 12.5 Rationale

Chapter 13

System and Options

13.1 Overview

Implementations of this specification run on many operating systems and this specification itself supports several variants, therefore a means of querying and handling this variation is required. For instance, though many realtime operating systems support the POSIX standard, many do not as well, Even the ones that do vary in their degree of compliance. POSIX provides a well defined means of signalling other processes and receiving signals from them, therefore one would like to be able to use this facility when available. The specification defines classes to help manage these differences providing the following:

- a class that contains operations and semantics that affect the entire system;
- the security semantics required by the additional features in the entirety of this specification, which are additional to those required by implementations of the Java Language Specification; and
- a common idiom for binding POSIX signals to instances of AsyncEventHandler when POSIX signals are available on the underlying platform.

The RealtimeSecurity class provides security primarily for physical memory access.

13.2 Semantics

There are four classes with semantics that do not fall into other categories: Real-timeSystem, RealtimeSecurity, POISIXSignal, and POSIXRealtimeSignal. Their overall semantics is detailed below. Afterwards, semantics that apply to methods, constructors, and fields of theses classes are provided as well.

620 13.2 Semantics

13.2.0.5 RealtimeSystem

RealtimeSystem is a required class, which provides basic information about the RTSJ extensions supported by the system. Via this class, a program can query the default monitor policy, the realtime security manager, and other realtime properties of the system. Starting from version 2, a program can also ask what modules are supported. Determining the current version is supported by a system property. If an application call the method, System.getProperty(''javax.realtime.version''), the return value will be a string of the form, "x.y.z". Where 'x' is the major version number and 'y' and 'z' are minor version numbers. These version numbers state to which version of the RTSJ the underlying implementation claims conformance. The first release of the RTSJ, dated 11/2001, was numbered 1.0.0. A release conforming to this version of the specification should return the string "2.0.0".

13.2.0.6 RealtimeSecurity

The RealtimeSecurity class controls access to key realtime features. Particularly critical is access to memory outside the heap. Core RTSJ features also have security checks. This should enable an application to restrict the use of the RTSJ, particularly for dynamically loaded code. Detailed information is provided in the class documentation below.

13.2.0.7 POSIX Signals

The POSIXSignal class represents POSIX signals and is required on platforms that provide POSIX signals. As a Happening, it is a subclass of AsyncEvent and implements ActiveEvent. Unlike Happening, it cannot be instantiated by the user. Instead, an instance exists for each POSIX signal defined on the system. They can be retrieved either by name or number using the POSIXSignal.get(int) and POSIXSignal.get(String) methods.

13.2.0.8 POSIX Realtime Signals

The POSIXRealtimeSignal class represents POSIX realtime events. It is also implements ActiveEvent, but is a subclass of AsyncLongEvent, so that it can pass the data sent with its signal. As with POSIXSignal, it cannot be instantiated by the user, rather an instance exists for each POSIX signal defined on the system, which can be retrieves either by name or number using the POSIXRealtimeSignal.get(int) and POSIXRealtimeSignal.get(String) methods.

13.3 Package javax.realtime

13.3.1 Classes

13.3.1.1 GarbageCollector

The system shall provide dynamic and static information characterizing the temporal behavior and imposed overhead of any garbage collection algorithm provided by the system. This information shall be made available to applications via methods on subclasses of GarbageCollector. Implementations are allowed to provide any set of methods in subclasses as long as the temporal behavior and overhead are sufficiently categorized. The implementations are also required to fully document the subclasses.

A reference to the garbage collector responsible for heap memory is available from RealtimeSystem.currentGC()¹.

Inheritance

```
java.lang.Object
javax.realtime.GarbageCollector
```

13.3.1.1.1 Methods

getPreemptionLatency

Preemption latency is a measure of the maximum time a schedulable object may have to wait for the collector to reach a preemption-safe point.

Instances of NoHeapRealtimeThread² and async event handlers with the no-heap option preempt garbage collection immediately, but other schedulables must wait until the collector reaches a preemption-safe point. For many garbage collectors the only preemption safe point is at the end of garbage collection, but an implementation of the garbage collector could permit a schedulable to preempt garbage collection before it completes. The getPreemptionLatency method gives such a garbage collector a way to report the worst-case interval between release of a schedulable during garbage collection, and the time the schedulable starts execution or gains full access to heap memory, whichever comes later.

¹Section 13.3.1.7.2

 $^{^2}$ Section 15.3.3.3

```
Signature public abstract
```

Returns

The worst-case preemption latency of the garbage collection algorithm represented by this. The returned object is allocated in the current allocation context. When there is no constant that bounds garbage collector preemption latency, this method shall return a relative time with Long.MAX_VALUE milliseconds. The number of nanoseconds in this special value is unspecified.

javax.realtime.RelativeTime getPreemptionLatency()

13.3.1.2 POSIXRealtimeSignal

A ActiveEvent³ subclass for defining a POSIX realtime signal.

Available since RTSJ 2.0

Inheritance

```
java.lang.Object
javax.realtime.AbstractAsyncEvent
javax.realtime.AsyncLongEvent
javax.realtime.POSIXRealtimeSignal
Interfaces
ActiveEvent
```

13.3.1.2.1 Methods

get(String)

Get the registered realtime signal with the given name.

```
Signature
```

```
public static
javax.realtime.POSIXRealtimeSignal get(String name)
```

 $^{^3}$ Section 8.4.1.1

```
Parameters
```

name of the signal to get.

Returns

the registered signal with name or null.

getId(String)

Get the ID of a registered signal.

```
Signature
```

```
public static
int getId(String name)
```

Parameters

name of the signal for which to search

Returns

the ID of the signal named by name

get(int)

Get the realtime signal corresponding to a given id.

```
Signature
```

```
public static
javax.realtime.POSIXRealtimeSignal get(int id)
```

Parameters

id of a registered signal

Returns

the signal corresponding to id.

isPOSIXRealtimeSignal(String)

Determine if a signal with a given name is registered.

```
Signature
```

```
\begin{array}{c} {\rm public~static}\\ {\rm boolean~isPOSIXRealtimeSignal(String~name)} \end{array} Parameters
```

2.0 (Draft 20)

```
name of the signal Returns true when a signal with the given name is registered
```

trigger(int, long)

Release the manager for the Realtime Signal identified by the given integer. The id range for POSiX Signals is distinct from that of other types of ActiveEvent⁴. This method is provided for simulating an occurrence of a realtime POSIX signal.

```
Signature

public static

void trigger(int id, long value)

Parameters

id of a registered signal

value passed from the signaler.
```

getId

Get the name of this realtime signal.

```
Signature

public

int getId()

Returns

its name.
```

getName

Get the name of this signal.

```
Signature

public final
java.lang.String getName()

Returns
the name of this signal.

4Section 8.4.1.1
```

isActive

Determine the activation state of this signal, i.e., it has been started.

```
Signature

public
boolean isActive()

Returns

true when active, false otherwise.
```

isRunning

Determine the firing state (releasing or skipping) of this signal, i.e., it is active and enabled.

```
Signature

public
boolean isRunning()

Returns

true when releasing, false when skipping.
```

start

Throws

Start this POSIXRealtimeSignal, i.e., change to a running state. A running realtime signal is a source of activation when in a scoped memory and is a member of the root set when in the heap. A running realtime signal can be triggered. See Section stop()

```
Signature

public final synchronized

void start()

throws IllegalStateException
```

IllegalStateException when this POSIXRealtimeSignal has already been started.

2.0 (Draft 20)

start(boolean)

Start this POSIXRealtimeSignal, i.e., change to a running state. A running realtime signal is a source of activation when in a scoped memory and is a member of the root set when in the heap. A running realtime signal can be triggered. See Section stop()

```
Signature
```

```
public final synchronized
void start(boolean disabled)
throws IllegalStateException
```

Parameters

disabled true for starting in a disabled state.

Throws

IllegalStateException when this POSIXRealtimeSignal has already been started.

stop

Stop this POSIXRealtimeSignal. A stopped realtime signal ceases to be a source of activation and no longer cause any AE attached to it to be a source of activation.

```
Signature
```

```
public final
boolean stop()
throws IllegalStateException
```

Throws

 ${\it IllegalStateException}$ when this POSIXRealtimeSignal is not running.

Returns

true when this was enabled and false otherwise.

getNextValue

```
Signature
```

```
public
long getNextValue()
```

2.0 (Draft 20)

Returns

the value of the next signal

send(long, long)

Send this signal to another process

```
Signature

public native
boolean send(long pid, long payload)

Parameters

pid of the process to which to send the signal

Returns

true when signal can be sent, otherwise false.
```

getDispatcher

```
Signature
    public
    javax.realtime.POSIXRealtimeSignalDispatcher getDispatcher()
```

13.3.1.3 POSIXRealtimeSignalDispatcher

Provides a means of dispatching a set of POSIXRealtimeSignal⁵s. An application can provide its own dispatcher, providing the priority for the internal dispatching thread. This dispatching thread calls process() each time the signal is triggered.

Available since RTSJ 2.0

Inheritance

```
java.lang.Object
javax.realtime.ActiveEventDispatcher
javax.realtime.POSIXRealtimeSignalDispatcher
```

⁵Section 13.3.1.2

13.3.1.3.1 Constructors

POSIXRealtimeSignalDispatcher(SchedulingParameters)

Create a new dispatcher, whose dispatching thread runs with the given scheduling parameters.

```
Signature
```

```
public
  POSIXRealtimeSignalDispatcher(SchedulingParameters schedule)
```

Parameters

schedule give the parameters for scheduling this dispatcher

13.3.1.3.2 Methods

register(POSIXRealtimeSignal)

Register signal with this dispatcher.

```
Signature
```

```
public
void register(POSIXRealtimeSignal signal)
throws RegistrationException, IllegalStateException,
IllegalArgumentException
```

Parameters

signal to register

Throws

RegistrationException when signal is already registered. IllegalStateException when this object has been destroyed. IllegalArgumentException when signal is not stopped.

2.0 (Draft 20)

unregister(POSIXRealtimeSignal)

Deregister the signal form this dispatcher.

```
Signature

public

void unregister(POSIXRealtimeSignal signal)

throws DeregistrationException, IllegalStateException,

IllegalArgumentException

Parameters

signal to unregister

Throws

DeregistrationException when signal is not already registered.

IllegalStateException when this object has been destroyed.

IllegalArgumentException when signal is not stopped.
```

destroy

Release all reasources thereby making the dispatcher unusable.

```
Signature
    public
    void destroy()
    throws IllegalStateException
Throws
```

IllegalStateException when called on a dispatcher that has one or more registered POSIXRealtimeSignal⁶ objects.

13.3.1.4 POSIXSignal

A ActiveEvent⁷ subclass for defining a POSIX signal.

Available since RTSJ 2.0

Inheritance

```
<sup>6</sup>Section 13.3.1.2

<sup>7</sup>Section 8.4.1.1
```

```
java.lang.Object
    javax.realtime.AbstractAsyncEvent
    javax.realtime.AsyncEvent
    javax.realtime.POSIXSignal

Interfaces
    ActiveEvent
```

13.3.1.4.1 Fields

MAX_NUM_SIGNALS

public static final MAX_NUM_SIGNALS this number of signals can be processed.

13.3.1.4.2 Methods

isPOSIXSignal(String)

Determine if a signal with a given name is registered.

```
Signature

public static
boolean isPOSIXSignal(String name)

Parameters
name of the signal

Returns

true when a signal with the given name is registered
```

get(String)

Get the registered signal with the given name.

```
Signature public static
```

2.0 (Draft 20)

```
javax.realtime.POSIXSignal get(String name)
Parameters
     name of the signal to get.
Returns
     the registered signal with name or null.
getId(String)
```

Get the ID of a registered signal.

```
Signature
    public static
    int getId(String name)
name of the signal for which to search
Returns
    the ID of the signal named by name
```

get(int)

Get the signal corresponding to a given id.

```
Signature
     public static
     javax.realtime.POSIXSignal get(int id)
Parameters
     id of a registered signal
Returns
     the signal corresponding to id or null.
```

trigger(int)

Release the manager for the Signal identified by the given integer. The id range for Signals is distinct from that of other types of ActiveEvent⁸. This method is provided for simulating occurrences of a POSIX signal.

⁸Section 8.4.1.1

```
Signature

public static

void trigger(int id)

Parameters

id of a registered signal
```

getProcessId

Obtain the OS Id of the JVM process. When running in kernel space, the result is VM dependent and must be documented. This number returned is only usable with POSIXSignal.send(long)⁹.

```
Signature

public static
long getProcessId()
Returns
the OS process id.
```

getId

Get the number of this signal.

```
public
  int getId()
Returns
  the signal number
```

getName

Get the name of this signal.

Signature

 $^{^9 {}m Section} \ 13.3.1.4.2$

```
public
    java.lang.String getName()
Returns
    the name of this signal.
```

isActive

Determine the activation state of this signal, i.e., it has been started.

```
Signature

public
boolean isActive()

Returns

true when active, false otherwise.
```

isRunning

Determine the firing state (releasing or skipping) of this signal, i.e., it is active and enabled.

```
Signature

public
boolean isRunning()

Returns

true when releasing, false when skipping.
```

start

Start this POSIXSignal, i.e., change to a running state. A running signal is a source of activation when in a scoped memory and is a member of the root set when in the heap. A running signal can be triggered.

```
See Section stop()
```

```
Signature public void start()
```

```
throws IllegalStateException
```

Throws

IllegalStateException when this POSIXSignal has already been started.

start(boolean)

Start this POSIXSignal, i.e., change to a running state. A running signal is a source of activation when in a scoped memory and is a member of the root set when in the heap. A running signal can be triggered.

See Section stop()

```
Signature
```

```
public
void start(boolean disabled)
throws IllegalStateException
```

Parameters

disabled true for starting in a disabled state.

Throws

IllegalStateException when this POSIXSignal has already been started.

stop

Stop this POSIXSignal. A stopped signal ceases to be a source of activation and no longer cause any AE attached to it to be a source of activation.

```
Signature
```

```
public
boolean stop()
throws IllegalStateException
```

Throws

IllegalStateException when this POSIXSignal is not running.

Returns

true when this was enabled and false otherwise.

send(long)

Send this signal to another process or process group.

On POSIX systems running in user space, the following holds:

- when pid is positive, the signal is sent to pid;
- when pid equals 0, the signal is sent to every process in the process group of the current process;
- when pid equals -1, the signal is sent to every process for which the calling process has permission to send signals, except for possibly OS-defined system processes; otherwise
- when pid is less than -1, the signal is sent to every process in the process group -pid.

POSIX.1-2001 requires the underlying mechanism of signal.send(-1) to send signal to all processes for which the current process may signal, except possibly for some OS-defined system processes.

For an RTVM running in kernel space, the meaning of the pid is implementation dependent, though it should be as closed to the standard definition as possible.

```
public
    public
    void send(long pid)
    throws POSIXInvalidSignalException,
    POSIXSignalPermissionException, POSIXInvalidTargetException
Parameters
    pid Id of the process to which to send the signal
Throws
```

POSIXInvalidSignalException when the signal number is not valid.

POSIXSignalPermissionException when the process does not have permission to send the target.

POSIXInvalidTargetException when the target does not exist.

getDispatcher

```
Signature

public

javax.realtime.POSIXSignalDispatcher getDispatcher()
```

13.3.1.5 POSIXSignalDispatcher

Provides a means of dispatching a set of POSIXSignal¹⁰s. An application can provide its own dispatcher, providing the priority for the internal dispatching thread. This dispatching thread calls process() each time the signal is triggered.

Inheritance

```
javax.realtime.ActiveEventDispatcher
javax.realtime.POSIXSignalDispatcher
```

13.3.1.5.1 Constructors

POSIXSignalDispatcher(SchedulingParameters)

Create a new dispatcher, whose dispatching thread runs with the given scheduling parameters.

```
Signature
```

```
public
  POSIXSignalDispatcher(SchedulingParameters scheduling)
```

Parameters

scheduling give the parameters for scheduling this dispatcher

13.3.1.5.2 Methods

register(POSIXSignal)

Register a POSIX signal with this dispatcher.

```
Signature
```

```
public synchronized
void register(POSIXSignal signal)
```

 $^{^{10}}$ Section 13.3.1.4

```
throws RegistrationException, IllegalStateException, IllegalArgumentException

Parameters
signal to register

Throws
RegistrationException when signal is already registered.
IllegalStateException when this object has been destroyed.
IllegalArgumentException when signal is not stopped.
```

unregister(POSIXSignal)

Deregister a POSIX Signal form this dispatcher. (This is a really naive implementation.)

```
Signature

public synchronized
void unregister(POSIXSignal signal)
throws DeregistrationException, IllegalStateException,
IllegalArgumentException

Parameters
signal to deregister

Throws

DeregistrationException when signal not is already registered.
IllegalStateException when this object has been destroyed.
IllegalArgumentException when signal is not stopped.
```

destroy

Release all reasources thereby making the dispatcher unusable.

```
public
    void destroy()
    throws IllegalStateException
Throws
    IllegalStateException when called on a dispatcher that has one or more regis-
```

tered POSIXSignal¹¹ objects.

¹¹Section 13.3.1.4

13.3.1.6 RealtimeSecurity

Security policy object for realtime specific issues. Primarily used to control access to physical memory.

Security requirements are generally application-specific. Every implementation shall have a default RealtimeSecurity instance, and a way to install a replacement at run-time, RealtimeSystem.setSecurityManager¹². The default security is minimal. All security managers should prevent access to JVM internal data and the Java heap; additional protection is implementation-specific and must be documented.

Inheritance

```
java.lang.Object
javax.realtime.RealtimeSecurity
```

13.3.1.6.1 Constructors

RealtimeSecurity

Create an RealtimeSecurity object.

```
Signature
```

```
public
  RealtimeSecurity()
```

13.3.1.6.2 Methods

checkAccessPhysical

Check whether the application is allowed to access physical memory.

 $^{^{12}}$ Section 13.3.1.7.2

```
Signature
public
void checkAccessPhysical()
```

throws SecurityException

Throws

SecurityException The application doesn't have permission to access physical memory.

checkAccessPhysicalRange(long, long)

Checks whether the application is allowed to access physical memory within the specified range.

```
Signature
```

void checkAccessPhysicalRange(long base, long size)
throws SecurityException

Parameters

base The beginning of the address range.

size The size of the address range.

Throws

SecurityException The application doesn't have permission to access the memory in the given range.

checkSetFilter

Checks whether the application is allowed to register PhysicalMemoryTypeFilter¹³ objects with the PhysicalMemoryManager¹⁴.

Signature

```
public
void checkSetFilter()
throws SecurityException
```

Throws

SecurityException The application doesn't have permission to register filter objects.

¹³Section 15.3.1.1 ¹⁴Section 15.3.3.5

checkSetMonitorControl(MonitorControl)

Checks whether the application is allowed to set the default monitor control policy.

Available since RTSJ 1.0.1

```
public
    void checkSetMonitorControl(MonitorControl policy)
    throws SecurityException
Parameters
    policy The new policy
Throws
```

SecurityException when the application doesn't have permission to change the default monitor control policy to policy.

checkAEHSetDaemon

Checks whether the application is allowed to set the daemon status of an AEH. Available since RTSJ 1.0.1

```
Signature

public

void checkAEHSetDaemon()

throws SecurityException
```

Throws

SecurityException when the application is not permitted to alter the daemon status.

checkSetScheduler

Checks whether the application is allowed to set the scheduler.

```
Signature public
```

```
void checkSetScheduler()
throws SecurityException
```

Throws

SecurityException The application doesn't have permission to set the scheduler.

checkCreateRealtimeThread

Check if an application may create a realtime thread.

Available since RTSJ 2.0

```
Signature

public

void checkCreateRealtimeThread()

throws SecurityException

Throws

SecurityException when not allowed
```

checkCreateTimer

Check if an application may create a Timer.

Available since RTSJ 2.0

```
public
    public
    void checkCreateTimer()
    throws SecurityException
Throws
    SecurityException when not allowed.
```

checkPOSIXSendSignal(POSIXSignal, long)

Check if the given signal can be sent to the given process id.

Available since RTSJ 2.0

```
public
void checkPOSIXSendSignal(POSIXSignal signal, long pid)
throws SecurityException

Parameters
signal is the signal being sent
pid is the id to which the signal is being set.

Throws
SecurityException when the operation is not allowed.
```

13.3.1.7 RealtimeSystem

RealtimeSystem provides a means for tuning the behavior of the implementation by specifying parameters such as the maximum number of locks that can be in use concurrently, and the monitor control policy. In addition, RealtimeSystem provides a mechanism for obtaining access to the security manager, garbage collector, and scheduler, to query or set parameters.

Open issue: Should there be flags to indicate which options are implemented? End of open issue

Inheritance

```
java.lang.Object
javax.realtime.RealtimeSystem
```

13.3.1.7.1 Fields

BIG_ENDIAN

public static final BIG_ENDIAN

Value indicating that the highest order byte of a bit word is stored at the lowest byte address: the int 0x0A0B0C0D is stored in the byte sequence 0x0A, 0x0B, 0x0C, 0x0D. and the long 0x0102030405060708 is stored in the sequence 0x01, 0x02, 0x03, 0x04, 0x05, 0x06, 0x07, 0x08.

LITTLE_ENDIAN

public static final LITTLE_ENDIAN

Value indicating that the lowest order byte of a word is stored at the lowest byte address: the int 0x0A0B0C0D is stored in the byte sequence 0x0D, 0x0C, 0x0B, 0x0A and the long 0x0102030405060708 is stored in the sequence 0x08, 0x07, 0x06, 0x05, 0x04, 0x03, 0x02, 0x01.

PDP_ENDIAN

public static final PDP_ENDIAN

Value indicating a mixed endian mode used by among others the PDP-11: the int 0x0A0B0C0D is stored in the byte sequence 0x0B, 0x0A, 0x0D, 0x0C, and the long 0x0102030405060708 is stored in the sequence 0x03, 0x04, 0x01, 0x02, 0x07, 0x08, 0x05, 0x06.

BYTE_ORDER

```
public static final BYTE_ORDER
```

The byte ordering of the underlying hardware.

13.3.1.7.2 Methods

currentGC

Return a reference to the currently active garbage collector for the heap.

Signature

```
public static
javax.realtime.GarbageCollector currentGC()
```

Returns

A GarbageCollector¹⁵ object which is the current collector collecting objects on the traditional Java heap.

 $^{^{15}}$ Section 13.3.1.1

getConcurrentLocksUsed

Gets the maximum number of locks that have been used concurrently. This value can be used for tuning the concurrent locks parameter, which is used as a hint by systems that use a monitor cache.

```
Signature

public static

int getConcurrentLocksUsed()
```

An integer whose value is the maximum number of locks that have been used concurrently. When the number of concurrent locks is not tracked by the implementation, return -1. Note that when the number of concurrent locks is not tracked, the number of available concurrent locks is effectively unlimited.

getMaximumConcurrentLocks

Gets the maximum number of locks that can be used concurrently without incurring an execution time increase as set by the setMaximumConcurrentLocks() methods.

Note: Any relationship between this method and setMaximumConcurrentLocks is implementation-specific. This method returns the actual maximum number of concurrent locks the platform can currently support, or Integer.MAX_VALUE when there is no maximum. The setMaximumConcurrentLocks method give the implementation a hint as to the maximum number of concurrent locks it should expect.

```
Signature

public static

int getMaximumConcurrentLocks()
```

An integer whose value is the maximum number of locks that can be in simultaneous use.

${\tt getSecurityManager}$

Gets a reference to the security manager used to control access to realtime system features such as access to physical memory.

```
Signature
```

```
public static
javax.realtime.RealtimeSecurity getSecurityManager()
```

Returns

A RealtimeSecurity¹⁶ object representing the default realtime security manager.

setMaximumConcurrentLocks(int)

Sets the anticipated maximum number of locks that may be held or waited on concurrently. Provide a hint to systems that use a monitor cache as to how much space to dedicate to the cache.

Signature

```
public static
void setMaximumConcurrentLocks(int numLocks)
```

Parameters 5

numLocks An integer whose value becomes the number of locks that can be in simultaneous use without incurring an execution time increase. When number is less than or equal to zero nothing happens. When the system does not use this hint this method has no effect other than on the value returned by getMaximumConcurrentLocks()¹⁷.

setMaximumConcurrentLocks(int, boolean)

Sets the anticipated maximum number of locks that may be held or waited on concurrently. Provide a limit for the size of the monitor cache on systems that provide one when hard is true.

Signature

```
public static
void setMaximumConcurrentLocks(int number, boolean hard)
```



```
<sup>16</sup>Section 13.3.1.6

<sup>17</sup>Section 13.3.1.7.2
```

number The maximum number of locks that can be in simultaneous use without incurring an execution time increase. When number is less than or equal to zero nothing happens. When the system does not use this hint this method has no effect other than on the value returned by getMaximumConcurrent—Locks()¹⁸.

hard When true, number sets a limit. When a lock is attempted which would cause the number of locks to exceed number then a ResourceLimitError¹⁹ is thrown. When the system does not limit use of concurrent locks, this parameter is silently ignored.

setSecurityManager(RealtimeSecurity)

Sets a new realtime security manager.

```
Signature
```

```
public static
void setSecurityManager(RealtimeSecurity manager)
```

Parameters

manager A RealtimeSecurity²⁰ object which will become the new security manager.

Throws

SecurityException when security manager has already been set.

getInitialMonitorControl

Returns the monitor control object that represents the initial monitor control policy.

Available since RTSJ 1.0.1

```
Signature
```

The initial monitor control policy.

¹⁸Section 13.3.1.7.2

¹⁹Section 14.2.3.5

²⁰Section 13.3.1.6

supports(RTSJModule)

Determine if a particular module is supported. Available since RTSJ 2.0

Signature

public static
boolean supports(RTSJModule module)

Parameters

module of interest.

Returns

true when module is supported; otherwise false.

13.4 Rationale

This specification accommodates the variation in underlying systems in a number of ways. The RealtimeSystem class functions in similar capacity to java.lang.System. Similarly, the RealtimeSecurity class functions similarly to java.lang.SecurityManager. The concept of optionally required classes provides additional flexibility. Such classes provide a commonality that can be relied upon by program logic that intends to execute on implementations that supports a given function, such as POSIXSignal and POSIXRealtimeSignal encapsulate common functionality for POSIX compliant systems.

648 13.4 Rationale

Chapter 14

Exceptions

14.1 Overview

This section contains exceptions defined by the RTSJ. These exception classes

- provide additional exception classes required for other sections of this specification, and
- provide the ability to asynchronously transfer the control of program logic (see AsynchronouslyInterruptedException).

14.1.1 Semantics

This list establishes the semantics that are applicable across the classes of this section. Semantics that apply to particular classes, constructors, methods, and fields will be found in the class description and the constructor, method, and field detail sections.

- All classes in this section are required.
- All exceptions, except AsynchronouslyInterruptedException, are required to have semantics exactly as those of their eventual superclass in the java.* hierarchy.

The AsynchronouslyInterruptedException class is not included in this chapter. It is more closely related to asynchronous operation than to exception handling and so can be found in the Asynchrony chapter.

14.2 Package javax.realtime

14.2.1 Interfaces

14.2.1.1 PreallocatedThrowable

A marker class to indicate that a Throwable is intended to be created once and reused. Throwables that implement this interface kept their state in a Schedulable Object (SO)local data structure instead of the object itself. This means that data is only valid until the next PreallocatedThrowable is thrown in the current SO. Having a marker interface makes it easier to provide checking tools to ensure the proper throw sequence for all Throwables thrown from user code.

See Section ConfigurationParameters

14.2.1.1.1 Methods

fillInStackTrace

Calls into the virtual machine to capture the current stack trace in SO local memory.

```
Signature

public
 java.lang.Throwable fillInStackTrace()

Returns

a reference to this Throwable.
```

getMessage

get the message describing the problem from SO local memory.

```
Signature

public

java.lang.String getMessage()

2.0 (Draft 20)
```

Returns

the message given to the constructor or null when no message was set.

${\bf getLocalized Message}$

Subclasses may override this message to get an error message that is localized to the default locale.

By default it returns getMessage().

```
Signature
    public
    java.lang.String getLocalizedMessage()
Returns
    the value of getMessage().
```

initMessage(String)

Set the message in SO local storage. This is the only method that is not also defined in Throwable.

```
Signature

public

void initMessage(String message)

Parameters

message is the text to save.
```

getCause

getCause returns the cause of this exception or null when no cause was set. The cause is another exception that was caught before this exception was created.

```
public
    java.lang.Throwable getCause()
Returns
    The cause or null.
```

initCause(Throwable)

Initializes the cause to the given Throwable is SO local memory.

```
public java.lang.Throwable initCause(Throwable causingThrowable)

Parameters causingThrowable the reason why this Throwable gets Thrown.

Throws

IllegalArgumentException when the cause is this Throwable itself.

Returns
```

the reference to this Throwable.

printStackTrace

Print stack trace of this Throwable to System.err.

The printed stack trace contains the result of toString() as the first line followed by one line for each stack trace element that contains the name of the method or constructor, optionally followed by the source file name and source file line number when available.

For JamaicaVM, this routine also works before System was initialized by using low-level exception printing mechanisms provided by class com.aicas.jamaica.lang.Debug.

```
Signature
    public
    void printStackTrace()
```

printStackTrace(PrintStream)

Print the stack trace of this Throwable to the given stream.

The printed stack trace contains the result of toString() as the first line followed by one line for each stack trace element that contains the name of the method or constructor, optionally followed by the source file name and source file line number when available.

For JamaicaVM, when printing to the stream causes another exception, low-level exception printing mechanisms provided by class com.aicas.jamaica.lang.Debug will be used to print the exception to stderr.

```
Signature

public

void printStackTrace(PrintStream stream)

Parameters

stream the stream to print to.
```

printStackTrace(PrintWriter)

Print the stack trace of this Throwable to the given PrintWriter.

The printed stack trace contains the result of toString() as the first line followed by one line for each stack trace element that contains the name of the method or constructor, optionally followed by the source file name and source file line number when available.

For JamaicaVM, when printing to the PrintWriter causes another exception, low-level exception printing mechanisms provided by class com.aicas.jamaica.lang.Debug will be used to print the exception to stderr.

```
Signature

public

void printStackTrace(PrintWriter s)

Parameters

s the PrintWriter to write to.
```

getStackTrace

Get the stack trace created by fillInStackTrace for this Throwable as an array of StackTraceElements.

The stack trace does not need to contain entries for all methods that are actually on the call stack, the virtual machine may decide to skip some stack trace entries. Even an empty array is a valid result of this function.

Repeated calls of this function without intervening calls to fillInStackTrace will return the same result.

For JamaicaVM, the stack trace may omit methods that are compiled by the static compiler. Particularly, methods are compiled and that do not contain an exception handler themselves usually do not require the creation of a stack frame at runtime. To improve performance, no stack frame is generated in these cases.

When memory areas of the RTSJ are used (see MemoryArea¹), and this Throwable was allocated in a different memory area than the current allocation context, the resulting stack trace will be allocated in either the same memory area this was allocated in or the current memory area, depending on which is the least deeply nested, thereby creating objects that are assignment compatible with both areas.

```
public
    java.lang.StackTraceElement[] getStackTrace()
Returns
    array representing the stack trace, never null.
```

setStackTrace(java.lang.StackTraceElement[])

This method allows overriding the stack trace that was filled during construction of this object. It is intended to be used in a serialization context when the stack trace of a remote exception should be treated like a local.

```
public
     void setStackTrace(java.lang.StackTraceElement[] new_stackTrace)
     throws NullPointerException
Parameters
     new_stackTrace the stack trace to replace be used.
```

Throws

NullPointerException when new_stackTrace or any element of new_stackTrace is null.

14.2.2 Exceptions

$14.2.2.1 \quad Arrival Time Queue Overflow Exception$

When an arrival time occurs and should be queued but the queue already holds a number of times equal to the initial queue length defined by this an instance of this class may be thrown. When the arrival time is a result of a happening to which the instance of AsyncEventHandler is bound then the arrival time is ignored.

¹Section 11.4.2.3

Available since RTSJ 1.0.1 Becomes unchecked

Inheritance

```
java.lang.Object
    java.lang.Throwable
    java.lang.Exception
    java.lang.RuntimeException
    javax.realtime.ArrivalTimeQueueOverflowException
```

14.2.2.1.1 Constructors

Arrival Time Queue Over flow Exception

A constructor for ArrivalTimeQueueOverflowException.

Signature

```
public
   ArrivalTimeQueueOverflowException()
```

Arrival Time Queue Overflow Exception (String)

A descriptive constructor for ArrivalTimeQueueOverflowException.

Signature

```
public
   ArrivalTimeQueueOverflowException(String description)
```

Parameters

description A description of the exception.

14.2.2.2 CeilingViolationException

This exception is thrown when a schedulable or java.lang.Thread attempts to lock an object governed by an instance of PriorityCeilingEmulation² and the thread or SO's base priority exceeds the policy's ceiling.

Inheritance

```
java.lang.Object
    java.lang.Throwable
    java.lang.Exception
    java.lang.RuntimeException
    java.lang.IllegalArgumentException
    java.lang.IllegalThreadStateException
    javax.realtime.CeilingViolationException
```

14.2.2.2.1 Methods

getCeiling

Gets the ceiling of the PriorityCeilingEmulation policy which was exceeded by the base priority of an SO or thread that attempted to synchronize on an object governed by the policy, which resulted in throwing of this.

```
Signature

public

int getCeiling()

Returns
```

The ceiling of the PriorityCeilingEmulation policy which caused this exception to be thrown.

getCallerPriority

Gets the base priority of the SO or thread whose attempt to synchronize resulted in the throwing of this.

²Section 7.4.1.2

```
Signature
    public
    int getCallerPriority()
Returns
    The synchronizing thread's base priority.
```

14.2.2.3 DeregistrationException

An exception to throw when trying to deregister an ActiveEvent³ from an ActiveEventDispatcher⁴ to which it is not registered.

Available since RTSJ 2.0

Inheritance

```
java.lang.Object
    java.lang.Throwable
    java.lang.Exception
    java.lang.RuntimeException
    javax.realtime.DeregistrationException
```

14.2.2.3.1 Constructors

${\bf Deregistration Exception}$

Create an exception with neither message nor cause

⁴Section 8.4.3.3

DeregistrationException(String)

Create an exception with just a message.

Signature

public

DeregistrationException(String message)

Parameters

message a description of the reason for this exception

DeregistrationException(Throwable)

Create an exception with just a cause.

Signature

public

DeregistrationException(Throwable cause)

Parameters

cause another exception that caused to this one.

DeregistrationException(String, Throwable)

Create an exception with a message and a cause.

Signature

```
public
```

DeregistrationException(String message, Throwable cause)

Parameters

message a description of the reason for this exception cause another exception that caused to this one.

14.2.2.4 InaccessibleAreaException

The specified memory area is not on the current thread's scope stack.

Available since RTSJ 1.0.1 Becomes unchecked

Inheritance

```
java.lang.Object
    java.lang.Throwable
    java.lang.Exception
    java.lang.RuntimeException
    javax.realtime.InaccessibleAreaException
```

14.2.2.4.1 Constructors

In accessible Area Exception

A constructor for InaccessibleAreaException.

```
Signature

public

InaccessibleAreaException()
```

InaccessibleAreaException(String)

A descriptive constructor for InaccessibleAreaException.

```
public
    InaccessibleAreaException(String description)
```

Parameters

description Description of the error.

14.2.2.5 LateStartException

Exception thrown when a periodic realtime thread or timer is started after its assigned, absolute, start time.

Available since RTSJ 2.0

Inheritance

```
java.lang.Object
java.lang.Throwable
java.lang.Exception
javax.realtime.LateStartException
```

14.2.2.5.1 Constructors

LateStartException

```
public
    LateStartException()
```

LateStartException(String)

14.2.2.6 MITViolationException

Thrown by the AsyncEvent.fire()⁵ on a minimum interarrival time violation. More specifically, it is thrown under the semantics of the base priority scheduler's sporadic parameters' mitViolationExcept policy when an attempt is made to introduce a release that would violate the MIT constraint.

Available since RTSJ 1.0.1 Becomes unchecked

Inheritance

```
java.lang.Object
    java.lang.Throwable
    java.lang.Exception
    java.lang.RuntimeException
    javax.realtime.MITViolationException
```

14.2.2.6.1 Constructors

MITViolationException

A constructor for MITViolationException.

```
Signature
```

```
public
   MITViolationException()
```

MITViolationException(String)

A descriptive constructor for MITViolationException.

Signature

⁵Section 8.4.3.4.2

```
public
   MITViolationException(String description)
```

Parameters

description Description of the error.

14.2.2.7 MemoryInUseException

There has been attempt to allocate a range of physical or virtual memory that is already in use.

Inheritance

```
java.lang.Object
    java.lang.Throwable
    java.lang.Exception
    java.lang.RuntimeException
    javax.realtime.MemoryInUseException
```

14.2.2.7.1 Constructors

${\bf Memory In Use Exception}$

A constructor for MemoryInUseException.

```
Signature
```

```
public
  MemoryInUseException()
```

MemoryInUseException(String)

A descriptive constructor for MemoryInUseException.

Signature

```
public
  MemoryInUseException(String description)
```


description Description of the error.

14.2.2.8 MemoryScopeException

when construction of any of the wait-free queues is attempted with the ends of the queue in incompatible memory areas. Also thrown by wait-free queue methods when such an incompatibility is detected after the queue is constructed.

Inheritance

```
java.lang.Object
    java.lang.Throwable
    java.lang.Exception
    java.lang.RuntimeException
    javax.realtime.MemoryScopeException
```

14.2.2.8.1 Constructors

MemoryScopeException

A constructor for MemoryScopeException.

Signature

```
public
  MemoryScopeException()
```

MemoryScopeException(String)

A descriptive constructor for MemoryScopeException.

Signature

```
public
  MemoryScopeException(String description)
```

Parameters

description A description of the exception.

14.2.2.9 MemoryTypeConflictException

This exception is thrown when the PhysicalMemoryManager⁶ is given conflicting specifications for memory. The conflict can be between types in an array of memory type specifiers, or between the specifiers and a specified base address.

Available since RTSJ 1.0.1 Changed to an unchecked exception.

Available since RTSJ 2.0 Moved to package javax.realtime.memory.

Inheritance

```
java.lang.Object
    java.lang.Throwable
    java.lang.Exception
    java.lang.RuntimeException
    javax.realtime.MemoryTypeConflictException
```

14.2.2.9.1 Constructors

${\bf Memory Type Conflict Exception}$

A constructor for MemoryTypeConflictException.

Signature

```
public
   MemoryTypeConflictException()
```

 $^{^6}$ Section $\overline{15.3.3.5}$

MemoryTypeConflictException(String)

A descriptive constructor for MemoryTypeConflictException.

Signature

```
public
```

MemoryTypeConflictException(String description)

Parameters

description A description of the exception.

14.2.2.10 OffsetOutOfBoundsException

when the constructor of an ImmortalPhysicalMemory⁷, LTPhysicalMemory⁸, VT-PhysicalMemory⁹, RawMemoryAccess¹⁰, or RawMemoryFloatAccess¹¹ is given an invalid address.

Available since RTSJ 1.0.1 Becomes unchecked

Inheritance

```
java.lang.Object
    java.lang.Throwable
    java.lang.Exception
    java.lang.RuntimeException
    javax.realtime.OffsetOutOfBoundsException
```

14.2.2.10.1 Constructors

```
<sup>7</sup>Section 15.3.3.1
```

⁸Section 15.3.3.2

⁹Section 15.3.3.11

 $^{^{10}}$ Section 15.3.3.8

 $^{^{11}}$ Section 15.3.3.9

Off Set Out Of Bounds Exception

A constructor for OffsetOutOfBoundsException.

```
Signature
```

```
public
   OffsetOutOfBoundsException()
```

OffsetOutOfBoundsException(String)

A descriptive constructor for OffsetOutOfBoundsException.

Signature

```
public
   OffsetOutOfBoundsException(String description)
```

Parameters

description A description of the exception.

14.2.2.11 ProcessorAffinityException

Exception used to report processor affinity-related errors.

Available since RTSJ 2.0

Inheritance

```
java.lang.Object
    java.lang.Throwable
    java.lang.Exception
    javax.realtime.ProcessorAffinityException
```

14.2.2.11.1 Constructors

${\bf Processor Affinity Exception}$

```
public
     ProcessorAffinityException()
```

ProcessorAffinityException(String)

```
public
     ProcessorAffinityException(String msg)
```

14.2.2.12 RegistrationException

An exception to throw when trying to register an ActiveEvent¹² with an ActiveEvent-Dispatcher¹³ to which it is already registered.

Inheritance

```
java.lang.Object
    java.lang.Throwable
    java.lang.Exception
    java.lang.RuntimeException
    javax.realtime.RegistrationException
```

14.2.2.12.1 Constructors

```
<sup>12</sup>Section 8.4.1.1

<sup>13</sup>Section 8.4.3.3
```

RegistrationException

Create an exception with neither message nor cause

```
public
    RegistrationException()
```

RegistrationException(String)

Create an exception with just a message.

```
Signature
```

```
public
   RegistrationException(String message)
```

Parameters

message a description of the reason for this exception

RegistrationException(Throwable)

Create an exception with just a cause.

Signature

```
public
   RegistrationException(Throwable cause)
```

Parameters

cause another exception that caused to this one.

2.0 (Draft 20)

RegistrationException(String, Throwable)

Create an exception with a message and a cause.

Signature

```
public
```

RegistrationException(String message, Throwable cause)

Parameters 1

message a description of the reason for this exception cause another exception that caused to this one.

14.2.2.13 ScopedCycleException

Thrown when a schedulable attempts to enter an instance of ScopedMemory¹⁴ where that operation would cause a violation of the single parent rule.

Inheritance

```
java.lang.Object
    java.lang.Throwable
    java.lang.Exception
    java.lang.RuntimeException
    javax.realtime.ScopedCycleException
```

14.2.2.13.1 Constructors

ScopedCycleException

A constructor for ScopedCycleException.

Signature

¹⁴Section 11.4.2.5

```
public
   ScopedCycleException()
```

ScopedCycleException(String)

A descriptive constructor for ScopedCycleException.

```
Signature
```

```
public
   ScopedCycleException(String description)
```


description Description of the error.

14.2.2.14 SizeOutOfBoundsException

To throw when the constructor of an ImmortalPhysicalMemory¹⁵, LTPhysicalMemory¹⁶, or VTPhysicalMemory¹⁷ is given an invalid size or when a memory access generated by a raw memory accessor instance (See RawMemory¹⁸.) would cause access to an invalid address.

Available since RTSJ 1.0.1 Becomes unchecked

Available since RTSJ 2.0 Moved to package javax.realtime.memory.

Inheritance

```
java.lang.Object
    java.lang.Throwable
    java.lang.Exception
    java.lang.RuntimeException
    javax.realtime.SizeOutOfBoundsException
```

 $^{^{15}}$ Section 15.3.3.1

 $^{^{16}}$ Section 15.3.3.2

 $^{^{17}}$ Section 15.3.3.11

 $^{^{18}}$ Section 12.4.1.16

14.2.2.14.1 Constructors

${\bf Size Out Of Bounds Exception}$

A constructor for SizeOutOfBoundsException.

```
Signature
```

```
public
   SizeOutOfBoundsException()
```

SizeOutOfBoundsException(String)

A descriptive constructor for SizeOutOfBoundsException.

Signature

```
public
   SizeOutOfBoundsException(String description)
```


description The description of the exception.

14.2.2.15 UnknownHappeningException

This exception is used to indicate a situation where an instance of AsyncEvent¹⁹ attempts to bind to a happening that does not exist.

Deprecated since RTSJ version since RTSJ 2.0

Inheritance

```
java.lang.Object
```

¹⁹Section 8.4.3.4

java.lang.Throwable java.lang.Exception java.lang.RuntimeException javax.realtime.UnknownHappeningException

14.2.2.15.1 Constructors

UnknownHappeningException

A constructor for UnknownHappeningException.

```
Signature
```

```
public
```

UnknownHappeningException()

UnknownHappeningException(String)

A descriptive constructor for UnknownHappeningException.

Signature

```
public
```

UnknownHappeningException(String description)

Parameters

description Description of the error.

14.2.2.16 UnsupportedPhysicalMemoryException

Thrown when the underlying hardware does not support the type of physical memory requested.

See Section PhysicalMemoryFactory

Available since RTSJ 1.0.1 Becomes unchecked

Available since RTSJ 2.0 Moved to package javax.realtime.memory.

Inheritance

```
java.lang.Object
    java.lang.Throwable
    java.lang.Exception
    java.lang.RuntimeException
    java.realtime.UnsupportedPhysicalMemoryException
```

14.2.2.16.1 Constructors

Unsupported Physical Memory Exception

A constructor for UnsupportedPhysicalMemoryException.

```
Signature
```

```
public
UnsupportedPhysicalMemoryException()
```

UnsupportedPhysicalMemoryException(String)

A descriptive constructor for UnsupportedPhysicalMemoryException.

```
Signature
```

```
public
   UnsupportedPhysicalMemoryException(String description)
```

Parameters

description The description of the exception.

2.0 (Draft 20)

14.2.3 Classes

14.2.3.1 AlignmentError

The exception thrown on an on a request for a raw memory factory to return memory for a base address that is aligned such that the factory cannot guarantee that loads and stores based on that address will meet the factory's specifications. For instance, on many processors, odd addresses are unsuitable for anything but byte access.

Inheritance

```
java.lang.Object
java.lang.Throwable
java.lang.Error
javax.realtime.AlignmentError
```

14.2.3.1.1 Constructors

AlignmentError

```
Signature

public

AlignmentError()
```

14.2.3.2 BacktraceManagement

Provide the static methods for managing the thread local memory used for storing the data needed by preallocated exceptions. Preallocated methods can implement their methods using these methods. User code should not call these methods directly.

Available since RTSJ 2.0

Inheritance

```
java.lang.Object
javax.realtime.BacktraceManagement
```

14.2.3.2.1 Constructors

Backtrace Management

```
Signature

public

BacktraceManagement()
```

14.2.3.2.2 Methods

fillInStackTrace

Capture the current thread's stack trace and save it in thread local storage. Only the part of the stack trace that fits in the preallocated buffer is stored. This method should be called by a preallocated exception to implement its method of the same name.

```
Signature

public static

void fillInStackTrace()
```

getMessage

Get the message from thread local storage that was saved by the last preallocated exception thrown. This method should be called by a preallocated exception to implement its method of the same name.

Signature

```
public static
  java.lang.String getMessage()
Returns
  the message
```

initMessage(String)

Save the message in thread local storage for later retrieval. Only the part of the message that fits in the preallocated buffer is stored. This method should be called by a preallocated exception to implement its method of the same name.

```
Signature

public static

void initMessage(String message)

Parameters

message the message to save.
```

getCause

Get the cause from thread local storage that was saved by the last preallocated exception thrown. The actual exception that of the cause is not saved, but just a reference to its type. This returns a newly allocated exception without any valid content, i.e., no valid stack trace. This method should be called by a preallocated exception to implement its method of the same name.

```
Signature

public static
java.lang.Throwable getCause()

Returns
the message
```

initCause(Throwable)

Save the message in thread local storage for later retrieval. Only a reference to the exception class is stored. The rest of its information is lost. This method should be called by a preallocated exception to implement its method of the same name.

```
Signature

public static

void initCause(Throwable causingThrowable)

Parameters

causingThrowable
```

getStackTrace

Get the stack trace from thread local storage that was saved by the last preallocated exception thrown. This method should be called by a preallocated exception to implement its method of the same name.

```
Signature

public static
 java.lang.StackTraceElement[] getStackTrace()

Returns

an array of the elements of the stack trace.
```

14.2.3.3 IllegalAssignmentError

The exception thrown on an attempt to make an illegal assignment. For example, this will be thrown on any attempt to assign a reference to an object in scoped memory (an area of memory identified be an instance of ScopedMemory²⁰) to a field of an object in immortal memory.

Inheritance

```
java.lang.Object
java.lang.Throwable
java.lang.Error
javax.realtime.IllegalAssignmentError
```

14.2.3.3.1 Constructors

 $^{^{20}}$ Section 11.4.2.5

IllegalAssignmentError

```
A constructor for IllegalAssignmentError.
```

```
Signature

public

IllegalAssignmentError()
```

IllegalAssignmentError(String)

A descriptive constructor for IllegalAssignmentError.

```
Signature
```

```
public
   IllegalAssignmentError(String description)
```

Parameters

description Description of the error.

14.2.3.4 MemoryAccessError

This error is thrown on an attempt to refer to an object in an inaccessible Memory-Area²¹. For example this will be when logic in a NoHeapRealtimeThread²² attempts to refer to an object in the traditional Java heap.

Inheritance

```
java.lang.Object
java.lang.Throwable
java.lang.Error
javax.realtime.MemoryAccessError
```

 $^{^{21}}$ Section 11.4.2.3

²²Section 15.3.3.3

14.2.3.4.1 Constructors

MemoryAccessError

A constructor for MemoryAccessError.

```
Signature
```

```
public
  MemoryAccessError()
```

MemoryAccessError(String)

A descriptive constructor for MemoryAccessError.

Signature

```
public
  MemoryAccessError(String description)
```

Parameters 1

description Description of the error.

14.2.3.5 ResourceLimitError

when an attempt is made to exceed a system resource limit, such as the maximum number of locks.

Inheritance

```
java.lang.Object
java.lang.Throwable
java.lang.Error
javax.realtime.ResourceLimitError
```

2.0 (Draft 20)

14.2.3.5.1 Constructors

ResourceLimitError

A constructor for ResourceLimitError.

```
Signature

public

ResourceLimitError()
```

ResourceLimitError(String)

A descriptive constructor for ResourceLimitError.

```
Signature

public

ResourceLimitError(String description)
```

Parameters

description The description of the exception.

14.2.3.6 ThrowBoundaryError

The error thrown by MemoryArea.enter(Runnable logic)²³ when a Throwable allocated from memory that is not usable in the surrounding scope tries to propagate out of the scope of the enter.

Inheritance

```
java.lang.Object
java.lang.Throwable
java.lang.Error
```

 $^{^{23}}$ Section 11.4.2.3.2

 ${\it javax.} real time. Throw Boundary Error \\ {\it Interfaces}$

PreallocatedThrowable

14.2.3.6.1 Constructors

${\bf Throw Boundary Error}$

A constructor for ThrowBoundaryError.

Signature

public

ThrowBoundaryError()

ThrowBoundaryError(String)

A descriptive constructor for ThrowBoundaryError.

Signature

public

ThrowBoundaryError(String description)

Parameters

description Description of the error.

14.2.3.6.2 Methods

getPreallocatedThrowable

Get the preallocated instance of this exception.

```
Signature

public

javax.realtime.ThrowBoundaryError getPreallocatedThrowable()

Returns

the preallocated instance of this exception.
```

initMessage(String)

```
Signature

public

void initMessage(String message)
```

14.2.4 Rationale

The need for additional exceptions given the new semantics added by the other sections of this specification is obvious. That the specification attaches new, nonconventional, exception semantics to AsynchronouslyInterruptedException is, perhaps, not so obvious. However, after careful thought, and given our self-imposed directive that only well-defined code blocks would be subject to having their control asynchronously transferred, the chosen mechanism is logical.

Chapter 15

Deprecated Classes

15.1 Overview

Since modules are new in 2.0 and this version introduces new ways of handling happening, POSIX signals, and raw memory access, there is no need to include the old API in the RTSJ subsets. Therefore the depricated classes have moved here. Only full implementation of the RTSJ should implement them.

15.2 Semantics

Implementations of these classes are optional. They are only needed for backward compatibility. They should not be included in implementations that do not include all modules.

15.3 Package javax.realtime

15.3.1 Interfaces

15.3.1.1 PhysicalMemoryTypeFilter

Implementation or device providers may include classes that implement PhysicalMemoryTypeFilter which allow additional characteristics of memory in devices to be specified. Implementations of PhysicalMemoryTypeFilter are intended to be used by the PhysicalMemoryManager¹, not directly from application code.

Deprecated since RTSJ version as of RTSJ 2.0

15.3.1.1.1 Methods

contains(long, long)

Queries the system about whether the specified range of memory contains any of this type.

See Section PhysicalMemoryManager.isRemovable

Signature

public

boolean contains(long base, long size)

Parameters

base The physical address of the beginning of the memory region.

size The size of the memory region.

Throws

IllegalArgumentException when base or size is negative.

OffsetOutOfBoundsException when base is less than zero.

SizeOutOfBoundsException when base plus size would be greater than the physical addressing range of the processor.

Returns

true when the specified range contains ANY of this type of memory.

 $^{^{1}}$ Section 15.3.3.5

find(long, long)

Search for physical memory of the right type.

```
Signature
```

```
public
long find(long base, long size)
```

Parameters

base The physical address at which to start searching. size The amount of memory to be found.

Throws

OffsetOutOfBoundsException when base is less than zero.

SizeOutOfBoundsException when base plus size would be greater than the physical addressing range of the processor.

IllegalArgumentException when base or size is negative.

Returns

The address where memory was found or -1 when it was not found.

getVMAttributes

Gets the virtual memory attributes of this. The value of this field is as defined for the POSIX mmap function's prot parameter for the platform. The meaning of the bits is platform-dependent. POSIX defines constants for PROT_READ, PROT_WRITE, PROT_EXEC, and PROT_NONE.

```
Signature
```

```
public
int getVMAttributes()
```

Returns

The virtual memory attributes as an integer.

getVMFlags

Gets the virtual memory flags of this. The value of this field is as defined for the POSIX mmap function's flags parameter for the platform. The meaning of the bits is platform-dependent. POSIX defines constants for MAP_SHARED, MAP_PRIVATE, and MAP_FIXED.

```
Signature

public
int getVMFlags()

Returns

The virtual memory flags as an integer.
```

initialize(long, long, long)

When configuration is required for memory to fit the attribute of this object, do the configuration here.

```
public
    void initialize(long base, long vBase, long size)

Parameters
    base The address of the beginning of the physical memory region.
    vBase The address of the beginning of the virtual memory region.
    size The size of the memory region.
Throws
```

IllegalArgumentException when base or size is negative.

OffsetOutOfBoundsException when base is less than zero.

SizeOutOfBoundsException when base plus size would be greater than the physical addressing range of the processor, or vBase plus size would exceed the virtual addressing range of the processor.

isPresent(long, long)

Queries the system about the existence of the specified range of physical memory. See Section PhysicalMemoryManager.isRemoved

```
Signature

public
boolean isPresent(long base, long size)

Parameters
base The address of the beginning of the memory region.

2.0 (Draft 20)
```

size The size of the memory region.

Throws

IllegalArgumentException when the base and size do not fall into this type of memory.

OffsetOutOfBoundsException when base is less than zero.

SizeOutOfBoundsException when base plus size would be greater than the physical addressing range of the processor.

Returns

True when all of the memory is present. False when any of the memory has been removed.

isRemovable

Queries the system about the removability of this memory.

```
Signature

public

boolean isRemovable()
```

Returns

true when this type of memory is removable.

onInsertion(long, long, AsyncEvent)

Register the specified AsyncEvent² to fire when any memory of this type in the range is added to the system.

Available since RTSJ 1.0.1

```
public
void onInsertion(long base, long size, AsyncEvent ae)

Parameters
base The starting address in physical memory.
size The size of the memory area.
ae The async event to fire.

Throws

2Section 8.4.3.4
```

IllegalArgumentException when ae is null, or when the specified range contains no removable memory of this type. IllegalArgumentException may also be thrown when size is less than zero.

OffsetOutOfBoundsException when base is less than zero.

SizeOutOfBoundsException when base plus size would be greater than the physical addressing range of the processor.

onRemoval(long, long, AsyncEvent)

Register the specified AE to fire when any memory in the range is removed from the system.

Available since RTSJ 1.0.1

Signature

public

void onRemoval(long base, long size, AsyncEvent ae)

Parameters

base The starting address in physical memory.

size The size of the memory area.

ae The async event to register.

Throws

IllegalArgumentException when the specified range contains no removable memory of this type, when ae is null, or when size is less than zero.

OffsetOutOfBoundsException when base is less than zero.

SizeOutOfBoundsException when base plus size would be greater than the physical addressing range of the processor.

unregisterInsertionEvent(long, long, AsyncEvent)

Unregister the specified insertion event. The event is only unregistered when all three arguments match the arguments used to register the event, except that ae of null matches all values of ae and will unregister every ae that matches the address range.

Note: This method has no effect on handlers registered directly as async event handlers.

Available since RTSJ 1.0.1

Signature

public

boolean unregisterInsertionEvent(long base, long size,

AsyncEvent ae)

base The starting address in physical memory associated with ae.

size The size of the memory area associated with ae.

ae The event to unregister.

Throws

IllegalArgumentException when size is less than 0.

OffsetOutOfBoundsException when base is less than zero.

SizeOutOfBoundsException when base plus size would be greater than the physical addressing range of the processor.

Returns

True when at least one event matched the pattern, false when no such event was found.

unregisterRemovalEvent(long, long, AsyncEvent)

Unregister the specified removal event. The async event is only unregistered when all three arguments match the arguments used to register the event, except that ae of null matches all values of ae and will unregister every ae that matches the address range. Note: This method has no effect on handlers registered directly as async event handlers.

Available since RTSJ 1.0.1

Signature

public

boolean unregisterRemovalEvent(long base, long size, AsyncEvent ae)

Parameters

base The starting address in physical memory associated with ae.

size The size of the memory area associated with ae.

ae The async event to unregister.

Throws

IllegalArgumentException when size is less than 0.

OffsetOutOfBoundsException when base is less than zero.

2.0 (Draft 20)

SizeOutOfBoundsException when base plus size would be greater than the physical addressing range of the processor.

Returns

True when at least one event matched the pattern, false when no such event was found.

vFind(long, long)

Search for virtual memory of the right type. This is important for systems where attributes are associated with particular ranges of virtual memory.

Signature

public

long vFind(long base, long size)

Parameters 1

base The address at which to start searching.

size The amount of memory to be found.

Throws

OffsetOutOfBoundsException when base is less than zero.

SizeOutOfBoundsException when base plus size would be greater than the physical addressing range of the processor.

IllegalArgumentException when base or size is negative. IllegalArgumentException may also be when base is an invalid virtual address.

Returns

The address where memory was found or -1 when it was not found.

15.3.2 Exceptions

15.3.2.1 DuplicateFilterException

PhysicalMemoryManager³ can only accommodate one filter object for each type of memory. It throws this exception when an attempt is made to register more than one filter for a type of memory.

Deprecated since RTSJ version since RTSJ 2.0

Inheritance

 $^{^3}$ Section 15.3.3.5

```
java.lang.Object
java.lang.Throwable
java.lang.Exception
javax.realtime.DuplicateFilterException
```

15.3.2.1.1 Constructors

DuplicateFilterException

A constructor for DuplicateFilterException.

```
Signature
    public
        DuplicateFilterException()
```

DuplicateFilterException(String)

A descriptive constructor for DuplicateFilterException.

DuplicateFilterException(String description)

```
Signature public
```

Parameters 1

description Description of the error.

15.3.2.2 UnknownHappeningException

This exception is used to indicate a situation where an instance of AsyncEvent⁴ attempts to bind to a happening that does not exist.

⁴Section 8.4.3.4

Deprecated since RTSJ version since RTSJ 2.0

Inheritance

```
java.lang.Object
    java.lang.Throwable
    java.lang.Exception
    java.lang.RuntimeException
    javax.realtime.UnknownHappeningException
```

15.3.2.2.1 Constructors

UnknownHappeningException

A constructor for UnknownHappeningException.

```
Signature
```

```
public
   UnknownHappeningException()
```

${\bf Unknown Happening Exception (String)}$

A descriptive constructor for UnknownHappeningException.

Signature

```
public
   UnknownHappeningException(String description)
```

Parameters

description Description of the error.

2.0 (Draft 20)

15.3.3 Classes

15.3.3.1 ImmortalPhysicalMemory

An instance of ImmortalPhysicalMemory allows objects to be allocated from a range of physical memory with particular attributes, determined by their memory type. This memory area has the same restrictive set of assignment rules as ImmortalMemory⁵ memory areas, and may be used in any execution context where ImmortalMemory is appropriate.

No provision is made for sharing object in ImmortalPhysicalMemory with entities outside the JVM that creates them, and, while the memory backing an instance of ImmortalPhysicalMemory could be shared by multiple JVMs, the class does not support such sharing.

Methods from ImmortalPhysicalMemory should be overridden only by methods that use super.

Deprecated since RTSJ version since RTSJ 2.0

Inheritance

```
javax.realtime.MemoryArea
javax.realtime.ImmortalPhysicalMemory
```

15.3.3.1.1 Constructors

ImmortalPhysicalMemory(Object, long)

Create an instance with the given parameters.

Signature

```
public
   ImmortalPhysicalMemory(Object type, long size)
```

Parameters

⁵Section 11.4.2.2

type An instance of Object representing the type of memory required (e.g., dma, shared) - used to define the base address and control the mapping. When the required memory has more than one attribute type may be an array of objects. When type is null or a reference to an array with no entries, any type of memory is acceptable. Note that type values are compared by reference (==), not by value (equals).

size The size of the area in bytes.

Throws

SecurityException when the application doesn't have permissions to access physical memory or the given type of memory.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryTypeFilter⁶ has been registered with the PhysicalMemoryManager⁷.

MemoryTypeConflictException when type specifies incompatible memory attributes.

IllegalArgumentException when size is less than zero.

OutOfMemoryError when there is insufficient memory for the ImmortalPhysicalMemory object or for the backing memory.

SizeOutOfBoundsException when the size extends into an invalid range of memory.

ImmortalPhysicalMemory(Object, long, long)

Create an instance with the given parameters.

Signature

public

ImmortalPhysicalMemory(Object type, long base, long size)

Parameters

type An instance of Object or an array of objects representing the type of memory required (e.g., dma, shared) - used to define the base address and control the mapping. When the required memory has more than one attribute type may be an array of objects. When type is null or a reference to an array with no entries, any type of memory is acceptable. Note that type values are compared by reference (==), not by value (equals).

 $^{^6}$ Section 15.3.1.1

⁷Section 15.3.3.5

base The physical memory address of the area.

size The size of the area in bytes.

Throws

SecurityException when the application doesn't have permissions to access physical memory or the given range of memory.

OffsetOutOfBoundsException when the base address is invalid.

SizeOutOfBoundsException when the size extends into an invalid range of memory.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryTypeFilter⁸ has been registered with the PhysicalMemoryManager⁹.

MemoryTypeConflictException when the specified base does not point to memory that matches the requested type, or when type specifies incompatible memory attributes.

IllegalArgumentException when size is less than zero. IllegalArgumentException may also be when base plus size would be greater than the maximum physical address supported by the processor.

MemoryInUseException when the specified memory is already in use.

OutOfMemoryError when there is insufficient memory for the ImmortalPhysicalMemory object or for the backing memory.

ImmortalPhysicalMemory(Object, SizeEstimator)

Create an instance with the given parameters.

Signature

public

ImmortalPhysicalMemory(Object type, SizeEstimator size)

Parameters

type An instance of Object or an array of objects representing the type of memory required (e.g., dma, shared) - used to define the base address and control the mapping. When the required memory has more than one attribute type may be an array of objects. When type is null or a reference to an array with no entries, any type of memory is acceptable. Note that type values are compared by reference (==), not by value (equals).

⁸Section 15.3.1.1

⁹Section 15.3.3.5

size A size estimator for this area.

Throws

SecurityException when the application doesn't have permissions to access physical memory or the given type of memory.

SizeOutOfBoundsException when the size estimate from size extends into an invalid range of memory.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryTypeFilter¹⁰ has been registered with the PhysicalMemoryManager¹¹.

Memory Type Conflict Exception when type specifies incompatible memory attributes.

IllegalArgumentException when size is null, or size.getEstimate() is negative.

OutOfMemoryError when there is insufficient memory for the ImmortalPhysicalMemory object or for the backing memory.

ImmortalPhysicalMemory(Object, long, SizeEstimator)

Create an instance with the given parameters.

Signature

public

ImmortalPhysicalMemory(Object type, long base, SizeEstimator size)

Parameters 1 4 1

type An instance of Object or an array of objects representing the type of memory required (e.g., dma, shared) - used to define the base address and control the mapping. When the required memory has more than one attribute type may be an array of objects. When type is null or a reference to an array with no entries, any type of memory is acceptable. Note that type values are compared by reference (==), not by value (equals).

base The physical memory address of the area.

size A size estimator for this memory area.

Throws

SecurityException when the application doesn't have permissions to access physical memory or the given type of memory.

 $^{^{10}}$ Section 15.3.1.1

 $^{^{11}}$ Section 15.3.3.5

OffsetOutOfBoundsException when the base address is invalid.

SizeOutOfBoundsException when the size estimate from size extends into an invalid range of memory.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryTypeFilter¹² has been registered with the PhysicalMemoryManager¹³.

MemoryTypeConflictException when the specified base does not point to memory that matches the requested type, or when type specifies incompatible memory attributes.

IllegalArgumentException when size is null, or size.getEstimate() is negative. IllegalArgumentException may also be when base plus the size indicated by size would be greater than the maximum physical address supported by the processor.

MemoryInUseException when the specified memory is already in use.

OutOfMemoryError when there is insufficient memory for the ImmortalPhysicalMemory object or for the backing memory.

ImmortalPhysicalMemory(Object, long, Runnable)

Create an instance with the given parameters.

Signature

public

ImmortalPhysicalMemory(Object type, long size, Runnable logic)

Parameters

type An instance of Object or an array of objects representing the type of memory required (e.g., dma, shared) - used to define the base address and control the mapping. When the required memory has more than one attribute type may be an array of objects. When type is null or a reference to an array with no entries, any type of memory is acceptable. Note that type values are compared by reference (==), not by value (equals).

size The size of the area in bytes.

logic The run() method of this object will be called whenever MemoryArea.enter()¹⁴ is called. When logic is null, logic must be supplied when the memory area is entered.

¹²Section 15.3.1.1

¹³Section 15.3.3.5

 $^{^{14}}$ Section 11.4.2.3.2

Throws

SecurityException when the application doesn't have permissions to access physical memory or the given type of memory.

SizeOutOfBoundsException when size extends into an invalid range of memory.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryTypeFilter¹⁵ has been registered with the PhysicalMemoryManager¹⁶.

IllegalArgumentException when size is negative.

Memory Type Conflict Exception when the specified base does not point to memory that matches the requested type, or when type specifies incompatible memory attributes.

OutOfMemoryError when there is insufficient memory for the ImmortalPhysicalMemory object or for the backing memory.

IllegalAssignmentError when storing logic in this would violate the assignment rules.

ImmortalPhysicalMemory(Object, long, long, Runnable)

Create an instance with the given parameters.

Signature

public

ImmortalPhysicalMemory(Object type, long base, long size, Runnable logic)

Parameters

type An instance of Object or an array of objects representing the type of memory required (e.g., dma, shared) - used to define the base address and control the mapping. When the required memory has more than one attribute type may be an array of objects. When type is null or a reference to an array with no entries, any type of memory is acceptable. Note that type values are compared by reference (==), not by value (equals).

base The physical memory address of the area.

size The size of the area in bytes.

¹⁵Section 15.3.1.1

 $^{^{16}}$ Section 15.3.3.5

logic The run() method of this object will be called whenever MemoryArea.enter()¹⁷ is called. When logic is null, logic must be supplied when the memory area is entered.

Throws

SecurityException when the application doesn't have permissions to access physical memory or the given type of memory.

OffsetOutOfBoundsException when the base address is invalid.

SizeOutOfBoundsException when size extends into an invalid range of memory.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryTypeFilter¹⁸ has been registered with the PhysicalMemoryManager¹⁹.

MemoryTypeConflictException when the specified base does not point to memory that matches the requested type, or when type specifies incompatible memory attributes.

IllegalArgumentException when size is negative. IllegalArgumentException may also be when base plus size would be greater than the maximum physical address supported by the processor.

MemoryInUseException when the specified memory is already in use.

OutOfMemoryError when there is insufficient memory for the ImmortalPhysicalMemory object or for the backing memory.

IllegalAssignmentError when storing logic in this would violate the assignment rules.

ImmortalPhysicalMemory(Object, SizeEstimator, Runnable)

Create an instance with the given parameters.

Signature

public

ImmortalPhysicalMemory(Object type, SizeEstimator size, Runnable logic)

Parameters

 $^{^{17}}$ Section 11.4.2.3.2

¹⁸Section 15.3.1.1

¹⁹Section 15.3.3.5

type An instance of Object or an array of objects representing the type of memory required (e.g., dma, shared) - used to define the base address and control the mapping. When the required memory has more than one attribute type may be an array of objects. When type is null or a reference to an array with no entries, any type of memory is acceptable. Note that type values are compared by reference (==), not by value (equals).

size A size estimator for this area.

logic The run() method of this object will be called whenever MemoryArea.enter()²⁰ is called. When logic is null, logic must be supplied when the memory area is entered.

Throws

SecurityException when the application doesn't have permissions to access physical memory or the given type of memory.

SizeOutOfBoundsException when the size extends into an invalid range of memory.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryTypeFilter²¹ has been registered with the PhysicalMemoryManager²².

IllegalArgumentException when size is null, or size.getEstimate() is negative.

Memory Type Conflict Exception when type specifies incompatible memory attributes.

OutOfMemoryError when there is insufficient memory for the ImmortalPhysicalMemory object or for the backing memory.

IllegalAssignmentError when storing logic in this would violate the assignment rules.

ImmortalPhysicalMemory(Object, long, SizeEstimator, Runnable)

Create an instance with the given parameters.

Signature

public

ImmortalPhysicalMemory(Object type, long base, SizeEstimator size, Runnable logic)

²⁰Section 11.4.2.3.2

²¹Section 15.3.1.1

 $^{^{22}}$ Section 15.3.3.5

type An instance of Object or an array of objects representing the type of memory required (e.g., dma, shared) - used to define the base address and control the mapping. When the required memory has more than one attribute type may be an array of objects. When type is null or a reference to an array with no entries, any type of memory is acceptable. Note that type values are compared by reference (==), not by value (equals).

base The physical memory address of the area.

size A size estimator for this memory area.

logic The run() method of this object will be called whenever MemoryArea.enter()²³ is called. When logic is null, logic must be supplied when the memory area is entered.

Throws

SecurityException when the application doesn't have permissions to access physical memory or the given type of memory.

OffsetOutOfBoundsException when the base address is invalid.

SizeOutOfBoundsException when the size estimate from size extends into an invalid range of memory.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryTypeFilter²⁴ has been registered with the PhysicalMemoryManager²⁵.

Memory Type Conflict Exception when the specified base does not point to memory that matches the requested type, or when type specifies incompatible memory attributes.

IllegalArgumentException when size is null, or size.getEstimate() is negative. IllegalArgumentException may also be when base plus the size indicated by size would be greater than the maximum physical address supported by the processor.

MemoryInUseException when the specified memory is already in use.

OutOfMemoryError when there is insufficient memory for the ImmortalPhysicalMemory object or for the backing memory.

IllegalAssignmentError when storing logic in this would violate the assignment rules.

15.3.3.1.2 Methods

 $^{^{23}}$ Section 11.4.2.3.2

 $^{^{24}}$ Section 15.3.1.1

 $^{^{25}}$ Section 15.3.3.5

executeInArea(Runnable)

Open issue: AJW: Why is this method here? Execute the run method from the logic parameter using this memory area as the current allocation context. For a schedulable, this saves the current scope stack and replaces it with one consisting only of the ImmortalMemory instance; restoring the original scope stack upon completion. End of open issue

```
Signature

public

void executeInArea(Runnable logic)
```

Parameters 1

logic The runnable object whose run() method should be executed.

Throws

IllegalArgumentException when logic is null.

visitScopedChildren(javax.realtime.ChildScopeVisitor<R>)

Open issue: AJW: Why is this method here? Visit each scoped memory area who's parent is the primordial scope and was created in this immortal memory area. **End of open issue**

```
Signature
```

```
public
R visitScopedChildren(javax.realtime.ChildScopeVisitor<R>
visitor)
```

Parameters

visitor invoke the ChildScopeVisitor.visit(ScopedMemory)²⁶ method for each member of the set of scoped memory areas that was created in this immortal memory area and has the primordial scope as its parent.

Throws

IllegalArgumentException @inheritDoc

Returns

@inheritDoc

²⁶Section 11.4.1.1.1

15.3.3.2 LTPhysicalMemory

An instance of LTPhysicalMemory allows objects to be allocated from a range of physical memory with particular attributes, determined by their memory type. This memory area has the same semantics as ScopedMemory²⁷ memory areas, and the same performance restrictions as LTMemory²⁸.

No provision is made for sharing object in LTPhysicalMemory with entities outside the JVM that creates them, and, while the memory backing an instance of LTPhysicalMemory could be shared by multiple JVMs, the class does not support such sharing.

Methods from LTPhysicalMemory should be overridden only by methods that use super.

Deprecated since RTSJ version since RTSJ 2.0

Inheritance

```
java.lang.Object
javax.realtime.MemoryArea
javax.realtime.ScopedMemory
javax.realtime.LTPhysicalMemory
```

15.3.3.2.1 Constructors

LTPhysicalMemory(Object, long)

Create an instance of LTPhysicalMemory with the given parameters. See Section PhysicalMemoryManager

```
Signature
```

```
public
  LTPhysicalMemory(Object type, long size)
```

 $^{^{27}}$ Section 11.4.2.5

²⁸Section 11.5.3.1

Parameters

type An instance of Object representing the type of memory required (e.g., dma, shared) - used to define the base address and control the mapping. When the required memory has more than one attribute, type may be an array of objects. When type is null or a reference to an array with no entries, any type of memory is acceptable. Note that type values are compared by reference (==), not by value (equals).

size The size of the area in bytes.

Throws

SecurityException when the application doesn't have permissions to access physical memory or the given type of memory.

IllegalArgumentException when size is less than zero.

SizeOutOfBoundsException when the implementation detects size extends beyond physically addressable memory.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryTypeFilter²⁹ has been registered with the PhysicalMemoryManager³⁰.

MemoryTypeConflictException when type specifies incompatible memory attributes.

LTPhysicalMemory(Object, long, long)

Create an instance of LTPhysicalMemory with the given parameters. See Section PhysicalMemoryManager

Signature

public

LTPhysicalMemory(Object type, long base, long size)

Parameters 1 4 1

type An instance of Object representing the type of memory required (e.g., dma, shared) - used to define the base address and control the mapping. When the required memory has more than one attribute, type may be an array of objects. When type is null or a reference to an array with no entries, any type

 $^{^{29}}$ Section 15.3.1.1

 $^{^{30}}$ Section 15.3.3.5

of memory is acceptable. Note that type values are compared by reference (==), not by value (equals).

base The physical memory address of the area.

size The size of the area in bytes.

Throws

SecurityException when the application doesn't have permissions to access physical memory or the given type of memory.

SizeOutOfBoundsException when the size is less than zero, or the implementation detects that base plus size extends beyond physically addressable memory.

OffsetOutOfBoundsException when the address is invalid.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryTypeFilter³¹ has been registered with the PhysicalMemoryManager³².

MemoryTypeConflictException when the specified base does not point to memory that matches the requested type, or when type specifies incompatible memory attributes.

IllegalArgumentException when size is less than zero.

MemoryInUseException when the specified memory is already in use.

LTPhysicalMemory(Object, SizeEstimator)

Create an instance of LTPhysicalMemory with the given parameters.

See Section PhysicalMemoryManager

Signature

public

LTPhysicalMemory(Object type, SizeEstimator size)

Parameters

type An instance of Object representing the type of memory required (e.g., dma, shared) - used to define the base address and control the mapping. When the required memory has more than one attribute, type may be an array of objects. When type is null or a reference to an array with no entries, any type

 $^{^{31}}$ Section 15.3.1.1

³²Section 15.3.3.5

of memory is acceptable. Note that type values are compared by reference (==), not by value (equals).

size A size estimator for this area.

Throws

SecurityException when the application doesn't have permissions to access physical memory or the given type of memory.

SizeOutOfBoundsException when the implementation detects that size extends beyond physically addressable memory.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryTypeFilter³³ has been registered with the PhysicalMemoryManager³⁴.

MemoryTypeConflictException when type specifies incompatible memory attributes.

IllegalArgumentException when size is null, or size.getEstimate() is negative.

LTPhysicalMemory(Object, long, SizeEstimator)

Create an instance of LTPhysicalMemory with the given parameters. See Section PhysicalMemoryManager

Signature

```
public
```

LTPhysicalMemory(Object type, long base, SizeEstimator size)

Parameters 1 4 1

type An instance of Object representing the type of memory required (e.g., dma, shared) - used to define the base address and control the mapping. When the required memory has more than one attribute, type may be an array of objects. When type is null or a reference to an array with no entries, any type of memory is acceptable. Note that type values are compared by reference (==), not by value (equals).

base The physical memory address of the area.

size A size estimator for this memory area.

Throws

 $^{^{33}}$ Section 15.3.1.1

 $^{^{34}}$ Section 15.3.3.5

SecurityException when the application doesn't have permissions to access physical memory or the given type of memory.

SizeOutOfBoundsException when the implementation detects that base plus the size estimate extends beyond physically addressable memory.

OffsetOutOfBoundsException when the address is invalid.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryTypeFilter³⁵ has been registered with the PhysicalMemoryManager³⁶.

MemoryTypeConflictException when the specified base does not point to memory that matches the requested type, or when type specifies incompatible memory attributes.

MemoryInUseException when the specified memory is already in use.

IllegalArgumentException when size is null, or size.getEstimate() is negative.

LTPhysicalMemory(Object, long, Runnable)

Create an instance of LTPhysicalMemory with the given parameters. See Section PhysicalMemoryManager

Signature

```
public
```

LTPhysicalMemory(Object type, long size, Runnable logic)

Parameters

type An instance of Object representing the type of memory required (e.g., dma, shared) - used to define the base address and control the mapping. When the required memory has more than one attribute, type may be an array of objects. When type is null or a reference to an array with no entries, any type of memory is acceptable. Note that type values are compared by reference (==), not by value (equals).

size The size of the area in bytes.

logic The run() method of this object will be called whenever MemoryArea.enter()³⁷ is called. When logic is null, logic must be supplied when the memory area is entered.

³⁵Section 15.3.1.1

³⁶Section 15.3.3.5

 $^{^{37}}$ Section 11.4.2.3.2

Throws

SecurityException when the application doesn't have permissions to access physical memory or the given type of memory.

IllegalArgumentException when size is less than zero.

SizeOutOfBoundsException when the implementation detects that size extends beyond physically addressable memory.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryTypeFilter³⁸ has been registered with the PhysicalMemoryManager³⁹.

MemoryTypeConflictException when the specified base does not point to memory that matches the requested type, or when type specifies incompatible memory attributes.

IllegalAssignmentError when storing logic in this would violate the assignment rules.

LTPhysicalMemory(Object, long, long, Runnable)

Create an instance of LTPhysicalMemory with the given parameters. See Section PhysicalMemoryManager

Signature

```
public
```

LTPhysicalMemory(Object type, long base, long size, Runnable logic)

Parameters

type An instance of Object representing the type of memory required (e.g., dma, shared) - used to define the base address and control the mapping. When the required memory has more than one attribute, type may be an array of objects. When type is null or a reference to an array with no entries, any type of memory is acceptable. Note that type values are compared by reference (==), not by value (equals).

base The physical memory address of the area.

size The size of the area in bytes.

 $^{^{38}}$ Section 15.3.1.1

 $^{^{39}}$ Section 15.3.3.5

logic The run() method of this object will be called whenever MemoryArea.enter()⁴⁰ is called. When logic is null, logic must be supplied when the memory area is entered.

Throws

SizeOutOfBoundsException when the implementation detects that base plus size extends beyond physically addressable memory.

LTPhysicalMemory

SecurityException when the application doesn't have permissions to access physical memory or the given type of memory.

IllegalArgumentException when size is less than zero.

OffsetOutOfBoundsException when the address is invalid.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryTypeFilter⁴¹ has been registered with the PhysicalMemoryManager⁴².

Memory Type Conflict Exception when the specified base does not point to memory that matches the requested type, or when type specifies incompatible memory attributes.

MemoryInUseException when the specified memory is already in use.

IllegalAssignmentError when storing logic in this would violate the assignment rules.

LTPhysicalMemory(Object, SizeEstimator, Runnable)

Create an instance of LTPhysicalMemory with the given parameters. See Section PhysicalMemoryManager

Signature

public

LTPhysicalMemory(Object type, SizeEstimator size, Runnable logic)

Parameters

type An instance of Object representing the type of memory required (e.g., dma, shared) - used to define the base address and control the mapping. When the required memory has more than one attribute, type may be an array of objects. When type is null or a reference to an array with no entries, any type

⁴⁰Section 11.4.2.3.2

 $^{^{41}}$ Section 15.3.1.1

 $^{^{42}}$ Section 15.3.3.5

of memory is acceptable. Note that type values are compared by reference (==), not by value (equals).

size A size estimator for this area.

logic The run() method of this object will be called whenever MemoryArea.enter()⁴³ is called. When logic is null, logic must be supplied when the memory area is entered.

Throws

SecurityException when the application doesn't have permissions to access physical memory or the given type of memory.

SizeOutOfBoundsException when the implementation detects that base plus the size estimate extends beyond physically addressable memory.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryTypeFilter⁴⁴ has been registered with the PhysicalMemoryManager⁴⁵.

Memory Type Conflict Exception when the specified base does not point to memory that matches the request type, or when type specifies attributes with a conflict.

IllegalArgumentException when size is null, or size.getEstimate() is negative.

IllegalAssignmentError when storing logic in this would violate the assignment rules.

LTPhysicalMemory(Object, long, SizeEstimator, Runnable)

Create an instance of LTPhysicalMemory with the given parameters. See Section PhysicalMemoryManager

Signature

public

LTPhysicalMemory(Object type, long base, SizeEstimator size, Runnable logic)

Parameters 1

⁴³Section 11.4.2.3.2

⁴⁴Section 15.3.1.1

 $^{^{45}}$ Section 15.3.3.5

type An instance of Object representing the type of memory required (e.g., dma, shared) - used to define the base address and control the mapping. When the required memory has more than one attribute, type may be an array of objects. When type is null or a reference to an array with no entries, any type of memory is acceptable. Note that type values are compared by reference (==), not by value (equals).

base The physical memory address of the area.

size A size estimator for this memory area.

logic The run() method of this object will be called whenever MemoryArea.enter()⁴⁶ is called. When logic is null, logic must be supplied when the memory area is entered.

Throws

SecurityException when the application doesn't have permissions to access physical memory or the given type of memory.

SizeOutOfBoundsException when the implementation detects that base plus the size estimate extends beyond physically addressable memory.

OffsetOutOfBoundsException when the address is invalid.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryTypeFilter⁴⁷ has been registered with the PhysicalMemoryManager⁴⁸.

MemoryTypeConflictException when the specified base does not point to memory that matches the requested type, or when type specifies incompatible memory attributes.

MemoryInUseException when the specified memory is already in use.

IllegalArgumentException when size is null, or size.getEstimate() is negative.

IllegalAssignmentError when storing logic in this would violate the assignment rules.

15.3.3.2.2 Methods

toString

Creates a string describing this object. The string is of the form (LTPhysicalMemory) Scoped memory # num

⁴⁶Section 11.4.2.3.2

⁴⁷Section 15.3.1.1

⁴⁸Section 15.3.3.5

where num is a number that uniquely identifies this LTPhysicalMemory memory area. representing the value of this.

```
public
    java.lang.String toString()
Returns
    A string representing the value of this.
```

15.3.3.3 NoHeapRealtimeThread

A NoHeapRealtimeThread is a specialized form of RealtimeThread⁴⁹. Because an instance of NoHeapRealtimeThread may immediately preempt any implemented garbage collector, logic contained in its run() is never allowed to allocate or reference any object allocated in the heap. At the byte-code level, it is illegal for a reference to an object allocated in heap to appear on a no-heap realtime thread's operand stack.

Thus, it is always safe for a NoHeapRealtimeThread to interrupt the garbage collector at any time, without waiting for the end of the garbage collection cycle or a defined preemption point. Due to these restrictions, a NoHeapRealtimeThread object must be placed in a memory area such that thread logic may unexceptionally access instance variables and such that Java methods on Thread (e.g., enumerate and join) complete normally except where execution would cause access violations. The constructors of NoHeapRealtimeThread require a reference to ScopedMemory⁵⁰ or ImmortalMemory⁵¹.

When the thread is started, all execution occurs in the scope of the given memory area. Thus, all memory allocation performed with the new operator is taken from this given area.

Deprecated since RTSJ version since RTSJ 2.0

Inheritance

```
java.lang.Object
java.lang.Thread
javax.realtime.RealtimeThread
javax.realtime.NoHeapRealtimeThread
```

⁴⁹Section 5.3.2.2

 $^{^{50}}$ Section 11.4.2.5

 $^{^{51}}$ Section 11.4.2.2

15.3.3.3.1 Constructors

NoHeapRealtimeThread(SchedulingParameters, ReleaseParameters, MemoryParameters, MemoryArea, ProcessingGroup-Parameters, Runnable)

Create a realtime thread with the given characteristics and a Runnable. The thread group of the new thread is (effectively) null. The newly-created no-heap real-time thread is associated with the scheduler in effect during execution of the constructor.

Signature

public

NoHeapRealtimeThread(SchedulingParameters scheduling, ReleaseParameters relea

scheduling the SchedulingParameters associated with this (and possibly other instances of Schedulable). When scheduling is null, the default is a copy of the creator's scheduling parameters created in the same memory area as the new NoHeapRealtimeThread.

release the ReleaseParameters associated with this (and possibly other instances of Schedulable). When release is null the it defaults to the a copy of the creator's release parameters created in the same memory area as the new NoHeapRealtimeThread.

memory the MemoryParameters associated with this (and possibly other instances of Schedulable). When memory is null, the new NoHeapRealtime-Thread will have a null value for its memory parameters, and the amount or rate of memory allocation is unrestricted.

area the MemoryArea associated with this. When area is null, an IllegalArgumentException is thrown.

group the ProcessingGroupParameters associated with this (and possibly other instances of Schedulable). When null, the new NoHeapRealtimeThread will not be associated with any processing group.

logic the Runnable object whose run() method will serve as the logic for the new NoHeapRealtimeThread. When logic is null, the run() method in the new object will serve as its logic.

Throws

IllegalArgumentException when the parameters are not compatible with the associated scheduler, when area is null, when area is heap memory, when area, scheduling release, memory or group is allocated in heap memory. when this is in heap memory, or when logic is in heap memory.

Illegal Assignment Error when the new NoHeap Real time Thread instance cannot hold references to non-null values of the scheduling release, memory and group, or when those parameters cannot hold a reference to the new NoHeap Real time Thread.

NoHeapRealtimeThread(SchedulingParameters, ReleaseParameters, MemoryArea)

Create a no-heap realtime thread with the given SchedulingParameters⁵², Re-leaseParameters⁵³ and MemoryArea⁵⁴, and default values for all other parameters. This constructor is equivalent to NoHeapRealtimeThread(scheduling, release, null, area, null, null).

Signature

public

 ${\tt NoHeap Real time Thread (Scheduling Parameters scheduling, Release Parameters release, NoHeap Real time Thread (Scheduling Parameters scheduling, Release Parameters release, NoHeap Real time Thread (Scheduling Parameters scheduling, Release Parameters release, NoHeap Real time Thread (Scheduling Parameters scheduling, Release Parameters release, NoHeap Real time Thread (Scheduling Parameters scheduling) and the scheduling Parameters scheduling (Scheduling Parameters) and the scheduling Parameters scheduling (Scheduling Parameters) and the scheduling (Scheduling Parameters)$

${\bf No Heap Real time Thread (Scheduling Parameters, Memory Area)}$

Create a realtime thread with the given SchedulingParameters⁵⁵ and Memory-Area⁵⁶ and default values for all other parameters.

This constructor is equivalent to NoHeapRealtimeThread(scheduling, null, null, area, null, null).

Signature

⁵²Section 6.4.2.13

 $^{^{53}}$ Section 6.4.2.9

⁵⁴Section 11.4.2.3

⁵⁵Section 6.4.2.13

 $^{^{56}}$ Section 11.4.2.3

```
public
```

NoHeapRealtimeThread(SchedulingParameters scheduling, MemoryArea area)

15.3.3.3.2 Methods

start

See Section RealtimeThread.start()

```
Signature

public

void start()
```

startPeriodic(PhasingPolicy)

See Section RealtimeThread.startPeriodic(PhasingPolicy)

Available since RTSJ 2.0

```
Signature
    public
    void startPeriodic(PhasingPolicy phasingPolicy)
    throws LateStartException
```

15.3.3.4 POSIXSignalHandler

This class enables the use of an AsyncEventHandler to react on the occurrence of POSIX signals.

On systems that support POSIX signals fully, the 13 signals required by POSIX will be supported. Any further signals defined in this class may be supported by the system. On systems that do not support POSIX signals, even the 13 standard signals may never be fired.

Deprecated since RTSJ version since RTSJ 2.0

Inheritance

java.lang.Object javax.realtime.POSIXSignalHandler

15.3.3.4.1 Fields

SIGHUP

public static final SIGHUP Hangup (POSIX).

SIGINT

public static final SIGINT
interrupt (ANSI)

SIGQUIT

 $\begin{array}{c} \text{public static final SIGQUIT} \\ \text{quit } (\text{POSIX}) \end{array}$

SIGILL

public static final SIGILL illegal instruction (ANSI)

SIGTRAP

public static final SIGTRAP trace trap (POSIX), optional signal.

SIGABRT

public static final SIGABRT Abort (ANSI).

SIGBUS

public static final SIGBUS BUS error (4.2 BSD), optional signal.

SIGFPE

public static final SIGFPE floating point exception

SIGKILL

public static final SIGKILL Kill, unblockable (POSIX).

SIGUSR1

public static final SIGUSR1 User-defined signal 1 (POSIX).

SIGSEGV

public static final SIGSEGV Segmentation violation (ANSI).

SIGUSR2

public static final SIGUSR2 User-defined signal 2 (POSIX).

SIGPIPE

public static final SIGPIPE Broken pipe (POSIX).

SIGALRM

public static final SIGALRM Alarm clock (POSIX).

SIGTERM

public static final SIGTERM Termination (ANSI).

SIGCHLD

public static final SIGCHLD Child status has changed (POSIX).

SIGCONT

public static final SIGCONT Continue (POSIX), optional signal.

SIGSTOP

public static final SIGSTOP Stop, unblockable (POSIX), optional signal.

SIGTSTP

public static final SIGTSTP Keyboard stop (POSIX), optional signal.

SIGTTIN

public static final SIGTTIN
Background read from tty (POSIX), optional signal.

SIGTTOU

public static final SIGTTOU Background write to tty (POSIX), optional signal.

SIGURG

public static final SIGURG Urgent condition on socket (4.2 BSD).

Deprecated since RTSJ version as of RTSJ 1.0.1 not part of POSIX 9945-1-1996 standard

SIGXCPU

public static final SIGXCPU CPU limit exceeded (4.2 BSD).

Deprecated since RTSJ version as of RTSJ 1.0.1 not part of POSIX 9945-1-1996 standard

SIGXFSZ

public static final SIGXFSZ File size limit exceeded (4.2 BSD).

Deprecated since RTSJ version as of RTSJ 1.0.1 not part of POSIX 9945-1-1996 standard

SIGVTALRM

public static final SIGVTALRM Virtual alarm clock (4.2 BSD).

Deprecated since RTSJ version as of RTSJ 1.0.1 not part of POSIX 9945-1-1996 standard

SIGPROF

public static final SIGPROF Profiling alarm clock (4.2 BSD).

Deprecated since RTSJ version as of RTSJ 1.0.1 not part of POSIX 9945-1-1996 standard

SIGWINCH

```
public static final SIGWINCH Window size change (4.3 BSD, Sun).
```

Deprecated since RTSJ version as of RTSJ 1.0.1 not part of POSIX 9945-1-1996 standard

SIGIO

```
public static final SIGIO I/O now possible (4.2 BSD).
```

Deprecated since RTSJ version as of RTSJ 1.0.1 not part of POSIX 9945-1-1996 standard

SIGPWR

```
public static final SIGPWR Power failure restart (System V).
```

Deprecated since RTSJ version as of RTSJ 1.0.1 not part of POSIX 9945-1-1996 standard

SIGSYS

```
public static final SIGSYS Bad system call, optional signal.
```

SIGIOT

```
public static final SIGIOT IOT instruction (4.2 BSD), optional signal.
```

SIGPOLL

```
public static final SIGPOLL
```

Pollable event occurred (System V).

Deprecated since RTSJ version as of RTSJ 1.0.1 not part of POSIX 9945-1-1996 standard

SIGCLD

public static final SIGCLD Same as SIGCHLD (System V), optional signal.

SIGEMT

public static final SIGEMT EMT instruction, optional signal.

SIGLOST

public static final SIGLOST

Deprecated since RTSJ version as of RTSJ 1.0.1 not part of POSIX 9945-1-1996 standard

SIGCANCEL

public static final SIGCANCEL

Deprecated since RTSJ version as of RTSJ 1.0.1 not part of POSIX 9945-1-1996 standard

SIGFREEZE

public static final SIGFREEZE

Deprecated since RTSJ version as of RTSJ 1.0.1 not part of POSIX 9945-1-1996 standard

SIGLWP

public static final SIGLWP

Deprecated since RTSJ version as of RTSJ 1.0.1 not part of POSIX 9945-1-1996 standard

SIGTHAW

public static final SIGTHAW

Deprecated since RTSJ version as of RTSJ 1.0.1 not part of POSIX 9945-1-1996 standard

SIGWAITING

public static final SIGWAITING

Deprecated since RTSJ version as of RTSJ 1.0.1 not part of POSIX 9945-1-1996 standard

15.3.3.4.2 Constructors

${\bf POSIXSignal Handler}$

Signature

public POSIXSignalHandler()

15.3.3.4.3 Methods

addHandler(int, AsyncEventHandler)

addHandler adds the handler provided to the set of handlers that will be released on the provided signal.

Signature

```
public static
void addHandler(int signal, AsyncEventHandler handler)
```

Parameters 5 4 1

signal The POSIX signal as defined in the constants SIG*.

handler the handler to be released on the given signal.

Throws

IllegalArgumentException iff signal is not defined by any of the constants in this class or handler is null.

removeHandler(int, AsyncEventHandler)

removeHandler removes a handler that was added for a given signal.

Signature

```
public static
void removeHandler(int signal, AsyncEventHandler handler)
```

signal The POSIX signal as defined in the constants SIG*.

handler the handler to be removed from the given signal. When this handler is null or has not been added to the signal, nothing will happen.

Throws

IllegalArgumentException iff signal is not defined by any of the constants in this class.

setHandler(int, AsyncEventHandler)

setHandler sets the set of handlers that will be released on the provided signal to the set with the provided handler being the single element.

Signature

public static

void setHandler(int signal, AsyncEventHandler handler)

Parameters

signal The POSIX signal as defined in the constants SIG*.

handler the handler to be released on the given signal, null to remove all handlers for the given signal.

Throws

IllegalArgumentException iff signal is not defined by any of the constants in this class.

15.3.3.5 PhysicalMemoryManager

The PhysicalMemoryManager is not ordinarily used by applications, except that the implementation may require the application to use the registerFilter⁵⁷ method to make the physical memory manager aware of the memory types on their platform. The PhysicalMemoryManager class is primarily intended for use by the various physical memory accessor objects (VTPhysicalMemory⁵⁸, LTPhysicalMemory⁵⁹, and ImmortalPhysicalMemory⁶⁰) to create objects of the types requested by the application. The physical memory manager is responsible for finding areas of physical memory with the appropriate characteristics and access rights, and moderating any required combination of physical and virtual memory characteristics.

The Physical Memory Manager assumes that the physical addresss space is linear but not necessarily contiguous. That is, addresses range from 0 .. MAX_LONG but there may be holes in the memory space. Some of these holes may be filled with removable memory.

The physical memory is partitioned into chunks (pages, segments, etc.). Each chunk of memory has a base address and a length.

Each chunk of memory has certain properties. Some of these properties may require actions to be performed by the Physical Memory Manager when the memory is accessed. For example, access to IO_PAGE may require the use of special instructions to even reach the devices, or it may require special code sequences to ensure proper handling of processor write queues and caches.

Filters tell the Physical Memory Manager about the properties of the memory that are available on the machine by registering with the Physical Memory Manager.

 $^{^{57}}$ Section 15.3.3.5.2

⁵⁸Section 15.3.3.11

⁵⁹Section 15.3.3.2

 $^{^{60}}$ Section 15.3.3.1

When the program requests a physical memory area with particular properties, the constructor communicates with the Physical Memory Manager through a private interface. The Physical Memory Manager asks the filter if the the address specified has the required properties and whether it is free, or asks for a chunk of memory with the requested size.

The Physical Memory Manager then maps the physical memory chunk into virtual memory (on systems that support virtual memory). and locks the virtual memory to the memory chunk.

Examples of characteristics that might be specified are: DMA memory, hardware byte swapping, non-cached access to memory, etc. Standard "names" for some memory characteristics are included in this class — DMA, SHARED, ALIGNED, BYTESWAP, and IO_PAGE — support for these characteristics is optional, but when they are supported they must use these names. Additional characteristics may be supported, but only names defined in this specification may be visible in the PhysicalMemoryManager API.

The base implementation will provide a Physical Memory Manager.

Original Equipment Manufacturers or other interested parties may provide PhysicalMemoryTypeFilter⁶¹ classes that allow additional characteristics of memory devices to be specified.

Deprecated since RTSJ version as of RTSJ 2.0

Inheritance

```
java.lang.Object
javax.realtime.PhysicalMemoryManager
```

15.3.3.5.1 Fields

ALIGNED

public static final ALIGNED

When aligned memory is supported by the implementation specify ALIGNED to identify aligned memory. This type of memory ignores low-order bits in load and store accesses to force accesses to fall on natural boundaries for the access type even when the processor uses a poorly aligned address.

Deprecated since RTSJ version as of RTSJ 2.0 This is only applicable to raw memory. Use RawMemory⁶².

```
<sup>61</sup>Section 15.3.1.1
<sup>62</sup>Section 12.4.1.16
```

BYTESWAP

public static final BYTESWAP

When automatic byte swapping is supported by the implementation specify BYTESWAP when byte swapping should be used. Byte-swapping memory re-orders the bytes in accesses for 16 bits or more such that little-endian data in memory is accessed as big-endian, and vice-versa. Such memory would typically be available in swapped mode in one physical address range and in un-swapped mode in another address range.

Deprecated since RTSJ version as of RTSJ 2.0 This is only applicable to raw memory. Use RawMemory⁶³.

DMA

public static final DMA

When DMA (Direct Memory Access) memory is supported by the implementation, specify DMA to identify DMA memory. This memory is visible to devices that use DMA. In some systems, only a portion of the physical address space is available to DMA devices. On such systems, memory that will be used for DMA must be allocated from the range of addresses that DMA can reach.

Deprecated since RTSJ version as of RTSJ 2.0 This is only applicable to raw memory. Use RawMemory⁶⁴.

IO_PAGE

public static final IO_PAGE

When access to the system I/O space is supported by the implementation specify IO_PAGE when I/O space should be used. Addresses tagged with the name IO_PAGE are used for memory mapped I/O devices. Such addresses are almost certainly not suitable for physical memory, but only for raw memory access.

Available since RTSJ 1.0.1

⁶³Section 12.4.1.16

 $^{^{64}}$ Section 12.4.1.16

SHARED

public static final SHARED

When shared memory is supported by the implementation specify SHARED to identify shared memory. In a NUMA (Non-Uniform Memory Access) architecture, processors may make some part of their local memory available to other processors. This memory would be tagged with SHARED, as would memory that is shared and non-local.

A fully built-out NUMA system might well need sub-classifications of SHARED to reflect different paths to memory. Note that, as with other physical memory names, a single byte of memory may be visible at several physical addresses with different access properties at each address. For instance, a byte of shared memory accesses at address x might be shared with high-performance access, but without the support of coherent caches. The same byte accessed at address y might be shared with coherent cache support, but substantially longer access times.

15.3.3.5.2 Methods

isRemovable(long, long)

Queries the system about the removability of the specified range of memory.

Signature

```
public static
boolean isRemovable(long base, long size)
```

Parameters 4 6 1

base The starting address in physical memory.

size The size of the memory area.

Throws

IllegalArgumentException when size is less than zero.

SizeOutOfBoundsException when base plus size would be greater than the physical addressing range of the processor.

OffsetOutOfBoundsException when base is less than zero.

Returns

true when any part of the specified range can be removed.

isRemoved(long, long)

Queries the system about the removed state of the specified range of memory. This method is used for devices that lie in the memory address space and can be removed while the system is running. (Such as PC cards).

```
public static
boolean isRemoved(long base, long size)

Parameters
base The starting address in physical memory.
size The size of the memory area.

Throws
IllegalArgumentException when size is less than zero.
OffsetOutOfBoundsException when base is less than zero.
SizeOutOfBoundsException when base plus size would be greater than the physical addressing range of the processor.
```

Returns

true when any part of the specified range is currently not usable.

onInsertion(long, long, AsyncEvent)

Register the specified AsyncEvent⁶⁵ to fire when any memory in the range is added to the system. When the specified range of physical memory contains multiple different types of removable memory, the AE will be registered with each of them.

Available since RTSJ 1.0.1

```
Signature

public static
void onInsertion(long base, long size, AsyncEvent ae)

Parameters

base The starting address in physical memory.
size The size of the memory area.
ae The async event to fire.

Throws

65 Section 8.4.3.4
```

IllegalArgumentException when ae is null, or when the specified range contains no removable memory, or when size is less than zero.

OffsetOutOfBoundsException when base is less than zero.

SizeOutOfBoundsException when base plus size would be greater than the physical addressing range of the processor.

onInsertion(long, long, AsyncEventHandler)

Register the specified AsyncEventHandler⁶⁶ to run when any memory in the range is added to the system. When the specified range of physical memory contains multiple different types of removable memory, the AEH will be registered with each of them. When the size or the base is less than 0, unregister all "onInsertion" references to the handler.

Note: This method only removes handlers that were registered with the same method. It has no effect on handlers that were registered using an associated async event.

Signature

public static

void onInsertion(long base, long size, AsyncEventHandler aeh)

Parameters 5

base The starting address in physical memory.

size The size of the memory area.

aeh The handler to register.

Throws

IllegalArgumentException when aeh is null, or when the specified range contains no removable memory, or when aeh is null and size and base are both greater than or equal to zero.

SizeOutOfBoundsException when base plus size would be greater than the physical addressing range of the processor.

onRemoval(long, long, AsyncEvent)

Register the specified AE to fire when any memory in the range is removed from the system. When the specified range of physical memory contains multiple different types of removable memory, the AE will be registered with each of them.

 $^{^{66}}$ Section 8.4.3.5

Signature

public static
void onRemoval(long base, long size, AsyncEvent ae)

Parameters 1

base The starting address in physical memory.

size The size of the memory area.

ae The async event to register.

Throws

IllegalArgumentException when the specified range contains no removable memory, when ae is null, or when size is less than zero.

OffsetOutOfBoundsException when base is less than zero.

SizeOutOfBoundsException when base plus size would be greater than the physical addressing range of the processor.

onRemoval(long, long, AsyncEventHandler)

Register the specified AEH to run when any memory in the range is removed from the system. When the specified range of physical memory contains multiple different types of removable memory, the AEH will be registered with each of them. When size or base is less than 0, unregister all "onRemoval" references to the handler parameter.

Note: This method only removes handlers that were registered with the same method. It has no effect on handlers that were registered using an associated async event.

Signature

public static
void onRemoval(long base, long size, AsyncEventHandler aeh)

Parameters 5 4 1

base The starting address in physical memory.

size The size of the memory area.

aeh The handler to register.

Throws

IllegalArgumentException when the specified range contains no removable memory, or when aeh is null and size and base are both greater than or equal to zero.

SizeOutOfBoundsException when base plus size would be greater than the physical addressing range of the processor.

registerFilter(Object, PhysicalMemoryTypeFilter)

Register a memory type filter with the physical memory manager.

Values of name are compared using reference equality (==) not value equality (equals()).

Signature

```
public static final
void registerFilter(Object name, PhysicalMemoryTypeFilter
filter)
```

throws DuplicateFilterException

Parameters

name The type of memory handled by this filter. filter The filter object.

Throws

DuplicateFilterException when a filter for this type of memory already exists. ResourceLimitError when the system is configured for a bounded number of filters. This filter exceeds the bound.

IllegalArgumentException when the name parameter is an array of objects, when the name and filter are not both in immortal memory, or when either name or filter is null.

SecurityException when this operation is not permitted.

removeFilter(Object)

Remove the identified filter from the set of registered filters. When the filter is not registered, silently do nothing.

Values of name are compared using reference equality (==) not value equality (equals()).

Signature

```
public static final
void removeFilter(Object name)
```

Parameters

name The identifying object for this memory attribute.

Throws

IllegalArgumentException when name is null.

SecurityException when this operation is not permitted.

unregisterInsertionEvent(long, long, AsyncEvent)

Unregister the specified insertion event. The event is only unregistered when all three arguments match the arguments used to register the event, except that ae of null matches all values of ae and will unregister every ae that matches the address range.

Note: This method has no effect on handlers registered directly as async event handlers.

Available since RTSJ 1.0.1

Signature

public static
boolean unregisterInsertionEvent(long base, long size,
AsyncEvent ae)

Parameters

base The starting address in physical memory associated with ae. size The size of the memory area associated with ae. ae The event to unregister.

Throws

IllegalArgumentException when size is less than 0.

OffsetOutOfBoundsException when base is less than zero.

SizeOutOfBoundsException when base plus size would be greater than the physical addressing range of the processor.

Returns

True when at least one event matched the pattern, false when no such event was found.

unregisterRemovalEvent(long, long, AsyncEvent)

Unregister the specified removal event. The async event is only unregistered when all three arguments match the arguments used to register the event, except that ae of null matches all values of ae and will unregister every ae that matches the address range.

Note: This method has no effect on handlers registered directly as async event handlers.

Available since RTSJ 1.0.1

Signature

public static
boolean unregisterRemovalEvent(long base, long size, AsyncEvent
ae)

Parameters

base The starting address in physical memory associated with ae.

size The size of the memory area associated with ae.

ae The async event to unregister.

Throws

IllegalArgumentException when size is less than 0.

OffsetOutOfBoundsException when base is less than zero.

SizeOutOfBoundsException when base plus size would be greater than the physical addressing range of the processor.

Returns

True when at least one event matched the pattern, false when no such event was found.

15.3.3.6 ProcessingGroupParameters

This is associated with one or more schedulables for which the system guarantees that the associated objects will not be given more time per period than indicated by cost. The motivation for this class is to allow the execution demands of one or more aperiodic schedulables to be bound. However, periodic or sporadic schedulables can also be associated with a processing group.

Processing groups have an associated affinity set that must contain only a single processor. The default affinity set is given by Affinity.getGroupDefaultAffinity().

For all schedulables with a reference to an instance of ProcessingGroupParameters p no more than p.cost will be allocated to the execution of these schedulables on the processor associated with its processing group in each interval of time given by p.period after the time indicated by p.start. No execution of the schedulables will be allowed on any processor other than this processor. When there is no intersection between the a schedulable objects affinity set and its processing group's affinity set, then the schedulable execution is constrained by the default processing group's affinit set.

Logically a virtual server is associated with each instance of ProcessingGroup-Parameters. This server has a start time, a period, a cost (budget) and a deadline. The server can only logically execute when (a) it has not consumed more execution

time in its current release than the cost (budget) parameter, (b) one of its associated schedulables is executable and is the most eligible of the executable schedulables. When the server is logically executable, the associated schedulable is executed. When the cost has been consumed, any overrunHandler is released, and the server is not eligible for logical execution until its next period is due. At this point, its allocated cost (budget) is replenished. When the server is logically executing when its deadline expires, any associated missHandler is released. The deadline and cost parameters of all the associated schedulable objects have the same impact as they would if the objects were not bound to a processing group.

Processing group parameters use HighResolutionTime⁶⁷ values for cost, deadline, period and start time. Since those times are expressed as a HighResolution-Time⁶⁸, the values use accurate timers with nanosecond granularity. The actual resolution available and even the quantity it measures depends on the clock associated with each time value.

When a reference to a ProcessingGroupParameters object is given as a parameter to a schedulable's constructor or passed as an argument to one of the schedulable's setter methods, the ProcessingGroupParameters object becomes the processing group parameters object bound to that schedulable object. Changes to the values in the ProcessingGroupParameters object affect that schedulable object. When bound to more than one schedulable then changes to the values in the ProcessingGroupParameters object affect all of the associated objects. Note that this is a one-to-many relationship and not a many-to-many.

The implementation must use modified copy semantics for each HighResolutionTime⁶⁹ parameter value. The value of each time object should be treated as if it were copied at the time it is passed to the parameter object, but the object reference must also be retained. Only changes to a ProcessingGroupParameters object caused by methods on that object are immediately visible to the scheduler. For instance, invoking setPeriod() on a ProcessingGroupParameters object will make the change, then notify that the scheduler that the parameter object has changed. At that point the scheduler's view of the processing group parameters object is updated. Invoking a method on the RelativeTime object that is the period for this object may change the period but it does not pass the change to the scheduler at that time. That new value for period must not change the behavior of the SOs that use the parameter object until a setter method on the ProcessingGroupParameters object is invoked, or the parameter object is used in setProcessingGroupParameters() or a constructor for an SO.

The implementation may use copy semantics for each HighResolutionTime pa-

 $^{^{67}}$ Section 9.4.1.2

 $^{^{68}}$ Section 9.4.1.2

 $^{^{69}} Section~9.4.1.2$

rameter value. For instance the value returned by getCost() must be equal to the value passed in by setCost, but it need not be the same object.

The following table gives the default parameter values for the constructors.

Attribute	Default Value
start	new Relative $Time(0,0)$
period	No default. A value must be sup-
	plied
cost	No default. A value must be sup-
	plied
deadline	new RelativeTime(period)
overrunHandler	None
missHandler	None

Caution: This class is explicitly unsafe in multithreaded situations when it is being changed. No synchronization is done. It is assumed that users of this class who are mutating instances will be doing their own synchronization at a higher level.

Caution: The cost parameter time should be considered to be measured against the target platform.

Deprecated since RTSJ version as of RTSJ 2.0

Inheritance

```
java.lang.Object
    javax.realtime.ProcessingGroupParameters
Interfaces
Cloneable
Serializable
```

15.3.3.6.1 Constructors

ProcessingGroupParameters(javax.realtime.HighResolutionTime<?>, RelativeTime, RelativeTime, RelativeTime, AsyncEventHandler, AsyncEventHandler)

Create a ProcessingGroupParameters object.

Signature

public

ProcessingGroupParameters(javax.realtime.HighResolutionTime<?> start, RelativeTime

throws IllegalArgumentException, IllegalAssignmentError

Parameters

start Time at which the first period begins. When a RelativeTime, this time is relative to the creation of this. When an AbsoluteTime, then the first release of the logical server is at the start time (or immediately when the absolute time is in the past). When null, the default value is a new instance of RelativeTime(0,0).

period The period is the interval between successive replenishment of the logical server's associated cost budget. There is no default value. When period is null an exception is thrown.

cost Processing time per period. The budget CPU time that the logical server can consume each period. When null, an exception is thrown.

deadline The latest permissible completion time measured from the start of the current period. Changing the deadline might not take effect after the expiration of the current deadline. Specifying a deadline less than the period constrains execution of all the members of the group to the beginning of each period. When null, the default value is new instance of Relative-Time(period).

overrunHandler This handler is invoked when any schedulable object member of this processing group attempts to use processor time beyond the group's budget. When null, no application async event handler is fired on the overrun condition.

missHandler This handler is invoked when the logical server is still executing after the deadline has passed. When null, no application async event handler is fired on the deadline miss condition.

Throws

IllegalArgumentException when the period is null or its time value is not greater than zero, when cost is null, or when the time value of cost is less than zero, when start is an instance of RelativeTime and its value is negative, or when the time value of deadline is not greater than zero and less than or equal to the period. When the implementation does not support processing group deadline less than period, deadline less than period will cause IllegalArgumentException to be thrown.

IllegalAssignmentError when start, period, cost, deadline, overrunHandler or missHandler cannot be stored in this.

15.3.3.6.2 Methods

clone

Signature

Returns

Create a clone of this. This method should behave effectively as when it constructed a new object with clones of the high-resolution time values of this.

- The new object is in the current allocation context.
- clone does not copy any associations from this and it does not implicitly bind the new object to a SO.
- The new object has clones of all high-resolution time values (deep copy).
- References to event handlers are copied (shallow copy.)

Available since RTSJ 1.0.1

```
java.lang.Object clone()
throws CloneNotSupportedException
Throws
CloneNotSupportedException never
Returns
the clone of this

getCost

Gets the value of cost.

Signature
public
javax.realtime.RelativeTime getCost()
```

getCostOverrunHandler

Gets the cost overrun handler.

a reference to the value of cost.

```
Signature
    public
    javax.realtime.AsyncEventHandler getCostOverrunHandler()
Returns
```

A reference to an instance of $AsyncEventHandler^{70}$ that is cost overrun handler of this.

getDeadline

Gets the value of deadline.

```
Signature
    public
    javax.realtime.RelativeTime getDeadline()
Returns
```

A reference to an instance of RelativeTime⁷¹ that is the deadline of this.

${\bf get Dead line Miss Handler}$

Gets the deadline miss handler.

```
Signature

public

javax.realtime.AsyncEventHandler getDeadlineMissHandler()

Returns
```

A reference to an instance of AsyncEventHandler⁷²that is deadline miss handler of this.

getPeriod

Gets the value of period.

⁷⁰Section 8.4.3.5

 $^{^{71}}$ Section 9.4.1.3

 $^{^{72}}$ Section 8.4.3.5

```
Signature
```

```
public
javax.realtime.RelativeTime getPeriod()
```

Returns

A reference to an instance of RelativeTime⁷³ that represents the value of period.

getStart

Gets the value of start. This is the value that was specified in the constructor or by setStart(), not the actual absolute time the corresponding to the start of the processing group.

Signature

```
public
javax.realtime.HighResolutionTime<?> getStart()
```

Returns

A reference to an instance of HighResolutionTime⁷⁴ that represents the value of start.

setCost(RelativeTime)

Sets the value of cost.

Signature

```
public
void setCost(RelativeTime cost)
throws IllegalArgumentException, IllegalAssignmentError
```

Parameters

cost The new value for cost. When null, an exception is thrown.

Throws

IllegalArgumentException when cost is null or its time value is less than zero. IllegalAssignmentError when cost cannot be stored in this.

 $^{^{73}}$ Section 9.4.1.3

⁷⁴Section 9.4.1.2

setCostOverrunHandler(AsyncEventHandler)

Sets the cost overrun handler.

Signature

public

void setCostOverrunHandler(AsyncEventHandler handler)

throws IllegalAssignmentError

Parameters

handler This handler is invoked when the run() method of and of the the schedulables attempt to execute for more than cost time units in any period. When null, no handler is attached, and any previous handler is removed.

Throws

IllegalAssignmentError when handler cannot be stored in this.

setDeadline(RelativeTime)

Sets the value of deadline.

Signature

public

void setDeadline(RelativeTime deadline)

throws IllegalArgumentException, IllegalAssignmentError

Parameters

deadline The new value for deadline. When null, the default value is new instance of RelativeTime(period).

Throws

IllegalArgumentException when deadline has a value less than zero or greater than the period. Unless the implementation supports deadline less than period in processing groups, IllegalArgumentException is also when deadline is less than the period.

IllegalAssignmentError when deadline cannot be stored in this.

set Deadline Miss Handler (Async Event Handler)

Sets the deadline miss handler.

Signature

```
public
void setDeadlineMissHandler(AsyncEventHandler handler)
throws IllegalAssignmentError
```

Parameters

handler This handler is invoked when the run() method of any of the schedulables still expect to execute after the deadline has passed. When null, no handler is attached, and any previous handler is removed.

Throws

IllegalAssignmentError when handler cannot be stored in this.

setPeriod(RelativeTime)

Sets the value of period.

Signature

```
public
void setPeriod(RelativeTime period)
throws IllegalArgumentException, IllegalAssignmentError
```

Parameters

period The new value for period. There is no default value. When period is null an exception is thrown.

Throws

IllegalArgumentException when period is null, or its time value is not greater than zero. When the implementation does not support processing group deadline less than period, and period is not equal to the current value of the processing group's deadline, the deadline is set to a clone of period created in the same memory area as period.

IllegalAssignmentError when period cannot be stored in this.

setStart(javax.realtime.HighResolutionTime<?>)

Sets the value of start. When the processing group is already started this method alters the value of this object's start time property, but has no other effect.

Signature

```
public
void setStart(javax.realtime.HighResolutionTime<?> start)
```

throws IllegalArgumentException, IllegalAssignmentError

Parameters

start The new value for start. When null, the default value is a new instance of RelativeTime(0,0).

Throws

IllegalAssignmentError when start cannot be stored in this.

IllegalArgumentException when start is a relative time value and less than zero.

15.3.3.7 RationalTime

An object that represents a time interval milliseconds/ 10^3 + nanoseconds/ 10^9 seconds long that is divided into subintervals by some frequency. This is generally used in periodic events, threads, and feasibility analysis to specify periods where there is a basic period that must be adhered to strictly (the interval), but within that interval the periodic events are supposed to happen frequency times, as uniformly spaced as possible, but clock and scheduling jitter is moderately acceptable.

Caution: This class is explicitly unsafe for multithreading when being changed. Code that mutates instances of this class should synchronize at a higher level. Deprecated since RTSJ version as of RTSJ 1.0.1

Inheritance

javax.realtime.HighResolutionTime javax.realtime.RelativeTime javax.realtime.RationalTime

15.3.3.8 RawMemoryAccess

An instance of RawMemoryAccess models a range of physical memory as a fixed sequence of bytes. A complement of accessor methods enable the contents of the physical area to be accessed through offsets from the base, interpreted as byte, short, int, or long data values or as arrays of these types.

Whether an offset addresses the high-order or low-order byte is normally based on the value of the RealtimeSystem.BYTE_ORDER⁷⁵ static byte variable in class Real-

⁷⁵Section 13.3.1.7.1

timeSystem⁷⁶. When the type of memory used for this RawMemoryAccess region implements non-standard byte ordering, accessor methods in this class continue to select bytes starting at offset from the base address and continuing toward greater addresses. The memory type may control the mapping of these bytes into the primitive data type. The memory type could even select bytes that are not contiguous. In each case the documentation for the PhysicalMemoryTypeFilter⁷⁷ must document any mapping other than the "normal" one specified above.

The RawMemoryAccess class allows a realtime program to implement device drivers, memory-mapped I/O, flash memory, battery-backed RAM, and similar low-level software.

A raw memory area cannot contain references to Java objects. Such a capability would be unsafe (since it could be used to defeat Java's type checking) and errorprone (since it is sensitive to the specific representational choices made by the Java compiler).

Many of the constructors and methods in this class throw OffsetOutOfBound-sexception⁷⁸. This exception means that the value given in the offset parameter is either negative or outside the memory area.

Many of the constructors and methods in this class throw SizeOutOfBound-sException⁷⁹. This exception means that the value given in the size parameter is either negative, larger than an allowable range, or would cause an accessor method to access an address outside of the memory area.

Unlike other integral parameters in this chapter, negative values are valid for byte, short, int, and long values that are copied in and out of memory by the set and get methods of this class.

All offset values used in this class are measured in bytes.

Atomic loads and stores on raw memory are defined in terms of physical memory. This memory may be accessible to threads outside the JVM and to non-programmed access (e.g., DMA), consequently atomic access must be supported by hardware. This specification is written with the assumption that all suitable hardware platforms support atomic loads for aligned bytes, shorts, and ints. Atomic access beyond the specified minimum may be supported by the implementation.

Storing values into raw memory is more hardware-dependent than loading values. Many processor architectures do not support atomic stores of variables except for aligned stores of the processor's word size. For instance, storing a byte into memory might require reading a 32-bit quantity into a processor register, updating the register to reflect the new byte value, then re-storing the whole 32-bit quantity.

 $^{^{76}}$ Section 13.3.1.7

⁷⁷Section 15.3.1.1

⁷⁸Section 14.2.2.10

 $^{^{79}}$ Section 14.2.2.14

Changes to other bytes in the 32-bit quantity that take place between the load and the store will be lost.

Some processors have mechanisms that can be used to implement an atomic store of a byte, but those mechanisms are often slow and not universally supported.

This class supports unaligned access to data, but it does not require the implementation to make such access atomic. Accesses to data aligned on its natural boundary will be atomic when the processor implements atomic loads and stores of that data size.

Except where noted, accesses to raw memory are not atomic with respect to the memory or with respect to schedulables. A raw memory area could be updated by another schedulable, or even unmapped in the middle of a method.

The characteristics of raw-memory access are necessarily platform dependent. This specification provides a minimum requirement for the RTSJ platform, but it also supports optional system properties that identify a platform's level of support for atomic raw put and get. The properties represent a four-dimensional sparse array with boolean values indicating whether that combination of access attributes is atomic. The default value for array entries is false. The dimension are

Attribute	Values	Comment
Access type	read, write	
Data type	• byte,	
	• short,	
	• int,	
	• long,	
	• float,	
A 1*	• double	
Alignment	0 to 7	For each data type,
		the possible align-
		$\begin{array}{c ccccccccccccccccccccccccccccccccccc$
		• to data size - 1 ==
		only the first byte of
		the data is alignment
		bytes away from nat-
		ural alignment. • processor means ac-
Atomicity		cess is atomic with
		respect to other
		schedulables on that
		processor.
		• smp means that
		access is processor
	• processor,	atomic, and atomic
	• smp,	with respect across
	• memory	the processors in an
		SMP.
		• memory means that
		access is smp atomic,
		and atomic with re-
		spect to all access to
		the memory includ-
		ing DMA.

The true values in the table are represented by properties of the following form. javax.realtime.atomicaccess_<access>_<type>_<alignment>_atomicity=true for example:

 $javax.real time.atomic access_read_byte_0_memory = true$

Table entries with a value of false may be explicitly represented, but since false is the default value, such properties are redundant.

All raw memory access is treated as volatile, and *serialized*. The run-time must be forced to re-read memory or write to memory on each call to a raw memory getxxx or putxxx method, and to complete the reads and writes in the order they appear in the program order.

Deprecated since RTSJ version as of RTSJ 2.0. Use RawMemoryFactory⁸⁰ to create the appropriate RawMemory⁸¹ object.

Inheritance

```
java.lang.Object
javax.realtime.RawMemoryAccess
```

15.3.3.8.1 Constructors

RawMemoryAccess(Object, long)

Construct an instance of RawMemoryAccess with the given parameters, and set the object to the mapped state. When the platform supports virtual memory, map the raw memory into virtual memory.

The run time environment is allowed to choose the virtual address where the raw memory area corresponding to this object will be mapped. The attributes of the mapping operation are controlled by the vMFlags and vMAttributes of the PhysicalMemoryTypeFilter objects that matched this object's type parameter. (See PhysicalMemoryTypeFilter.getVMAttributes⁸² and PhysicalMemoryTypeFilter.getVMFlags⁸³.

Deprecated since RTSJ version as of RTSJ 2.0. Use RawMemoryFactory⁸⁴ to create the appropriate RawMemory⁸⁵ object.

```
Signature
```

public

RawMemoryAccess(Object type, long size)

```
<sup>80</sup>Section 12.4.3.5

<sup>81</sup>Section 12.4.1.16
```

 $^{^{82}}$ Section 15.3.1.1.1

⁸³Section 15.3.1.1.1

⁸⁴Section 12.4.3.5

⁸⁵ Section 12.4.1.16

Parameters

type An instance of Object representing the type of memory required (e.g., dma, shared) - used to define the base address and control the mapping. When the required memory has more than one attribute, type may be an array of objects. When type is null or a reference to an array with no entries, any type of memory is acceptable. Note that type values are compared by reference (==), not by value (equals).

size The size of the area in bytes.

Throws

SecurityException when the application doesn't have permissions to access physical memory, the specified range of addresses, or the given type of memory. SizeOutOfBoundsException when the size is negative or extends into an invalid range of memory.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryTypeFilter⁸⁶ has been registered with the PhysicalMemoryManager⁸⁷.

Memory Type Conflict Exception when the specified base does not point to memory that matches the request type, or when type specifies incompatible memory attributes.

OutOfMemoryError when the requested type of memory exists, but there is not enough of it free to satisfy the request.

SecurityException when the application doesn't have permissions to access physical memory or the given range of memory.

RawMemoryAccess(Object, long, long)

Construct an instance of RawMemoryAccess with the given parameters, and set the object to the mapped state. When the platform supports virtual memory, map the raw memory into virtual memory.

The run time environment is allowed to choose the virtual address where the raw memory area corresponding to this object will be mapped. The attributes of the mapping operation are controlled by the vMFlags and vMAttributes of the PhysicalMemoryTypeFilter objects that matched this object's type parameter. (See PhysicalMemoryTypeFilter.getVMAttributes⁸⁸ and PhysicalMemoryTypeFilter.getVMFlags⁸⁹.

⁸⁶Section 15.3.1.1

⁸⁷Section 15.3.3.5

⁸⁸Section 15.3.1.1.1

⁸⁹Section 15.3.1.1.1

Deprecated since RTSJ version as of RTSJ 2.0. Use RawMemoryFactory⁹⁰ to create the appropriate RawMemory⁹¹ object.

Signature

```
public
```

RawMemoryAccess(Object type, long base, long size)

Parameters

type An instance of Object representing the type of memory required (e.g., dma, shared) - used to define the base address and control the mapping. When the required memory has more than one attribute, type may be an array of objects. When type is null or a reference to an array with no entries, any type of memory is acceptable. Note that type values are compared by reference (==), not by value (equals).

base The physical memory address of the region.

size The size of the area in bytes.

Throws

SecurityException when application doesn't have permissions to access physical memory, the specified range of addresses, or the given type of memory.

OffsetOutOfBoundsException when the address is invalid.

SizeOutOfBoundsException when the size is negative or extends into an invalid range of memory.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryTypeFilter⁹² has been registered with the PhysicalMemoryManager⁹³.

MemoryTypeConflictException when the specified base does not point to memory that matches the request type, or when type specifies incompatible memory attributes.

OutOfMemoryError when the requested type of memory exists, but there is not enough of it free to satisfy the request.

15.3.3.8.2 Methods

 $^{^{90}}$ Section 12.4.3.5

 $^{^{91}}$ Section 12.4.1.16

⁹²Section 15.3.1.1

 $^{^{93}}$ Section 15.3.3.5

getByte(long)

Gets the byte at the given offset in the memory area associated with this object. The byte is always loaded from memory in a single atomic operation.

Caching of the memory access is controlled by the memory type requested when the RawMemoryAccess instance was created. When the memory is not cached, this method guarantees serialized access (that is, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.)

See Section RawMemoryAccess.map(long,long).

Signature

```
public
byte getByte(long offset)
```

Parameters

offset The offset in bytes from the beginning of the raw memory from which to load the byte.

Throws

SizeOutOfBoundsException when the object is not mapped, or when the byte falls in an invalid address range.

OffsetOutOfBoundsException when the offset is negative or greater than the size of the raw memory area. The role of the SizeOutOfBoundsException⁹⁴ somewhat overlaps this exception since it is when the offset is within the object but outside the mapped area.

SecurityException when this access is not permitted by the security manager. Returns

The byte from raw memory.

getBytes(long, byte[], int, int)

Gets number bytes starting at the given offset in the memory area associated with this object and assigns them to the byte array passed starting at position low. Each byte is loaded from memory in a single atomic operation. Groups of bytes may be loaded together, but this is unspecified.

Caching of the memory access is controlled by the memory type requested when the RawMemoryAccess instance was created. When the memory is not cached, this method guarantees serialized access (that is, the memory access at the memory

⁹⁴Section 14.2.2.14

occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.)

See Section RawMemoryAccess.map(long,long).

Signature

public

void getBytes(long offset, byte[] bytes, int low, int number)

Parameters

offset The offset in bytes from the beginning of the raw memory from which to start loading.

bytes The array into which the loaded items are placed.

low The offset which is the starting point in the given array for the loaded items to be placed.

number The number of items to load.

Throws

OffsetOutOfBoundsException when the offset is negative or greater than the size of the raw memory area. The role of the SizeOutOfBoundsException⁹⁵ somewhat overlaps this exception since it is when the offset is within the object but outside the mapped area.

SizeOutOfBoundsException when the object is not mapped, or when the byte falls in an invalid address range. This is checked at every entry in the array to allow for the possibility that the memory area could be unmapped or remapped. The bytes array could, therefore, be partially updated when the raw memory is unmapped or remapped mid-method.

ArrayIndexOutOfBoundsException when low is less than 0 or greater than bytes.length - 1, or when low + number is greater than or equal to bytes.length. SecurityException when this access is not permitted by the security manager.

getInt(long)

Gets the int at the given offset in the memory area associated with this object. When the integer is aligned on a "natural" boundary it is always loaded from memory in a single atomic operation. When it is not on a natural boundary it may not be loaded atomically, and the number and order of the load operations is unspecified.

Caching of the memory access is controlled by the memory type requested when the RawMemoryAccess instance was created. When the memory is not cached, this method guarantees serialized access (that is, the memory access at the memory

⁹⁵Section 14.2.2.14

occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.)

See Section RawMemoryAccess.map(long,long).

Signature

```
public
int getInt(long offset)
```


offset The offset in bytes from the beginning of the raw memory area from which to load the integer.

Throws

OffsetOutOfBoundsException when the offset is negative or greater than the size of the raw memory area. The role of the SizeOutOfBoundsException⁹⁶ somewhat overlaps this exception since it is when the offset is within the object but outside the mapped area.

SizeOutOfBoundsException when the object is not mapped, or when the integer falls in an invalid address range.

SecurityException when this access is not permitted by the security manager. Returns

The integer from raw memory.

getInts(long, int[], int, int)

Gets number integers starting at the given offset in the memory area associated with this object and assign them to the int array passed starting at position low.

When the integers are aligned on natural boundaries each integer is loaded from memory in a single atomic operation. Groups of integers may be loaded together, but this is unspecified. When the integers are not aligned on natural boundaries they may not be loaded atomically and the number and order of load operations is unspecified.

Caching of the memory access is controlled by the memory type requested when the RawMemoryAccess instance was created. When the memory is not cached, this method guarantees serialized access (that is, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.)

See Section RawMemoryAccess.map(long,long).

⁹⁶Section 14.2.2.14

Signature

public

void getInts(long offset, int[] ints, int low, int number)

Parameters 1

offset The offset in bytes from the beginning of the raw memory area at which to start loading.

ints The array into which the integers read from the raw memory are placed. low The offset which is the starting point in the given array for the loaded items to be placed.

number The number of integers to loaded.

Throws

OffsetOutOfBoundsException when the offset is negative or greater than the size of the raw memory area. The role of the SizeOutOfBoundsException⁹⁷ somewhat overlaps this exception since it is when the offset is within the object but outside the mapped area.

SizeOutOfBoundsException when the object is not mapped, or when the integers fall in an invalid address range. This is checked at every entry in the array to allow for the possibility that the memory area could be unmapped or remapped. The ints array could, therefore, be partially updated when the raw memory is unmapped or remapped mid-method.

ArrayIndexOutOfBoundsException when low is less than 0 or greater than bytes.length - 1, or when low + number is greater than or equal to bytes.length. SecurityException when this access is not permitted by the security manager.

getLong(long)

Gets the long at the given offset in the memory area associated with this object. The load is not required to be atomic even it is located on a natural boundary.

Caching of the memory access is controlled by the memory type requested when the RawMemoryAccess instance was created. When the memory is not cached, this method guarantees serialized access (that is, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.)

Signature

public

⁹⁷Section 14.2.2.14

long getLong(long offset)

offset The offset in bytes from the beginning of the raw memory area from which to load the long.

Throws

OffsetOutOfBoundsException when the offset is invalid.

SizeOutOfBoundsException when the object is not mapped, or when the double falls in an invalid address range.

SecurityException when this access is not permitted by the security manager.

Returns

The long from raw memory.

getLongs(long, long[], int, int)

Gets number longs starting at the given offset in the memory area associated with this object and assign them to the long array passed starting at position low.

The loads are not required to be atomic even when they are located on natural boundaries.

Caching of the memory access is controlled by the memory type requested when the RawMemoryAccess instance was created. When the memory is not cached, this method guarantees serialized access (that is, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.)

See Section RawMemoryAccess.map(long,long).

Signature

```
public
```

void getLongs(long offset, long[] longs, int low, int number)

Parameters

offset The offset in bytes from the beginning of the raw memory area at which to start loading.

longs The array into which the loaded items are placed.

low The offset which is the starting point in the given array for the loaded items to be placed.

number The number of longs to load.

Throws

OffsetOutOfBoundsException when the offset is negative or greater than the

size of the raw memory area. The role of the SizeOutOfBoundsException⁹⁸ somewhat overlaps this exception since it is when the offset is within the object but outside the mapped area.

SizeOutOfBoundsException when the object is not mapped, or when a long falls in an invalid address range. This is checked at every entry in the array to allow for the possibility that the memory area could be unmapped or remapped. The longs array could, therefore, be partially updated when the raw memory is unmapped or remapped mid-method.

ArrayIndexOutOfBoundsException when low is less than 0 or greater than bytes.length - 1, or when low + number is greater than or equal to bytes.length. SecurityException when this access is not permitted by the security manager.

getMappedAddress

Gets the virtual memory location at which the memory region is mapped. Deprecated since RTSJ version as of RTSJ 2.0 The program should never need this information.

```
Signature

public

long getMappedAddress()
```

Throws

 ${\it IllegalStateException}$ when the raw memory object is not in the mapped state. ${\it Returns}$

The virtual address to which this is mapped (for reference purposes). Same as the base address when virtual memory is not supported.

getShort(long)

Gets the **short** at the given offset in the memory area associated with this object. When the short is aligned on a natural boundary it is always loaded from memory in a single atomic operation. When it is not on a natural boundary it may not be loaded atomically, and the number and order of the load operations is unspecified.

Caching of the memory access is controlled by the memory type requested when the RawMemoryAccess instance was created. When the memory is not cached, this method guarantees serialized access (that is, the memory access at the memory

⁹⁸Section 14.2.2.14

occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.)

See Section RawMemoryAccess.map(long,long).

```
Signature
```

```
public
short getShort(long offset)
```

Parameters

offset The offset in bytes from the beginning of the raw memory area from which to load the short.

Throws

OffsetOutOfBoundsException when the offset is negative or greater than the size of the raw memory area. The role of the SizeOutOfBoundsException⁹⁹ somewhat overlaps this exception since it is when the offset is within the object but outside the mapped area.

SizeOutOfBoundsException when the object is not mapped, or when the short falls in an invalid address range.

Security Exception when this access is not permitted by the security manager. Returns

The short loaded from raw memory.

getShorts(long, short[], int, int)

Gets number shorts starting at the given offset in the memory area associated with this object and assign them to the short array passed starting at position low.

When the shorts are located on natural boundaries each short is loaded from memory in a single atomic operation. Groups of shorts may be loaded together, but this is unspecified.

When the shorts are not located on natural boundaries the load may not be atomic, and the number and order of load operations is unspecified. Caching of the memory access is controlled by the memory type requested when the RawMemoryAccess instance was created. When the memory is not cached, this method guarantees serialized access (that is, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.) See Section RawMemoryAccess.map(long,long).

⁹⁹Section 14.2.2.14

Signature

public

void getShorts(long offset, short[] shorts, int low, int number)

Parameters 1

offset The offset in bytes from the beginning of the raw memory area from which to start loading.

shorts The array into which the loaded items are placed.

low The offset which is the starting point in the given array for the loaded shorts to be placed.

number The number of shorts to load.

Throws

OffsetOutOfBoundsException when the offset is negative or greater than the size of the raw memory area. The role of the SizeOutOfBoundsException¹⁰⁰ somewhat overlaps this exception since it is when the offset is within the object but outside the mapped area.

SizeOutOfBoundsException when the object is not mapped, or when a short falls in an invalid address range. This is checked at every entry in the array to allow for the possibility that the memory area could be unmapped or remapped. The shorts array could, therefore, be partially updated when the raw memory is unmapped or remapped mid-method.

ArrayIndexOutOfBoundsException when low is less than 0 or greater than bytes.length - 1, or when low + number is greater than or equal to bytes.length. SecurityException when this access is not permitted by the security manager.

map

Maps the physical memory range into virtual memory. No-op when the system doesn't support virtual memory.

The run time environment is allowed to choose the virtual address where the raw memory area corresponding to this object will be mapped. The attributes of the mapping operation are controlled by the vMFlags and vMAttributes of the PhysicalMemoryTypeFilter objects that matched this object's type parameter. (See PhysicalMemoryTypeFilter.getVMAttributes 101 and PhysicalMemoryTypeFilter.getVMFlags 102.

¹⁰⁰Section 14.2.2.14

 $^{^{101}}$ Section 15.3.1.1.1

 $^{^{102}}$ Section 15.3.1.1.1

When the object is already mapped into virtual memory, this method does not change anything.

```
Signature public long map()
```

Throws

OutOfMemoryError when there is insufficient free virtual address space to map the object.

Returns

The starting point of the virtual memory range.

map(long)

Maps the physical memory range into virtual memory at the specified location. No-op when the system doesn't support virtual memory.

The attributes of the mapping operation are controlled by the vMFlags and vMAttributes of the PhysicalMemoryTypeFilter objects that matched this object's type parameter. (See PhysicalMemoryTypeFilter.getVMAttributes¹⁰³ and PhysicalMemoryTypeFilter.getVMFlags¹⁰⁴.

When the object is already mapped into virtual memory at a different address, this method remaps it to base.

When a remap is requested while another schedulable is accessing the raw memory, the map will block until one load or store completes. It can interrupt an array operation between entries.

Deprecated since RTSJ version as of RTSJ 2.0 No replacement

```
Signature

public

long map(long base)

Parameters
```

base The location to map at the virtual memory space.

Throws

OutOfMemoryError when there is insufficient free virtual memory at the specified address.

```
<sup>103</sup>Section 15.3.1.1.1
<sup>104</sup>Section 15.3.1.1.1
```

IllegalArgumentException when base is not a legal value for a virtual address, or the memory-mapping hardware cannot place the physical memory at the designated address.

Returns

The starting point of the virtual memory.

map(long, long)

Maps the physical memory range into virtual memory. No-op when the system doesn't support virtual memory.

The attributes of the mapping operation are controlled by the vMFlags and vMAttributes of the PhysicalMemoryTypeFilter objects that matched this object's type parameter. (See PhysicalMemoryTypeFilter.getVMAttributes¹⁰⁵ and PhysicalMemoryTypeFilter.getVMFlags¹⁰⁶.

When the object is already mapped into virtual memory at a different address, this method remaps it to base.

When a remap is requested while another schedulable is accessing the raw memory, the map will block until one load or store completes. It can interrupt an array operation between entries.

Deprecated since RTSJ version as of RTSJ 2.0 No replacement

```
Signature
```

```
public
long map(long base, long size)
```

Parameters

base The location to map at the virtual memory space.

size The size of the block to map in. When the size of the raw memory area is greater than size, the object is unchanged but accesses beyond the mapped region will throw SizeOutOfBoundsException¹⁰⁷. When the size of the raw memory area is smaller than the mapped region access to the raw memory will behave as if the mapped region matched the raw memory area, but additional virtual address space will be consumed after the end of the raw memory area.

Throws

IllegalArgumentException when size is not greater than zero, base is not a legal value for a virtual address, or the memory-mapping hardware cannot

¹⁰⁵Section 15.3.1.1.1

 $^{^{106}}$ Section 15.3.1.1.1

 $^{^{107}}$ Section 14.2.2.14

place the physical memory at the designated address.

Returns

The starting point of the virtual memory.

setByte(long, byte)

Sets the byte at the given offset in the memory area associated with this object.

This memory access may involve a load and a store, and it may have unspecified effects on surrounding bytes in the presence of concurrent access.

Caching of the memory access is controlled by the memory type requested when the RawMemoryAccess instance was created. When the memory is not cached, this method guarantees serialized access (that is, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.)

See Section RawMemoryAccess.map(long,long).

Signature

```
public
void setByte(long offset, byte value)
```

Parameters

offset The offset in bytes from the beginning of the raw memory area to which to write the byte.

value The byte to write.

Throws

OffsetOutOfBoundsException when the offset is negative or greater than the size of the raw memory area. The role of the SizeOutOfBoundsException¹⁰⁸ somewhat overlaps this exception since it is when the offset is within the object but outside the mapped area.

SizeOutOfBoundsException when the object is not mapped, or when the byte falls in an invalid address range.

SecurityException when this access is not permitted by the security manager.

setBytes(long, byte[], int, int)

Sets number bytes starting at the given offset in the memory area associated with this object from the byte array passed starting at position low.

¹⁰⁸Section 14.2.2.14

This memory access may involve multiple load and a store operations, and it may have unspecified effects on surrounding bytes (even bytes in the range being stored) in the presence of concurrent access.

Caching of the memory access is controlled by the memory type requested when the RawMemoryAccess instance was created. When the memory is not cached, this method guarantees serialized access (that is, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.)

See Section RawMemoryAccess.map(long,long).

Signature

public

void setBytes(long offset, byte[] bytes, int low, int number)

Parameters 5 4 1

offset The offset in bytes from the beginning of the raw memory area to which to start writing.

bytes The array from which the items are obtained.

low The offset which is the starting point in the given array for the items to be obtained.

number The number of items to write.

Throws

OffsetOutOfBoundsException when the offset is negative or greater than the size of the raw memory area. The role of the SizeOutOfBoundsException¹⁰⁹ somewhat overlaps this exception since it is when the offset is within the object but outside the mapped area.

SizeOutOfBoundsException when the object is not mapped, or when the a short falls in an invalid address range. This is checked at every entry in the array to allow for the possibility that the memory area could be unmapped or remapped. The store of the array into memory could, therefore, be only partially complete when the raw memory is unmapped or remapped mid-method. ArrayIndexOutOfBoundsException when low is less than 0 or greater than bytes.length - 1, or when low + number is greater than or equal to bytes.length. SecurityException when this access is not permitted by the security manager.

setInt(long, int)

¹⁰⁹Section 14.2.2.14

Sets the int at the given offset in the memory area associated with this object. On most processor architectures an aligned integer can be stored in an atomic operation, but this is not required.

This memory access may involve multiple load and a store operations, and it may have unspecified effects on surrounding bytes (even bytes in the range being stored) in the presence of concurrent access.

Caching of the memory access is controlled by the memory type requested when the RawMemoryAccess instance was created. When the memory is not cached, this method guarantees serialized access (that is, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.)

See Section RawMemoryAccess.map(long,long).

```
Signature
```

```
public
void setInt(long offset, int value)
```

Parameters

offset The offset in bytes from the beginning of the raw memory area at which to write the integer.

value The integer to write.

Throws

OffsetOutOfBoundsException when the offset is negative or greater than the size of the raw memory area. The role of the SizeOutOfBoundsException¹¹⁰ somewhat overlaps this exception since it is when the offset is within the object but outside the mapped area.

SizeOutOfBoundsException when the object is not mapped, or when the integer falls in an invalid address range.

Security Exception when this access is not permitted by the security manager.

setInts(long, int[], int, int)

Sets number into starting at the given offset in the memory area associated with this object from the int array passed starting at position low. On most processor architectures each aligned integer can be stored in an atomic operation, but this is not required.

This memory access may involve multiple load and a store operations, and it may have unspecified effects on surrounding bytes (even bytes in the range being

¹¹⁰Section 14.2.2.14

stored) in the presence of concurrent access.

Caching of the memory access is controlled by the memory type requested when the RawMemoryAccess instance was created. When the memory is not cached, this method guarantees serialized access (that is, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.)

See Section RawMemoryAccess.map(long,long).

```
Signature
```

public

void setInts(long offset, int[] ints, int low, int number)

Parameters

offset The offset in bytes from the beginning of the raw memory area at which to start writing.

ints The array from which the items are obtained.

low The offset which is the starting point in the given array for the items to be obtained.

number The number of items to write.

Throws

OffsetOutOfBoundsException when the offset is negative or greater than the size of the raw memory area. The role of the SizeOutOfBoundsException¹¹¹ somewhat overlaps this exception since it is when the offset is within the object but outside the mapped area.

SizeOutOfBoundsException when the object is not mapped, or when an int falls in an invalid address range. This is checked at every entry in the array to allow for the possibility that the memory area could be unmapped or remapped. The store of the array into memory could, therefore, be only partially complete when the raw memory is unmapped or remapped mid-method. ArrayIndexOutOfBoundsException when low is less than 0 or greater than bytes.length - 1, or when low + number is greater than or equal to bytes.length. SecurityException when this access is not permitted by the security manager.

setLong(long, long)

Sets the long at the given offset in the memory area associated with this object. Even when it is aligned, the long value may not be updated atomically. It is unspecified how many load and store operations will be used or in what order.

¹¹¹Section 14.2.2.14

This memory access may involve multiple load and a store operations, and it may have unspecified effects on surrounding bytes (even bytes in the range being stored) in the presence of concurrent access.

Caching of the memory access is controlled by the memory type requested when the RawMemoryAccess instance was created. When the memory is not cached, this method guarantees serialized access (that is, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.)

See Section RawMemoryAccess.map(long,long).

```
Signature
```

```
public
void setLong(long offset, long value)
```

Parameters 5 4 1

offset The offset in bytes from the beginning of the raw memory area at which to write the long.

value The long to write.

Throws

OffsetOutOfBoundsException when the offset is negative or greater than the size of the raw memory area. The role of the SizeOutOfBoundsException¹¹² somewhat overlaps this exception since it is when the offset is within the object but outside the mapped area.

SizeOutOfBoundsException when the object is not mapped, or when the long falls in an invalid address range.

Security Exception when this access is not permitted by the security manager.

setLongs(long, long[], int, int)

Sets number longs starting at the given offset in the memory area associated with this object from the long array passed starting at position low. Even when they are aligned, the long values may not be updated atomically. It is unspecified how many load and store operations will be used or in what order.

This memory access may involve multiple load and a store operations, and it may have unspecified effects on surrounding bytes (even bytes in the range being stored) in the presence of concurrent access.

Caching of the memory access is controlled by the memory type requested when the RawMemoryAccess instance was created. When the memory is not cached, this

¹¹²Section 14.2.2.14

method guarantees serialized access (that is, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.)

See Section RawMemoryAccess.map(long,long).

Signature

public

void setLongs(long offset, long[] longs, int low, int number)

Parameters

offset The offset in bytes from the beginning of the raw memory area at which to start writing.

longs The array from which the items are obtained.

low The offset which is the starting point in the given array for the items to be obtained.

number The number of items to write.

Throws

OffsetOutOfBoundsException when the offset is negative or greater than the size of the raw memory area. The role of the SizeOutOfBoundsException¹¹³ somewhat overlaps this exception since it is when the offset is within the object but outside the mapped area.

SizeOutOfBoundsException when the object is not mapped, or when the a short falls in an invalid address range. This is checked at every entry in the array to allow for the possibility that the memory area could be unmapped or remapped. The store of the array into memory could, therefore, be only partially complete when the raw memory is unmapped or remapped mid-method. ArrayIndexOutOfBoundsException when low is less than 0 or greater than bytes.length - 1, or when low + number is greater than or equal to bytes.length. SecurityException when this access is not permitted by the security manager.

setShort(long, short)

Sets the **short** at the given offset in the memory area associated with this object. This memory access may involve a load and a store, and it may have unspecified effects on surrounding shorts in the presence of concurrent access.

Caching of the memory access is controlled by the memory type requested when the RawMemoryAccess instance was created. When the memory is not cached, this method guarantees serialized access (that is, the memory access at the memory

¹¹³Section 14.2.2.14

occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.)

See Section RawMemoryAccess.map(long,long).

Signature

```
public
void setShort(long offset, short value)
```


offset The offset in bytes from the beginning of the raw memory area at which to write the short.

value The short to write.

Throws

OffsetOutOfBoundsException when the offset is negative or greater than the size of the raw memory area. The role of the SizeOutOfBoundsException¹¹⁴ somewhat overlaps this exception since it is when the offset is within the object but outside the mapped area.

SizeOutOfBoundsException when the object is not mapped, or when the short falls in an invalid address range.

SecurityException when this access is not permitted by the security manager.

setShorts(long, short[], int, int)

Sets number shorts starting at the given offset in the memory area associated with this object from the short array passed starting at position low.

Each write of a short value may involve a load and a store, and it may have unspecified effects on surrounding shorts in the presence of concurrent access - even on other shorts in the array.

Caching of the memory access is controlled by the memory type requested when the RawMemoryAccess instance was created. When the memory is not cached, this method guarantees serialized access (that is, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.)

See Section RawMemoryAccess.map(long,long).

Signature

¹¹⁴Section 14.2.2.14

public
 void setShorts(long offset, short[] shorts, int low, int number)
Parameters

offset The offset in bytes from the beginning of the raw memory area at which to start writing.

shorts The array from which the items are obtained.

low The offset which is the starting point in the given array for the items to be obtained.

number The number of items to write.

Throws

OffsetOutOfBoundsException when the offset is negative or greater than the size of the raw memory area. The role of the SizeOutOfBoundsException¹¹⁵ somewhat overlaps this exception since it is when the offset is within the object but outside the mapped area.

SizeOutOfBoundsException when the object is not mapped, or when the a short falls in an invalid address range. This is checked at every entry in the array to allow for the possibility that the memory area could be unmapped or remapped. The store of the array into memory could, therefore, be only partially complete when the raw memory is unmapped or remapped mid-method. ArrayIndexOutOfBoundsException when low is less than 0 or greater than bytes.length - 1, or when low + number is greater than or equal to bytes.length. SecurityException when this access is not permitted by the security manager.

unmap

Unmap the physical memory range from virtual memory. This changes the raw memory from the mapped state to the unmapped state. When the platform supports virtual memory, this operation frees the virtual addresses used for the raw memory region.

When the object is already in the unmapped state, this method has no effect.

While a raw memory object is unmapped all attempts to set or get values in the raw memory will throw SizeOutOfBoundsException¹¹⁶.

An unmapped raw memory object can be returned to mapped state with any of the object's map methods.

When an unmap is requested while another schedulable is accessing the raw memory, the unmap will throw an IllegalStateException. The unmap method can interrupt an array operation between entries.

 $^{^{115}}$ Section 14.2.2.14

 $^{^{116}}$ Section 14.2.2.14

```
Signature
public
void unmap()
```

15.3.3.9 RawMemoryFloatAccess

This class holds the accessor methods for accessing a raw memory area by float and double types. Implementations are required to implement this class when and only when the underlying Java Virtual Machine supports floating point data types.

See RawMemoryAccess¹¹⁷ for commentary on changes in the preferred use of this class following RTSJ 2.0.

By default, the byte addressed by offset is the byte at the lowest address of the floating point processor's floating point representation. When the type of memory used for this RawMemoryFloatAccess region implements a non-standard floating point format, accessor methods in this class continue to select bytes starting at offset from the base address and continuing toward greater addresses. The memory type may control the mapping of these bytes into the primitive data type. The memory type could even select bytes that are not contiguous. In each case the documentation for the PhysicalMemoryTypeFilter¹¹⁸ must document any mapping other than the "normal" one specified above.

All offset values used in this class are measured in bytes.

Atomic loads and stores on raw memory are defined in terms of physical memory. This memory may be accessible to threads outside the JVM and to non-programmed access (e.g., DMA), consequently atomic access must be supported by hardware. This specification is written with the assumption that all suitable hardware platforms support atomic loads for aligned floats. Atomic access beyond the specified minimum may be supported by the implementation.

Storing values into raw memory is more hardware-dependent than loading values. Many processor architectures do not support atomic stores of variables except for aligned stores of the processor's word size.

This class supports unaligned access to data, but it does not require the implementation to make such access atomic. Accesses to data aligned on its natural boundary will be atomic when the processor implements atomic loads and stores of that data size.

 $^{^{117}}$ Section 15.3.3.8

 $^{^{118}}$ Section 15.3.1.1

Except where noted, accesses to raw memory are not atomic with respect to the memory or with respect to threads. A raw memory area could be updated by another thread, or even unmapped in the middle of a method.

The characteristics of raw-memory access are necessarily platform dependent. This specification provides a minimum requirement for the RTSJ platform, but it also supports a optional system properties that identify a platform's level of support for atomic raw put and get. (See RawMemoryAccess¹¹⁹.) The properties represent a four-dimensional sparse array with boolean values whether that combination of access attributes is atomic. The default value for array entries is false.

Many of the constructors and methods in this class throw OffsetOutOfBound-sexception¹²⁰. This exception means that the value given in the offset parameter is either negative or outside the memory area.

Many of the constructors and methods in this class throw SizeOutOfBoundsException¹²¹. This exception means that the value given in the size parameter is either negative, larger than an allowable range, or would cause an accessor method to access an address outside of the memory area.

Deprecated since RTSJ version as of RTSJ 2.0. Use RawMemory¹²².

Inheritance

```
javax.realtime.RawMemoryAccess
javax.realtime.RawMemoryFloatAccess
```

15.3.3.9.1 Constructors

RawMemoryFloatAccess(Object, long)

Construct an instance of RawMemoryFloatAccess with the given parameters, and set the object to the mapped state. When the platform supports virtual memory, map the raw memory into virtual memory.

The run time environment is allowed to choose the virtual address where the raw memory area corresponding to this object will be mapped. The attributes of the mapping operation are controlled by the vMFlags and vMAttributes of the PhysicalMemoryTypeFilter objects that matched this object's type parameter.

```
^{119}Section 15.3.3.8
```

¹²⁰Section 14.2.2.10

¹²¹Section 14.2.2.14

 $^{^{122}}$ Section 12.4.1.16

(See Physical Memory Type Filter. get VMA ttributes 123 and Physical Memory Type Filter. get VMF lags 124 .

Deprecated since RTSJ version as of RTSJ 2.0. Use RawMemoryFactory.createRawFloat(Rawlong, int, int)¹²⁵ or RawMemoryFactory.createRawDouble(RawMemoryRegion, long, int, int)¹²⁶.

Signature

public

RawMemoryFloatAccess(Object type, long size)

type An instance of Object representing the type of memory required (e.g., dma, shared) - used to define the base address and control the mapping. When the required memory has more than one attribute, type may be an array of objects. When type is null or a reference to an array with no entries, any type of memory is acceptable. Note that type values are compared by reference (==), not by value (equals).

size The size of the area in bytes.

Throws

SecurityException when the application doesn't have permissions to access physical memory, the specified range of addresses, or the given type of memory. SizeOutOfBoundsException when the size is negative or extends into an invalid range of memory.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryTypeFilter¹²⁷ has been registered with the PhysicalMemoryManager¹²⁸.

MemoryTypeConflictException when the specified base does not point to memory that matches the request type, or when type specifies incompatible memory attributes.

OutOfMemoryError when the requested type of memory exists, but there is not enough of it free to satisfy the request.

```
123 Section 15.3.1.1.1

124 Section 15.3.1.1.1

125 Section 12.4.3.5.3

126 Section 12.4.3.5.3

127 Section 15.3.1.1

128 Section 15.3.3.5
```

RawMemoryFloatAccess(Object, long, long)

Construct an instance of RawMemoryFloatAccess with the given parameters, and set the object to the mapped state. When the platform supports virtual memory, map the raw memory into virtual memory.

The run time environment is allowed to choose the virtual address where the raw memory area corresponding to this object will be mapped. The attributes of the mapping operation are controlled by the vMFlags and vMAttributes of the PhysicalMemoryTypeFilter objects that matched this object's type parameter. (See PhysicalMemoryTypeFilter.getVMAttributes¹²⁹ and PhysicalMemoryTypeFilter.getVMFlags¹³⁰.

Deprecated since RTSJ version as of RTSJ 2.0. Use RawMemoryFactory.createRawFloat(RawMemoryFactory.treateRawDouble(RawMemoryRegion, long, int, int)¹³¹ or RawMemoryFactory.createRawDouble(RawMemoryRegion, long, int, int)¹³².

Signature

public

RawMemoryFloatAccess(Object type, long base, long size)

Parameters

type An instance of Object representing the type of memory required (e.g., dma, shared) - used to define the base address and control the mapping. When the required memory has more than one attribute, type may be an array of objects. When type is null or a reference to an array with no entries, any type of memory is acceptable. Note that type values are compared by reference (==), not by value (equals).

base The physical memory address of the region.

size The size of the area in bytes.

Throws

SecurityException when the application doesn't have permissions to access physical memory, the specified range of addresses, or the given type of memory. OffsetOutOfBoundsException when the address is invalid.

SizeOutOfBoundsException when the size is negative or extends into an invalid range of memory.

 $^{^{129}}$ Section 15.3.1.1.1

 $^{^{130}}$ Section 15.3.1.1.1

¹³¹Section 12.4.3.5.3

¹³²Section 12.4.3.5.3

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryTypeFilter¹³³ has been registered with the PhysicalMemoryManager¹³⁴.

Memory Type Conflict Exception when the specified base does not point to memory that matches the request type, or when type specifies incompatible memory attributes.

OutOfMemoryError when the requested type of memory exists, but there is not

15.3.3.9.2 Methods

getDouble(long)

Gets the double at the given offset in the memory area associated with this object.

The load is not required to be atomic even it is located on a natural boundary.

Caching of the memory access is controlled by the memory type requested when the RawMemoryAccess instance was created. When the memory is not cached, this method guarantees serialized access (that is, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.)

Signature

```
public
double getDouble(long offset)
```


offset The offset in bytes from the beginning of the raw memory area from which to load the long.

Throws

OffsetOutOfBoundsException when the offset is invalid.

SizeOutOfBoundsException when the object is not mapped, or when the double falls in an invalid address range.

SecurityException when this access is not permitted by the security manager. Returns

The double from raw memory.

```
<sup>133</sup>Section 15.3.1.1

<sup>134</sup>Section 15.3.3.5
```

getDoubles(long, double[], int, int)

Gets number doubles starting at the given offset in the memory area associated with this object and assign them to the double array passed starting at position low

The loads are not required to be atomic even when they are located on natural boundaries.

Caching of the memory access is controlled by the memory type requested when the RawMemoryAccess instance was created. When the memory is not cached, this method guarantees serialized access (that is, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.)

Signature

```
public
void getDoubles(long offset, double[] doubles, int low, int
number)
```

Parameters 1 4 1

offset The offset in bytes from the beginning of the raw memory area at which to start loading.

doubles The array into which the loaded items are placed.

low The offset which is the starting point in the given array for the loaded items to be placed.

number The number of doubles to load.

Throws

OffsetOutOfBoundsException when the offset is negative or greater than the size of the raw memory area. The role of the SizeOutOfBoundsException somewhat overlaps this exception since it is when the offset is within the object but outside the mapped area. (See RawMemoryAccess.map(long,long)¹³⁵). SizeOutOfBoundsException when the object is not mapped, or when a double falls in an invalid address range. This is checked at every entry in the array to allow for the possibility that the memory area could be unmapped or remapped. The doubles array could, therefore, be partially updated when the raw memory is unmapped or remapped mid-method.

ArrayIndexOutOfBoundsException when low is less than 0 or greater than bytes.length - 1, or when low + number is greater than or equal to bytes.length. SecurityException when this access is not permitted by the security manager.

 $^{^{135}}$ Section 15.3.3.8.2

getFloat(long)

Gets the float at the given offset in the memory area associated with this object. When the float is aligned on a "natural" boundary it is always loaded from memory in a single atomic operation. When it is not on a natural boundary it may not be loaded atomically, and the number and order of the load operations is unspecified.

Caching of the memory access is controlled by the memory type requested when the RawMemoryAccess instance was created. When the memory is not cached, this method guarantees serialized access (that is, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.)

```
Signature
```

public
float getFloat(long offset)

Parameters

offset The offset in bytes from the beginning of the raw memory area from which to load the float.

Throws

OffsetOutOfBoundsException when the offset is negative or greater than the size of the raw memory area. The role of the SizeOutOfBoundsException somewhat overlaps this exception since it is when the offset is within the object but outside the mapped area. (See RawMemoryAccess.map(long,long)¹³⁶). SizeOutOfBoundsException when the object is not mapped, or when the float falls in an invalid address range.

 $Security Exception \ \ \ when this access is not permitted by the security manager.$ Returns

The float from raw memory.

getFloats(long, float[], int, int)

Gets number floats starting at the given offset in the memory area associated with this object and assign them to the int array passed starting at position low.

When the floats are aligned on natural boundaries each float is loaded from memory in a single atomic operation. Groups of floats may be loaded together, but this is unspecified.

When the floats are not aligned on natural boundaries they may not be loaded atomically and the number and order of load operations is unspecified.

¹³⁶Section 15.3.3.8.2

Caching of the memory access is controlled by the memory type requested when the RawMemoryAccess instance was created. When the memory is not cached, this method guarantees serialized access (that is, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.)

Signature

public

void getFloats(long offset, float[] floats, int low, int number)

Parameters 1

offset The offset in bytes from the beginning of the raw memory area at which to start loading.

floats The array into which the floats loaded from the raw memory are placed. low The offset which is the starting point in the given array for the loaded items to be placed.

number The number of floats to loaded.

Throws

OffsetOutOfBoundsException when the offset is negative or greater than the size of the raw memory area. The role of the SizeOutOfBoundsException somewhat overlaps this exception since it is when the offset is within the object but outside the mapped area. (See RawMemoryAccess.map(long,long)¹³⁷). SizeOutOfBoundsException when the object is not mapped, or when a float falls in an invalid address range. This is checked at every entry in the array to allow for the possibility that the memory area could be unmapped or remapped. The floats array could, therefore, be partially updated when the raw memory is unmapped or remapped mid-method.

ArrayIndexOutOfBoundsException when low is less than 0 or greater than bytes.length - 1, or when low + number is greater than or equal to bytes.length. SecurityException when this access is not permitted by the security manager.

setDouble(long, double)

Sets the double at the given offset in the memory area associated with this object. Even when it is aligned, the double value may not be updated atomically. It is unspecified how many load and store operations will be used or in what order.

Caching of the memory access is controlled by the memory type requested when the RawMemoryAccess instance was created. When the memory is not cached, this method guarantees serialized access (that is, the memory access at the memory

¹³⁷Section 15.3.3.8.2

occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.)

```
Signature
```

```
public
void setDouble(long offset, double value)
```

Parameters 1 4 1

offset The offset in bytes from the beginning of the raw memory area at which to write the double.

value The double to write.

Throws

OffsetOutOfBoundsException when the offset is negative or greater than the size of the raw memory area. The role of the SizeOutOfBoundsException somewhat overlaps this exception since it is when the offset is within the object but outside the mapped area. (See RawMemoryAccess.map(long,long)¹³⁸). SizeOutOfBoundsException when the object is not mapped, or when the double falls in an invalid address range.

Security Exception when this access is not permitted by the security manager.

setDoubles(long, double[], int, int)

Sets number doubles starting at the given offset in the memory area associated with this object from the double array passed starting at position low. Even when they are aligned, the double values may not be updated atomically. It is unspecified how many load and store operations will be used or in what order.

Caching of the memory access is controlled by the memory type requested when the RawMemoryAccess instance was created. When the memory is not cached, this method guarantees serialized access (that is, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.)

```
Signature
```

```
public
void setDoubles(long offset, double[] doubles, int low, int
number)
```

Parameters

¹³⁸Section 15.3.3.8.2

offset The offset in bytes from the beginning of the raw memory area at which to start writing.

doubles The array from which the items are obtained.

low The offset which is the starting point in the given array for the items to be obtained.

number The number of items to write.

Throws

OffsetOutOfBoundsException when the offset is negative or greater than the size of the raw memory area. The role of the SizeOutOfBoundsException somewhat overlaps this exception since it is when the offset is within the object but outside the mapped area. (See RawMemoryAccess.map(long,long)¹³⁹). SizeOutOfBoundsException when the object is not mapped, or when the a short falls in an invalid address range. This is checked at every entry in the array to allow for the possibility that the memory area could be unmapped or remapped. The doubles array could, therefore, be partially updated when the raw memory is unmapped or remapped mid-method.

ArrayIndexOutOfBoundsException when low is less than 0 or greater than bytes.length - 1, or when low + number is greater than or equal to bytes.length. SecurityException when this access is not permitted by the security manager.

setFloat(long, float)

Sets the float at the given offset in the memory area associated with this object. On most processor architectures an aligned float can be stored in an atomic operation, but this is not required.

Caching of the memory access is controlled by the memory type requested when the RawMemoryAccess instance was created. When the memory is not cached, this method guarantees serialized access (that is, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.)

```
Signature
```

public
void setFloat(long offset, float value)

Parameters 1 4 1

offset The offset in bytes from the beginning of the raw memory area at which to write the integer.

value The float to write.

 $^{^{139}}$ Section 15.3.3.8.2

Throws

OffsetOutOfBoundsException when the offset is negative or greater than the size of the raw memory area. The role of the SizeOutOfBoundsException somewhat overlaps this exception since it is when the offset is within the object but outside the mapped area. (See RawMemoryAccess.map(long,long)¹⁴⁰). SizeOutOfBoundsException when the object is not mapped, or when the float falls in an invalid address range.

SecurityException when this access is not permitted by the security manager.

setFloats(long, float[], int, int)

Sets number floats starting at the given offset in the memory area associated with this object from the float array passed starting at position low. On most processor architectures each aligned float can be stored in an atomic operation, but this is not required. Caching of the memory access is controlled by the memory type requested when the RawMemoryAccess instance was created. When the memory is not cached, this method guarantees serialized access (that is, the memory access at the memory occurs in the same order as in the program. Multiple writes to the same location may not be coalesced.)

Signature

public

void setFloats(long offset, float[] floats, int low, int number)

Parameters 5 4 1

offset The offset in bytes from the beginning of the raw memory area at which to start writing.

floats The array from which the items are obtained.

low The offset which is the starting point in the given array for the items to be obtained.

number The number of floats to write.

Throws

OffsetOutOfBoundsException when the offset is negative or greater than the size of the raw memory area. The role of the SizeOutOfBoundsException somewhat overlaps this exception since it is when the offset is within the object but outside the mapped area. (See RawMemoryAccess.map(long, long) 141). SizeOutOfBoundsException when the object is not mapped, or when the float falls in an invalid address range. This is checked at every entry in the ar-

 $^{^{140}}$ Section 15.3.3.8.2

 $^{^{141}}$ Section 15.3.3.8.2

ray to allow for the possibility that the memory area could be unmapped or remapped. The store of the array into memory could, therefore, be only partially complete when the raw memory is unmapped or remapped mid-method. ArrayIndexOutOfBoundsException when low is less than 0 or greater than bytes.length - 1, or when low + number is greater than or equal to bytes.length. SecurityException when this access is not permitted by the security manager.

15.3.3.10 VTMemory

VTMemory is similar to LTMemory¹⁴² except that the execution time of an allocation from a VTMemory area need not complete in linear time.

Methods from VTMemory should be overridden only by methods that use super. Deprecated since RTSJ version as of RTSJ 2.0

Inheritance

```
javax.realtime.MemoryArea
javax.realtime.ScopedMemory
javax.realtime.VTMemory
```

15.3.3.10.1 Constructors

VTMemory(long, long)

Creates a VTMemory with the given parameters.

Signature

```
public
  VTMemory(long initial, long maximum)
```

Parameters

initial The size in bytes of the memory to initially allocate for this area.

¹⁴²Section 11.5.3.1

maximum The maximum size in bytes this memory area to which the size may grow.

VTMemory

Throws

Illegal Argument Exception when initial is greater than maximum or when initial or maximum is less than zero.

OutOfMemoryError when there is insufficient memory for the VTMemory object or for the backing memory.

VTMemory(long, long, Runnable)

Creates a VTMemory with the given parameters.

Signature

```
public
```

VTMemory(long initial, long maximum, Runnable logic)

initial The size in bytes of the memory to initially allocate for this area. maximum The maximum size in bytes this memory area to which the size may grow.

logic An instance of Runnable whose run() method will use this as its initial memory area. When logic is null, this constructor is equivalent to VTMemory(long initial, long maximum)¹⁴³.

Throws

IllegalArgumentException when initial is greater than maximum, or when initial or maximum is less than zero.

OutOfMemoryError when there is insufficient memory for the VTMemory object or for the backing memory.

IllegalAssignmentError when storing logic in this would violate the assignment rules.

VTMemory(SizeEstimator, SizeEstimator)

Creates a VTMemory with the given parameters.

Signature

¹⁴³Section 15.3.3.10.1

public

VTMemory(SizeEstimator initial, SizeEstimator maximum)

initial The size in bytes of the memory to initially allocate for this area.

maximum The maximum size in bytes this memory area to which the size may grow estimated by an instance of SizeEstimator¹⁴⁴.

Throws

IllegalArgumentException when initial is null, maximum is null, initial.getEstimate() is greater than maximum.getEstimate(), or when initial.getEstimate() is less than zero.

OutOfMemoryError when there is insufficient memory for the VTMemory object or for the backing memory.

VTMemory(SizeEstimator, SizeEstimator, Runnable)

Creates a VTMemory with the given parameters.

Signature

public

VTMemory(SizeEstimator initial, SizeEstimator maximum, Runnable logic)

Parameters

initial The size in bytes of the memory to initially allocate for this area.

maximum The maximum size in bytes this memory area to which the size may grow estimated by an instance of SizeEstimator¹⁴⁵.

logic An instance of Runnable whose run() method will use this as its initial memory area. When logic is null, this constructor is equivalent to VTMemory(SizeEstimator initial, SizeEstimator maximum)¹⁴⁶.

Throws

IllegalArgumentException when initial is null, maximum is null, initial.getEstimate() is greater than maximum.getEstimate(), or when initial.getEstimate() is less than zero.

OutOfMemoryError when there is insufficient memory for the VTMemory object or for the backing memory.

 $^{^{144}}$ Section 11.4.2.6

 $^{^{145}}$ Section 11.4.2.6

 $^{^{146}}$ Section 15.3.3.10.1

IllegalAssignmentError when storing logic in this would violate the assignment rules.

VTMemory(long)

Create an VTMemory of the given size. This constructor is equivalent to VTMemory(size, size)

Available since RTSJ 1.0.1

Signature

```
public
```

VTMemory(long size)

Parameters

size The size in bytes of the memory to allocate for this area. This memory must be committed before the completion of the constructor.

Throws

IllegalArgumentException when size is less than zero.

OutOfMemoryError when there is insufficient memory for the VTMemory object or for the backing memory.

VTMemory(long, Runnable)

Create an VTMemory of the given size. This constructor is equivalent to VTMemory(size, size, logic).

Available since RTSJ 1.0.1

Signature

```
public
```

VTMemory(long size, Runnable logic)

Parameters 1

size The size in bytes of the memory to allocate for this area. This memory must be committed before the completion of the constructor.

2.0 (Draft 20)

logic The run() of the given Runnable will be executed using this as its initial memory area. When logic is null, this constructor is equivalent to VTMemory(long size)¹⁴⁷.

Throws

IllegalArgumentException when size is less than zero.

OutOfMemoryError when there is insufficient memory for the VTMemory object or for the backing memory.

IllegalAssignmentError when storing logic in this would violate the assignment rules.

VTMemory(SizeEstimator)

Create an VTMemory of the given size. This constructor is equivalent to VTMemory(size, size).

Available since RTSJ 1.0.1

Signature

public

VTMemory(SizeEstimator size)

Parameters

size An instance of SizeEstimator¹⁴⁸ used to give an estimate of the initial size. This memory must be committed before the completion of the constructor.

Throws

IllegalArgumentException when size is null, or size.getEstimate() is less than zero.

OutOfMemoryError when there is insufficient memory for the VTMemory object or for the backing memory.

VTMemory(SizeEstimator, Runnable)

Create an VTMemory of the given size.

Available since RTSJ 1.0.1

¹⁴⁸Section 11.4.2.6

 $^{^{147}}$ Section 15.3.3.10.1

Signature

public

VTMemory(SizeEstimator size, Runnable logic)

Parameters

size An instance of SizeEstimator¹⁴⁹ used to give an estimate of the initial size. This memory must be committed before the completion of the constructor.

logic The run() of the given Runnable will be executed using this as its initial memory area. When logic is null, this constructor is equivalent to VTMemory(SizeEstimator initial)¹⁵⁰.

Throws

IllegalArgumentException when size is null, or size.getEstimate() is less than zero.

OutOfMemoryError when there is insufficient memory for the VTMemory object or for the backing memory.

IllegalAssignmentError when storing logic in this would violate the assignment rules.

15.3.3.10.2 Methods

toString

Create a string representing this object. The string is of the form (VTMemory) Scoped memory # num where num uniquely identifies the VTMemory area.

Signature

```
public
java.lang.String toString()
```

Returns

A string representing the value of this.

```
<sup>149</sup>Section 11.4.2.6

<sup>150</sup>Section 15.3.3.10.1
```

15.3.3.11 VTPhysicalMemory

An instance of VTPhysicalMemory allows objects to be allocated from a range of physical memory with particular attributes, determined by their memory type. This memory area has the same semantics as ScopedMemory¹⁵¹ memory areas, and the same performance restrictions as VTMemory.

No provision is made for sharing object in VTPhysicalMemory with entities outside the JVM that creates them, and, while the memory backing an instance of VTPhysicalMemory could be shared by multiple JVMs, the class does not support such sharing.

Methods from VTPhysicalMemory should be overridden only by methods that use super.

See Section MemoryArea

See Section ScopedMemory

See Section VTMemory

See Section LTMemory

See Section LTPhysicalMemory

See Section ImmortalPhysicalMemory

See Section RealtimeThread

See Section NoHeapRealtimeThread

Deprecated since RTSJ version since RTSJ 2.0

Inheritance

java.lang.Object javax.realtime.MemoryArea javax.realtime.ScopedMemory javax.realtime.VTPhysicalMemory

15.3.3.11.1 Constructors

 $^{^{151}}$ Section 11.4.2.5

VTPhysicalMemory(Object, long)

Create an instance of VTPhysicalMemory with the given parameters. See Section PhysicalMemoryManager

Signature

```
public
```

VTPhysicalMemory(Object type, long size)

Parameters

type An instance of Object representing the type of memory required (e.g., dma, shared) - used to define the base address and control the mapping. When the required memory has more than one attribute, type may be an array of objects. When type is null or a reference to an array with no entries, any type of memory is acceptable. Note that type values are compared by reference (==), not by value (equals).

size The size of the area in bytes.

Throws

SecurityException when the application doesn't have permissions to access physical memory or the given range of memory.

SizeOutOfBoundsException when the implementation detects that size extends beyond physically addressable memory.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryTypeFilter¹⁵² has been registered with the PhysicalMemoryManager¹⁵³.

MemoryTypeConflictException when the specified base does not point to memory that matches the requested type, or when type specifies incompatible memory attributes.

IllegalArqumentException when size is less than zero.

VTPhysicalMemory(Object, long, long)

¹⁵²Section 15.3.1.1 ¹⁵³Section 15.3.3.5 Create an instance of VTPhysicalMemory with the given parameters. See Section PhysicalMemoryManager

Signature

```
public
```

VTPhysicalMemory(Object type, long base, long size)

type An instance of Object representing the type of memory required (e.g., dma, shared) - used to define the base address and control the mapping. When the required memory has more than one attribute, type may be an array of objects. When type is null or a reference to an array with no entries, any type of memory is acceptable. Note that type values are compared by reference (==), not by value (equals).

base The physical memory address of the area.

size The size of the area in bytes.

Throws

SecurityException when the application doesn't have permissions to access physical memory or the given range of memory.

SizeOutOfBoundsException when the implementation detects that size extends beyond physically addressable memory.

OffsetOutOfBoundsException when the base address is invalid.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryTypeFilter¹⁵⁴ has been registered with the PhysicalMemoryManager¹⁵⁵.

Memory Type Conflict Exception when the specified base does not point to memory that matches the requested type, or when type specifies incompatible memory attributes.

MemoryInUseException when the specified memory is already in use.

VTPhysicalMemory(Object, SizeEstimator)

Create an instance of VTPhysicalMemory with the given parameters.

See Section PhysicalMemoryManager

 $^{^{154}}$ Section 15.3.1.1

 $^{^{155}\}mathrm{Section}\ 15.3.3.5$

Signature

public

VTPhysicalMemory(Object type, SizeEstimator size)

Parameters

type An instance of Object representing the type of memory required (e.g., dma, shared) - used to define the base address and control the mapping. When the required memory has more than one attribute, type may be an array of objects. When type is null or a reference to an array with no entries, any type of memory is acceptable. Note that type values are compared by reference (==), not by value (equals).

size A size estimator for this area.

Throws

SecurityException when the application doesn't have permissions to access physical memory or the given range of memory.

SizeOutOfBoundsException when the implementation detects that the size estimate from size extends beyond physically addressable memory.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryTypeFilter¹⁵⁶ has been registered with the PhysicalMemoryManager¹⁵⁷.

MemoryTypeConflictException when the specified base does not point to memory that matches the requested type, or when type specifies incompatible memory attributes.

IllegalArgumentException when size is null, or size.getEstimate() is negative.

VTPhysicalMemory(Object, long, SizeEstimator)

Create an instance of VTPhysicalMemory with the given parameters. See Section PhysicalMemoryManager

Signature

¹⁵⁶Section 15.3.1.1 ¹⁵⁷Section 15.3.3.5

public

VTPhysicalMemory(Object type, long base, SizeEstimator size)

Parameters

type An instance of Object representing the type of memory required (e.g., dma, shared) - used to define the base address and control the mapping. When the required memory has more than one attribute, type may be an array of objects. When type is null or a reference to an array with no entries, any type of memory is acceptable. Note that type values are compared by reference (==), not by value (equals).

base The physical memory address of the area.

size A size estimator for this memory area.

Throws

SecurityException when the application doesn't have permissions to access physical memory or the given range of memory.

SizeOutOfBoundsException when the implementation detects that the size estimate from size extends beyond physically addressable memory.

OffsetOutOfBoundsException when the base address is invalid.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryTypeFilter¹⁵⁸ has been registered with the PhysicalMemoryManager¹⁵⁹.

Memory Type Conflict Exception when the specified base does not point to memory that matches the requested type, or when type specifies incompatible memory attributes.

MemoryInUseException when the specified memory is already in use.

IllegalArgumentException when size is null, or size.getEstimate() is negative.

VTPhysicalMemory(Object, long, Runnable)

Create an instance of VTPhysicalMemory with the given parameters. See Section PhysicalMemoryManager

Signature

public

 $^{^{158}}$ Section 15.3.1.1 159 Section 15.3.3.5

VTPhysicalMemory(Object type, long size, Runnable logic)

type An instance of Object representing the type of memory required (e.g., dma, shared) - used to define the base address and control the mapping. When the required memory has more than one attribute, type may be an array of objects. When type is null or a reference to an array with no entries, any type of memory is acceptable. Note that type values are compared by reference (==), not by value (equals).

size The size of the area in bytes.

logic The run() method of this object will be called whenever MemoryArea.enter() 160 is called. When logic is null, logic must be supplied when the memory area is entered.

Throws

SecurityException when the application doesn't have permissions to access physical memory or the given range of memory.

SizeOutOfBoundsException when the implementation detects that size extends beyond physically addressable memory.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryTypeFilter¹⁶¹ has been registered with the PhysicalMemoryManager¹⁶².

MemoryTypeConflictException when the specified base does not point to memory that matches the requested type, or when type specifies incompatible memory attributes.

IllegalAssignmentError when storing logic in this would violate the assignment rules.

VTPhysicalMemory(Object, long, long, Runnable)

Create an instance of VTPhysicalMemory with the given parameters. See Section PhysicalMemoryManager

Signature

public

¹⁶⁰Section 11.4.2.3.2 ¹⁶¹Section 15.3.1.1

 162 Section 15.3.3.5

VTPhysicalMemory(Object type, long base, long size, Runnable logic)

Parameters

type An instance of Object representing the type of memory required (e.g., dma, shared) - used to define the base address and control the mapping. When the required memory has more than one attribute, type may be an array of objects. When type is null or a reference to an array with no entries, any type of memory is acceptable. Note that type values are compared by reference (==), not by value (equals).

base The physical memory address of the area.

size The size of the area in bytes.

logic The run() method of this object will be called whenever MemoryArea.enter() ¹⁶³ is called. When logic is null, logic must be supplied when the memory area is entered.

Throws

SizeOutOfBoundsException when the implementation detects that size extends beyond physically addressable memory.

SecurityException when the application doesn't have permissions to access physical memory or the given range of memory.

OffsetOutOfBoundsException when the base address is invalid.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryTypeFilter¹⁶⁴ has been registered with the PhysicalMemoryManager¹⁶⁵.

Memory Type Conflict Exception when the specified base does not point to memory that matches the requested type, or when type specifies incompatible memory attributes.

MemoryInUseException when the specified memory is already in use.

IllegalAssignmentError when storing logic in this would violate the assignment rules.

VTPhysicalMemory(Object, SizeEstimator, Runnable)

Create an instance of VTPhysicalMemory with the given parameters. See Section PhysicalMemoryManager

 165 Section 15.3.3.5

¹⁶³Section 11.4.2.3.2

 $^{^{164}}$ Section 15.3.1.1

Signature

public

VTPhysicalMemory(Object type, SizeEstimator size, Runnable logic)

type An instance of Object representing the type of memory required (e.g., dma, shared) - used to define the base address and control the mapping. When the required memory has more than one attribute, type may be an array of objects. When type is null or a reference to an array with no entries, any type of memory is acceptable. Note that type values are compared by reference (==), not by value (equals).

size A size estimator for this area.

logic The run() method of this object will be called whenever MemoryArea.enter() ¹⁶⁶ is called. When logic is null, logic must be supplied when the memory area is entered.

Throws

SecurityException when the application doesn't have permissions to access physical memory or the given range of memory.

SizeOutOfBoundsException when the implementation detects that the size estimate from size extends beyond physically addressable memory.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryTypeFilter¹⁶⁷ has been registered with the PhysicalMemoryManager¹⁶⁸.

MemoryTypeConflictException when the specified base does not point to memory that matches the requested type, or when type specifies incompatible memory attributes.

IllegalArgumentException when size is null, or size.getEstimate() is negative.

IllegalAssignmentError when storing logic in this would violate the assignment rules.

VTPhysicalMemory(Object, long, SizeEstimator, Runnable)

Create an instance of VTPhysicalMemory with the given parameters.

¹⁶⁶Section 11.4.2.3.2

 $^{^{167}}$ Section 15.3.1.1

¹⁶⁸Section 15.3.3.5

See Section PhysicalMemoryManager

Signature

public

VTPhysicalMemory(Object type, long base, SizeEstimator size, Runnable logic)

Parameters

type An instance of Object representing the type of memory required (e.g., dma, shared) - used to define the base address and control the mapping. When the required memory has more than one attribute, type may be an array of objects. When type is null or a reference to an array with no entries, any type of memory is acceptable. Note that type values are compared by reference (==), not by value (equals).

base The physical memory address of the area.

size A size estimator for this memory area.

logic The run() method of this object will be called whenever MemoryArea.enter() 169 is called. When logic is null, logic must be supplied when the memory area is entered.

Throws

SecurityException when the application doesn't have permissions to access physical memory or the given range of memory.

SizeOutOfBoundsException when the implementation detects that the size estimate from size extends beyond physically addressable memory.

OffsetOutOfBoundsException when the base address is invalid.

UnsupportedPhysicalMemoryException when the underlying hardware does not support the given type, or when no matching PhysicalMemoryTypeFilter¹⁷⁰ has been registered with the PhysicalMemoryManager¹⁷¹.

Memory Type Conflict Exception when the specified base does not point to memory that matches the requested type, or when type specifies incompatible memory attributes.

MemoryInUseException when the specified memory is already in use.

IllegalArgumentException when size is null, or size.getEstimate() is negative

IllegalAssignmentError when storing logic in this would violate the assignment rules.

 $^{^{169}}$ Section 11.4.2.3.2

 $^{^{170}}$ Section 15.3.1.1

 $^{^{171}}$ Section 15.3.3.5

15.3.3.11.2 Methods

toString

Creates a string representing this object. The string is of the form (VTPhysicalMemory) Scoped memory # num

where num is a number that uniquely identifies this VTPhysicalMemory memory area.

```
Signature

public
 java.lang.String toString()

Returns

A string representing the value of this.
```

15.3.3.12 WaitFreeDequeue

A WaitFreeDequeue encapsulates a WaitFreeWriteQueue and a WaitFreeRead-Queue. Each method on a WaitFreeDequeue corresponds to an equivalent operation on the underlying WaitFreeWriteQueue or WaitFreeReadQueue.

Incompatibility with V1.0: Three exceptions previously thrown by the constructor have been deleted from the throws clause. These are:

- java.lang.IllegalAccessException,
- java.lang.ClassNotFoundException, and
- java.lang.InstantiationException.

Including these exceptions on the throws clause was an error. Their deletion may cause compile-time errors in code using the previous constructor. The repair is to remove the exceptions from the catch clause around the constructor invocation.

WaitFreeDequeue is one of the classes allowing NoHeapRealtimeThreads and regular Java threads to synchronize on an object without the risk of a NoHeapRealtimeThread incurring Garbage Collector latency due to priority inversion avoidance management.

Deprecated since RTSJ version as of RTSJ 1.0.1

Inheritance

794 15.4 Rationale

java.lang.Object javax.realtime.WaitFreeDequeue

15.4 Rationale

These are interface that have been shown to be less the ideal. They have been replaced by classes that better fulfill the requirements. Compatibility can be provided by implementations that use existing facilities so there is not reason to continue requiring their inclusion new implementations.

Chapter 16

Conformance, Compliance, and Portability

16.1 Minimum Implementations

The flexibility of the RTSJ indicates that implementations may provide different semantics for scheduling, synchronization, and garbage collection. This section defines what minimum semantics for these areas and other semantics and APIs required of all implementations of the RTSJ. Other than what is described in the optional modules or explicitly noted as optionally required, the RTSJ does not allow any subsetting of the APIs in the <code>javax.realtime</code> package; however, some of the classes are specific to certain well-known scheduling or synchronization algorithms and may have no underlying support in a minimum implementation of the RTSJ. The RTSJ provides these classes as standard parent classes for implementations supporting such algorithms.

16.2 Modules

As described in Section 3.2, the RTSJ now has modules. Every implementation must implement the Core module. If any of the other modules is provided, it must be provided in full. None of the classes of an unimplemented module should be present.

16.3 Optionally Required Components

The RTSJ does not, in general, support the concept of optional components of the specification. Optional components would further complicate the already difficult task of writing WORA (Write Once Run Anywhere) software components for real-

time systems. However, understanding the difficulty of providing implementations of mechanisms for which there is no underlying support, the RTSJ does provide for a few exceptions. Any components that are considered optional will be listed as such in the class definitions.

The most notable optional component of the specification is the POSIXSignal-Handler. A conformant implementation which implements the Device module must support POSIX signals if and only if the underlying system supports them.

16.3.1 Deployment Implementation

The minimum scheduling semantics that must be supported in all implementations of the RTSJ are fixed-priority preemptive scheduling and at least 28 unique priority levels. By fixed-priority we mean that the system does not change the priority of any RealtimeThread or NoHeapRealtimeThread except, temporarily, for priority inversion avoidance. Note, however, that application code may change such priorities. What the RTSJ precludes by this statement is scheduling algorithms that change thread priorities according to policies for optimizing throughput (such as increasing the priority of threads that have been receiving few processor cycles because of higher priority threads (aging)). The 28 unique priority levels are required to be unique to preclude implementations from using fewer priority levels of underlying systems to implement the required 28 by simplistic algorithms (such as lumping four RTSJ priorities into seven buckets for an underlying system that only supports seven priority levels). It is sufficient for systems with fewer than 28 priority levels to use more sophisticated algorithms to implement the required 28 unique levels as long as RealtimeThreads and NoHeapRealtimeThreads behave as though there were at least 28 unique levels. (e.g. if there were 28 RealtimeThreads $(t_1,...,t_{28})$ with priorities $(p_1, ..., p_{28})$, respectively, where the value of p_1 was the highest priority and the value of p_2 the next highest priority, etc., then for all executions of threads t_1 through t_{28} thread t_1 would always execute in preference to threads $t_2, ..., t_{28}$ and thread t_2 would always execute in preference to threads $t_3, ..., t_{28}$, etc.)

The minimum synchronization semantics that must be supported in all deployment implementations of the RTSJ are detailed in the above section on synchronization and repeated here.

All deployment implementations of the RTSJ must provide an implementation of the synchronized primitive with default behavior that ensures that there is no unbounded priority inversion. Furthermore, this must apply to code if it is run within the implementation as well as to realtime threads. The priority inheritance protocol must be implemented by default.

All threads waiting to acquire a resource must be queued in priority order. This applies to the processor as well as to synchronized blocks. If threads with the same exact priority are possible under the active scheduling policy, threads with the same

priority are queued in FIFO order. (Note that these requirements apply only to the required base scheduling policy and hence use the specific term "priority"). In particular:

- Threads waiting to enter synchronized blocks are granted access to the synchronized block in priority order.
- A blocked thread that becomes ready to run is given access to the processor in priority order.
- A thread whose execution eligibility is explicitly set by itself or another thread is given access to the processor in priority order.
- A thread that performs a yield() will be given access to the processor after waiting threads of the same priority.
- However, threads that are preempted in favor of a thread with higher priority may be given access to the processor at any time as determined by a particular implementation. The implementation is required to provide documentation stating exactly the algorithm used for granting such access.

The RTSJ does not require any particular garbage collection algorithm; however, every deployment implementation must either support memory areas or have a realtime garbage collection. In the later case, the realtime limitations must be documented. All implementations of the RTSJ must support the class GarbageCollector and implement all of its methods.

16.4 Simulation Implementation

An implementation that chooses not to provide realtime guarentees, is termed a simulation implementation. Such an implementation does not need to provide the realtime characteristic described above, but does need to at least provide all the APIs of the core module. A simulation implementation can be a production system, but not for realtime applications. This enables a conventional JVM to make the base APIs available to a wider audience without changing its performance characteristics.

16.5 Documentation Requirements

In order to properly engineer a realtime system, an understanding of the cost associated with any arbitrary code segment is required. This is especially important for operations that are performed by the runtime system, largely hidden from the programmer. (An example of this is the maximum expected latency before the garbage collector can be interrupted.)

The RTSJ does not require specific performance or latency numbers to be matched. Rather, to be conformant to this specification, an implementation must provide doc-

umentation regarding the expected behavior of particular mechanisms. The mechanisms requiring such documentation, and the specific data to be provided, will be detailed in the class and method definitions.

Appendix A

Bibliography

- [1] Portable Operating System Interface (POSIX®) Part 1: System Application Program Interface, International Standard ISO/IEC 9945-1, 1996 (E) IEEE Std 1003.1, 1996 edition ed. The Institute of Electrical and Electronics Engineers, Inc., 1996.
- [2] Barr, M. Memory types. Embedded Systems Programming (2001), 103–104.
- [3] Burns, A., and Wellings, A. J. Real-Time Systems and Programming Languages:, 4th ed. Addison Wesley, 2010.
- [4] Dos Santos, O. M., and Wellings, A. Cost enforcement in the real-time specification for java. *Real-Time Syst.* 37, 2 (Nov. 2007), 139–179.
- [5] GOSLING, J., JOY, B., STEELE, G., BRACHA, G., AND BUCKLEY, A. The Java Language Specification Java SE 8 Edition. Oracle, 2014.
- [6] LINDHOLM, T., YELLIN, F., BRACHA, G., AND BUCKLEY, A. The Java Virtual Machine Specification Java SE 8 Edition. Oracle, 2014.
- [7] Regehr, J. Safe and structured use of interrupts in real-time and embedded software. In *Handbook of Real-Time and Embedded Systems*, I. Lee, J. Y.-T. Leug, and S. H. Son, Eds. Chapman and Hall/CRC, 2007, pp. 16–1–16–12.

800 A.0